

VSI OpenVMS System Analysis Tools Manual

Document Number: DO-DSYATM-01A

Publication Date: April 2024

Operating System and Version: VSI OpenVMS IA-64 Version 8.4-1H1 or higher
VSI OpenVMS Alpha Version 8.4-2L1 or higher

VSI OpenVMS System Analysis Tools Manual



VMS Software

Copyright © 2024 VMS Software, Inc. (VSI), Boston, Massachusetts, USA

Legal Notice

Confidential computer software. Valid license from VSI required for possession, use or copying. Consistent with FAR 12.211 and 12.212, Commercial Computer Software, Computer Software Documentation, and Technical Data for Commercial Items are licensed to the U.S. Government under vendor's standard commercial license.

The information contained herein is subject to change without notice. The only warranties for VSI products and services are set forth in the express warranty statements accompanying such products and services. Nothing herein should be construed as constituting an additional warranty. VSI shall not be liable for technical or editorial errors or omissions contained herein.

HPE, HPE Integrity, HPE Alpha, and HPE Proliant are trademarks or registered trademarks of Hewlett Packard Enterprise.

Intel, Itanium and IA-64 are trademarks or registered trademarks of Intel Corporation or its subsidiaries in the United States and other countries.

Preface	xi
1. About VSI	xi
2. About This Manual	xi
3. Document Structure	xi
4. Related Documents	xi
5. VSI Encourages Your Comments	xii
6. OpenVMS Documentation	xii
7. Typographical Conventions	xii
Chapter 1. Overview of System Analysis Tools	1
1.1. System Dump Analyzer (SDA)	2
1.2. System Code Debugger (SCD)	2
1.3. System Dump Debugger (SDD)	3
1.4. Watchpoint Utility (Alpha Only)	3
1.5. System Service Logging	3
1.6. Delta/XDelta Debugger	3
1.7. Dump-Off-System-Disk (DOSD)	4
1.8. On-Chip Logic Analyzer (OCLA)	4

Part I. OpenVMS System Dump Analyzer (SDA)

Chapter 2. SDA Description	7
2.1. Capabilities of SDA	7
2.2. System Management and SDA	8
2.2.1. Writing System Dumps	8
2.2.1.1. Dump File Style	9
2.2.1.2. Comparison of Full and Selective Dumps	10
2.2.1.3. Controlling the Size of Page Files and Dump Files	11
2.2.1.4. Writing to the System Dump File	11
2.2.1.5. Writing to a Dump File off the System Disk	12
2.2.1.6. Writing to the System Page File	12
2.2.2. Saving System Dumps	13
2.2.3. Partial Dump Copies	14
2.2.3.1. Example - Use of Partial Dump Copies	15
2.2.3.2. Additional notes on Partial Dump Copies	16
2.2.4. Invoking SDA When Rebooting the System	16
2.3. Analyzing a System Dump	18
2.3.1. Requirements	18
2.3.2. Invoking SDA	18
2.3.3. Mapping the Contents of the Dump File	18
2.3.4. Building the SDA Symbol Table	19
2.3.5. Executing the SDA Initialization File (SDA\$INIT)	19
2.4. Analyzing a Running System	20
2.5. SDA Context	21
2.6. SDA Command Format	23
2.6.1. Using Expressions and Operators	23
2.6.1.1. Radix Operators	23
2.6.1.2. Arithmetic and Logical Operators	24
2.6.1.3. Precedence Operators	25
2.6.1.4. SDA Symbols	25
2.6.2. SDA Display Mode	31
2.7. Investigating System Failures	31

2.7.1. Procedure for Analyzing System Failures	31
2.7.2. Fatal Bugcheck Conditions	32
2.7.2.1. Alpha Mechanism Array	33
2.7.2.2. Integrity server Mechanism Array	34
2.7.2.3. Signal Array	37
2.7.2.4. 64-Bit Signal Array	38
2.7.2.5. Alpha Exception Stack Frame	38
2.7.2.6. Integrity server Exception Stack Frame	39
2.7.2.7. SSRVEXCEPT Example	42
2.7.2.8. Illegal Page Faults	48
2.8. Page Protections and Access Rights	48
2.9. Inducing a System Failure	49
2.9.1. Meeting Crash Dump Requirements	50
2.9.2. Procedure for Causing a System Failure	50
Chapter 3. ANALYZE Usage	53
3.1. ANALYZE	53
3.2. /COLLECTION	56
3.3. /CRASH_DUMP	56
3.4. /LOG	57
3.5. /OVERRIDE	58
3.6. /RELEASE	59
3.7. /SHADOW_MEMBER	60
3.8. /SSLOG	62
3.9. /SYMBOL	62
3.10. /SYSTEM	63
Chapter 4. SDA Commands	65
4.1. @(Execute Command)	65
4.2. ATTACH	65
4.3. COLLECT	66
4.4. COPY	67
4.5. DEFINE	70
4.6. DEFINE/KEY	72
4.7. DUMP	75
4.8. EVALUATE	78
4.9. EXAMINE	81
4.10. EXIT	86
4.11. FORMAT	87
4.12. HELP	90
4.13. MAP	92
4.14. MODIFY DUMP	94
4.15. READ	96
4.16. REPEAT	103
4.17. SEARCH	106
4.18. SET CPU	108
4.19. SET ERASE_SCREEN	110
4.20. SET FETCH	110
4.21. SET LOG	112
4.22. SET OUTPUT	113
4.23. SET PROCESS	114
4.24. SET RMS	117
4.25. SET SIGN_EXTEND	120

4.26. SET SYMBOLIZE	121
4.27. SHOW ACPI (Integrity servers only)	121
4.28. SHOW ADDRESS	124
4.29. SHOW BUGCHECK	125
4.30. SHOW CALL_FRAME	126
4.31. SHOW CBB	130
4.32. SHOW CEB	130
4.33. SHOW CLASS	132
4.34. SHOW CLUSTER	133
4.35. SHOW CONNECTIONS	139
4.36. SHOW CPU	141
4.37. SHOW CRASH	145
4.38. SHOW DEVICE	155
4.39. SHOW DUMP	159
4.40. SHOW EFI (Integrity servers Only)	164
4.41. SHOW EXCEPTION_FRAME	166
4.42. SHOW EXECUTIVE	167
4.43. SHOW GALAXY	170
4.44. SHOW GCT	171
4.45. SHOW GLOBAL_SECTION_TABLE	174
4.46. SHOW GLOCK	176
4.47. SHOW GMDB	180
4.48. SHOW GSD	182
4.49. SHOW GST	184
4.50. SHOW HEADER	184
4.51. SHOW IMAGE	185
4.52. SHOW KFE	187
4.53. SHOW KNOWN_FILE_ENTRY	189
4.54. SHOW LAN	189
4.55. SHOW LOCKS	202
4.56. SHOW MACHINE_CHECK	207
4.57. SHOW MEMORY	210
4.58. SHOW PAGE_TABLE	211
4.59. SHOW PARAMETER	218
4.60. SHOW PFN_DATA	221
4.61. SHOW POOL	227
4.62. SHOW PORTS	234
4.63. SHOW PROCESS	238
4.64. SHOW RAD	258
4.65. SHOW RESOURCES	259
4.66. SHOW RMD	266
4.67. SHOW RMS	268
4.68. SHOW RSPID	269
4.69. SHOW SHM_CPP	270
4.70. SHOW SHM_REG	272
4.71. SHOW SPINLOCKS	275
4.72. SHOW STACK	281
4.73. SHOW SUMMARY	287
4.74. SHOW SWIS (Integrity servers Only)	291
4.75. SHOW SYMBOL	293
4.76. SHOW TQE	294
4.77. SHOW TQEIDX	297

4.78. SHOW UNWIND (Integrity servers Only)	298
4.79. SHOW VHPT (Integrity servers Only)	300
4.80. SHOW WORKING_SET_LIST	303
4.81. SHOW WSL	304
4.82. SPAWN	304
4.83. UNDEFINE	306
4.84. VALIDATE PFN_LIST	306
4.85. VALIDATE POOL	307
4.86. VALIDATE PROCESS	308
4.87. VALIDATE QUEUE	310
4.88. VALIDATE SHM_CPP	312
4.89. VALIDATE TQEIDX	314
4.90. WAIT	314
Chapter 5. SDA CLUE Extension	317
5.1. Overview of SDA CLUE Extension	317
5.2. Displaying Data with CLUE	318
5.3. Using CLUE with DOSD	318
5.4. SDA CLUE Extension Commands	318
5.4.1. CLUE CALL_FRAME (Alpha Only)	318
5.4.2. CLUE CLEANUP	321
5.4.3. CLUE CONFIG	322
5.4.4. CLUE CRASH	322
5.4.5. CLUE ERRLOG	325
5.4.6. CLUE FRU	326
5.4.7. CLUE HISTORY	326
5.4.8. CLUE MCHK	327
5.4.9. CLUE MEMORY	328
5.4.10. CLUE PROCESS	341
5.4.11. CLUE REGISTER	342
5.4.12. CLUE SCSI	344
5.4.13. CLUE SG	347
5.4.14. CLUE STACK	347
5.4.15. CLUE SYSTEM	351
5.4.16. CLUE VCC	352
5.4.17. CLUE XQP	354
Chapter 6. SDA FLT Extension	359
6.1. FLT Commands	359
6.1.1. FLT	359
6.1.2. FLT LOAD	359
6.1.3. FLT SHOW TRACE	360
6.1.4. FLT START TRACE	360
6.1.5. FLT STOP TRACE	361
6.1.6.	361
Chapter 7. SDA OCLA Extension (Alpha Only)	365
7.1. Overview of OCLA	365
7.2. SDA OCLA Commands	365
7.2.1. OCLA DISABLE	366
7.2.2. OCLA DUMP	366
7.2.3. OCLA ENABLE	367
7.2.4. OCLA HELP	367
7.2.5. OCLA LOAD	367

7.2.6. OCLA SET REGISTER	368
7.2.7. OCLA SHOW REGISTER	368
7.2.8. OCLA SHOW STATUS	369
7.2.9. OCLA SHOW TRACE	370
7.2.10. OCLA START	371
7.2.11. OCLA STOP	372
7.2.12. OCLA UNLOAD	372
Chapter 8. SDA SPL Extension	375
8.1. Overview of the SDA Spinlock Tracing Utility	375
8.2. How to Use the SDA Spinlock Tracing Utility	375
8.3. Example Command Procedure for Collection of Spinlock Statistics	376
8.4. SDA Spinlock Tracing Commands	377
8.4.1. SPL	377
8.4.2. SPL ANALYZE	377
8.4.3. SPL LOAD	380
8.4.4. SPL SHOW COLLECT	381
8.4.5. SPL SHOW TRACE	381
8.4.6. SPL START COLLECT	386
8.4.7. SPL START TRACE	387
8.4.8. SPL STOP COLLECT	389
8.4.9. SPL STOP TRACE	390
8.4.10. SPL UNLOAD	390
Chapter 9. SDA XFC Extension	393
9.1. SDA XFC Commands	393
9.1.1. XFC SET TRACE	393
9.2. XFC SHOW CONTEXT	394
9.3. XFC SHOW EXTENT	395
9.4. XFC SHOW FILE	396
9.5. XFC SHOW HISTORY	400
9.6. XFC SHOW IRP	400
9.7. XFC SHOW MEMORY	401
9.8. XFC SHOW SUMMARY	404
9.9. XFC SHOW TABLES	407
9.10. XFC SHOW TRACE	409
9.11. XFC SHOW VOLUME	410
Chapter 10. SDA Extensions and Callable Routines	413
10.1. Introduction	413
10.2. Description	413
10.2.1. Compiling and Linking an SDA Extension	414
10.2.2. Invoking an SDA Extension	414
10.2.3. Contents of an SDA Extension	414
10.3. Debugging an Extension	417
10.4. Callable Routines Overview	418
10.5. Routines	419
10.5.1. SDA\$ADD_SYMBOL	419
10.5.2. SDA\$ALLOCATE	420
10.5.3. SDA\$CBB_BOOLEAN_OPER	421
10.5.4. SDA\$CBB_CLEAR_BIT	423
10.5.5. SDA\$CBB_COPY	423
10.5.6. SDA\$CBB_FFC	424
10.5.7. SDA\$CBB_FFS	425

10.5.8. SDA\$CBB_INIT	426
10.5.9. SDA\$CBB_SET_BIT	427
10.5.10. SDA\$CBB_TEST_BIT	428
10.5.11. SDA\$DBG_IMAGE_INFO	429
10.5.12. SDA\$DEALLOCATE	430
10.5.13. SDA\$DELETE_PREFIX	431
10.5.14. SDA\$DISPLAY_HELP	431
10.5.15. SDA\$ENSURE	433
10.5.16. SDA\$FAO	433
10.5.17. SDA\$FID_TO_NAME	435
10.5.18. SDA\$FORMAT	436
10.5.19. SDA\$FORMAT_HEADING	438
10.5.20. SDA\$GET_ADDRESS	439
10.5.21. SDA\$GET_BLOCK_NAME	439
10.5.22. SDA\$GET_BUGCHECK_MSG	441
10.5.23. SDA\$GET_CURRENT_CPU	442
10.5.24. SDA\$GET_CURRENT_PCB	443
10.5.25. SDA\$GET_DEVICE_NAME	443
10.5.26. SDA\$GET_FLAGS	445
10.5.27. SDA\$GET_HEADER	446
10.5.28. SDA\$GET_HW_NAME	448
10.5.29. SDA\$GET_IMAGE_OFFSET	449
10.5.30. SDA\$GET_INPUT	451
10.5.31. SDA\$GET_LINE_COUNT	453
10.5.32. SDA\$GETMEM	453
10.5.33. SDA\$INSTRUCTION_DECODE	455
10.5.34. SDA\$NEW_PAGE	457
10.5.35. SDA\$PARSE_COMMAND	458
10.5.36. SDA\$PRINT	459
10.5.37. SDA\$READ_SYMFILE	460
10.5.38. SDA\$REQMEM	462
10.5.39. SDA\$SET_ADDRESS	464
10.5.40. SDA\$SET_CPU	464
10.5.41. SDA\$SET_HEADING_ROUTINE	465
10.5.42. SDA\$SET_LINE_COUNT	466
10.5.43. SDA\$SET_PROCESS	467
10.5.44. SDA\$SKIP_LINES	468
10.5.45. SDA\$SYMBOL_VALUE	469
10.5.46. SDA\$SYMBOLIZE	470
10.5.47. SDA\$TRYMEM	471
10.5.48. SDA\$TYPE	472
10.5.49. SDA\$VALIDATE_QUEUE	473

Part II. OpenVMS System Code Debugger and System Dump Debugger

Chapter 11. OpenVMS System Code Debugger	477
11.1. User-Interface Options	477
11.2. Building a System Image to Be Debugged	478
11.3. Setting Up the Target System for Connections	479
11.3.1. Making Connections Between the Target Kernel and the System Code Debugger	483

11.3.2. Interactions Between XDELTA and the Target Kernel/System Code Debugger	484
11.3.3. Interactions between the Target Kernel, the System Code Debugger, and other system components	485
11.4. Setting Up the Host System	485
11.5. Starting the System Code Debugger	486
11.6. Summary of System Code Debugger Commands	486
11.7. Using System Dump Analyzer Commands	487
11.8. System Code Debugger Network Information	487
11.9. Troubleshooting Checklist	488
11.10. Troubleshooting Network Failures	488
11.11. Access to Symbols in OpenVMS Executive Images	489
11.11.1. Overview of How the OpenVMS Debugger Maintains Symbols	489
11.11.2. Overview of OpenVMS Executive Image Symbols	490
11.11.3. Possible Problems You May Encounter	490
11.12. Sample System Code Debugging Session	491
Chapter 12. OpenVMS System Dump Debugger	507
12.1. User-Interface Options	507
12.2. Preparing a System Dump to Be Analyzed	508
12.3. Setting Up the Test System	508
12.4. Setting Up the Build System	509
12.5. Starting the System Dump Debugger	509
12.6. Summary of System Dump Debugger Commands	510
12.7. Using System Dump Analyzer Commands	510
12.8. Limitations of the System Dump Debugger	511
12.9. Access to Symbols in OpenVMS Executive Images	511
12.10. Sample System Dump Debugging Session	512
Part III. OpenVMS Alpha Watchpoint Utility	
Chapter 13. Watchpoint Utility (Alpha Only)	519
13.1. Introduction	519
13.2. Initializing the Watchpoint Utility	520
13.3. Creating and Deleting Watchpoints	520
13.3.1. Using the \$QIO Interface	521
13.3.2. Invoking WPDRIIVER Entry Points from System Routines	523
13.4. Data Structures	524
13.4.1. Watchpoint Restore Entry (WPRE)	524
13.4.2. Watchpoint Control Blocks (WPCB)	524
13.4.3. Trace Table Entries (WPTTEs)	525
13.5. Analyzing Watchpoint Results	526
13.6. Watchpoint Protection Overview	527
13.7. Restrictions	528
Part IV. OpenVMS System Service Logging Utility	
Chapter 14. System Service Logging	533
14.1. Overview	533
14.2. Enabling Logging	534
14.3. Disabling Logging	534
14.4. Displaying Logged Information	534

Preface

1. About VSI

VMS Software, Inc. (VSI) is an independent software company licensed by Hewlett Packard Enterprise to develop and support the OpenVMS operating system.

2. About This Manual

The *VSI OpenVMS System Analysis Tools Manual* is intended primarily for the system programmer or analyst who must investigate the causes of system failures and debug kernel-mode code, such as a device driver.

This manual also includes system management information for maintaining the system resources necessary to capture and store system crash dumps, including the use of dump-off-system-disk (DOSD). To help determine the cause of a hung process or improve system performance, consult this manual for instructions on using the appropriate system analysis tool to analyze your system.

3. Document Structure

This *VSI OpenVMS System Analysis Tools Manual* contains an introductory chapter and four parts.

Chapter 1 presents an overview of the system analysis tools, which are:

- System Dump Analyzer Utility including Crash Log Utility Extractor, several other extensions, and descriptions of the callable routines available to user-written extensions
- System Code and System Dump debuggers
- Alpha Watchpoint Utility
- System Service Logging Utility
- Delta/XDelta Debugger
- Dump-Off-System-Disk

Part I describes the System Dump Analyzer (SDA), its use and commands, the SDA Crash Log Utility Extractor (CLUE), several other SDA extensions, and the SDA callable routines.

Part II describes the System Code Debugger (SCD) and the System Dump Debugger (SDD).

Part III describes the Alpha Watchpoint Utility (WP).

Part IV describes the System Service Logging Utility (SSLOG).

4. Related Documents

For additional information, refer to the following documents:

- *VSI OpenVMS Version 8.4 Upgrade and Installation Manual*

- *VSI OpenVMS Calling Standard*
- *VSI OpenVMS System Manager's Manual, Volume 1: Essentials*
- *VSI OpenVMS System Manager's Manual, Volume 2: Tuning, Monitoring, and Complex Systems*
- *VSI OpenVMS Programming Concepts Manual, Volume II*
- *Writing OpenVMS Alpha Device Drivers in C*
- *OpenVMS AXP Internals and Data Structures*
- *Alpha Architecture Reference Manual*
- *Intel IA-64 Architecture Software Developer's Manual*
- *MACRO-64 Assembler for OpenVMS AXP Systems Reference Manual*

5. VSI Encourages Your Comments

You may send comments or suggestions regarding this manual or any VSI document by sending electronic mail to the following Internet address: <docinfo@vmssoftware.com>. Users who have VSI OpenVMS support contracts through VSI can contact <support@vmssoftware.com> for help with this product.

6. OpenVMS Documentation

The full VSI OpenVMS documentation set can be found on the VMS Software Documentation webpage at <https://docs.vmssoftware.com>.

7. Typographical Conventions

The following conventions may be used in this manual:

Convention	Meaning
Ctrl/ <i>x</i>	A sequence such as Ctrl/ <i>x</i> indicates that you must hold down the key labeled Ctrl while you press another key or a pointing device button.
PF1 <i>x</i>	A sequence such as PF1 <i>x</i> indicates that you must first press and release the key labeled PF1 and then press and release another key or a pointing device button.
Return	In examples, a key name enclosed in a box indicates that you press a key on the keyboard. (In text, a key name is not enclosed in a box.)
. . .	A horizontal ellipsis in examples indicates one of the following possibilities: <ul style="list-style-type: none"> • Additional optional arguments in a statement have been omitted. • The preceding item or items can be repeated one or more times. • Additional parameters, values, or other information can be entered.
. . . .	A vertical ellipsis indicates the omission of items from a code example or command format; the items are omitted because they are not important to the topic being discussed.

Convention	Meaning
()	In command format descriptions, parentheses indicate that you must enclose the options in parentheses if you choose more than one.
[]	In command format descriptions, brackets indicate optional choices. You can choose one or more items or no items. Do not type the brackets on the command line. However, you must include the brackets in the syntax for OpenVMS directory specifications and for a substring specification in an assignment statement.
[]	In command format descriptions, vertical bars separate choices within brackets or braces. Within brackets, the choices are options; within braces, at least one choice is required. Do not type the vertical bars on the command line.
{ }	In command format descriptions, braces indicate required choices; you must choose at least one of the items listed. Do not type the braces on the command line.
bold text	This typeface represents the introduction of a new term. It also represents the name of an argument, an attribute, or a reason.
<i>italic text</i>	Italic text indicates important information, complete titles of manuals, or variables. Variables include information that varies in system output (Internal error <i>number</i>), in command lines (/PRODUCER= <i>name</i>), and in command parameters in text (where <i>dd</i> represents the predefined code for the device type).
UPPERCASE TEXT	Uppercase text indicates a command, the name of a routine, the name of a file, or the abbreviation for a system privilege.
Monospace type	Monospace type indicates code examples and interactive screen displays. In the C programming language, monospace type in text identifies the following elements: keywords, the names of independently compiled external functions and files, syntax summaries, and references to variables or identifiers introduced in an example.
-	A hyphen at the end of a command format description, command line, or code line indicates that the command or statement continues on the following line.
numbers	All numbers in text are assumed to be decimal unless otherwise noted. Nondecimal radices—binary, octal, or hexadecimal—are explicitly indicated.

Chapter 1. Overview of System Analysis Tools

This chapter presents an overview of the following system dump analysis tools and features:

- System Dump Analyzer (SDA)
- System Code Debugger (SCD)
- System Dump Debugger (SDD)
- Alpha Watchpoint Utility (WP)
- Delta Debugger
- XDelta Debugger
- Dump-Off-System-Disk (DOSD)
- System Service Logging Utility (SSLOG)
- On-Chip Logic Analyzer (OCLA)

To do the following:	Use this utility:	Described in:
Analyze a running system.	SDA	Chapter 2
Analyze a dump file.	SDA	Chapter 2
Automate the analysis of crash dumps and maintain a fatal-bugcheck history.	CLUE	Chapter 5
Debug nonpagable system code and device drivers running at any IPL.	SCD	Chapter 11
Analyze certain system dumps, display source code, variables or registers in use at the time of a system failure.	SDD	Chapter 12
Maintain a history of modifications made to a specific location in shared memory on an Alpha system.	WP	Chapter 13
Monitor execution of user programs and OpenVMS running at IPL 0.	Delta Debugger	Section 1.6
Debug system code that runs early in booting or when there is no Ethernet adapter dedicated to SCD.	Xdelta Debugger	Section 1.6
Write the system dump file to a device other than the system disk.	DOSD	Section 1.7

Characterize spinlock usage and collect per-CPU spinlock performance data.	SPL	Chapter 8
Display XFC data structures and statistics to help tune the extended file cache.	XFC	Chapter 9
Extend the functionality of SDA.	SDA Extension Callable Routines	Chapter 10
Log system services.	SSLOG	Chapter 14
Determine which instructions have executed in a specific Alpha EV7 CPU.	OCLA	Chapter 7

1.1. System Dump Analyzer (SDA)

The OpenVMS system dump analyzer (SDA) utility enables you to analyze a running system or a system dump after a system failure occurs. With a system failure, the operating system copies the contents of memory to a system dump file or the primary page file. Additionally, it records the hardware context of each processor. With SDA, you can interpret the contents of the dump file, examine the status of each processor at the time of the system failure, and investigate possible causes of failure.

See Part I for more complete information about SDA, SDA CLUE (Crash Log Utility Extractor), SPL (Spinlock Tracing Utility), other SDA extensions, and the SDA Extension routines.

1.2. System Code Debugger (SCD)

The OpenVMS System Code Debugger (SCD) allows you to debug nonpageable system code and device drivers running at any interrupt priority level (IPL). You can use the SCD to perform the following tasks:

- Control the system software's execution---stop at points of interest, resume execution, intercept fatal exceptions, and so on
- Trace the execution path of the system software
- Display the source code where the software is executing, and step by source line
- Monitor exception conditions
- Examine and modify the values of variables
- In some cases, test the effect of modifications without having to edit the source code, recompile, and relink

SCD is a symbolic debugger. You can specify variable names, routine names, and so on, precisely as they appear in your source code.

SCD recognizes the syntax, data typing, operators, expressions, scoping rules, and other constructs of a given language. If your code or driver is written in more than one language, you can change the debugging context from one language to another during a debugging session.

See Part II for complete information about SCD.

1.3. System Dump Debugger (SDD)

The OpenVMS System Dump Debugger allows you to analyze certain system dumps using the commands and semantics of SCD. You can use SDD to perform the following tasks:

- Display the source code where the software was executing at the time of the system failure
- Examine the values of variables and registers at the time of the system failure

SDD is a symbolic debugger. You can specify variable names, routine names, and so on, precisely as they appear in your source code.

SDD recognizes the syntax, data typing, operators, expressions, scoping rules, and other constructs of a given language. If your code or driver is written in more than one language, you can change the debugging context from one language to another during a debugging session.

See Part II for complete information about SCD.

1.4. Watchpoint Utility (Alpha Only)

The OpenVMS Watchpoint utility allows you to maintain a history of modifications that are made to a particular location in shared system space. It sets watchpoints on 32-bit and 64-bit addresses, and watches any system addresses whether in S0, S1, or S2 space.

See Part III for complete information about the Watchpoint utility.

1.5. System Service Logging

To log system services, use the System Service Logging (SSLOG) Utility. For additional information, see Chapter 14.

1.6. Delta/XDelta Debugger

The OpenVMS Delta/XDelta debugger allows you to monitor the execution of user programs and the OpenVMS operating system. The Delta/XDelta debuggers both use the same commands and expressions, but they are different in how they operate. Delta operates as an exception handler in a process context; whereas XDelta is invoked directly from the hardware system control block (SCB) vector in a system context.

You use OpenVMS Delta instead of the OpenVMS symbolic debugger to debug programs that run in privileged processor mode at interrupt priority level (IPL) 0. Because Delta operates in a process context, you can use it to debug user-mode programs or programs that execute at interrupt priority level (IPL) 0 in any processor mode---user, supervisor, executive, and kernel. To run Delta in a processor mode other than user mode, your process must have the privilege that allows Delta to change to that mode: change-mode-to-executive (CMEXEC), or change-mode-to-kernel (CMKRNL) privilege. You cannot use Delta to debug code that executes at an elevated IPL. To debug with Delta, you invoke it from within your process by specifying it as the debugger instead of the symbolic debugger.

You use OpenVMS XDelta instead of the System Code Debugger when debugging system code that runs early in booting or when there is no Ethernet adapter that can be dedicated to SCD. Because XDelta is invoked directly from the hardware system control block (SCB), it can be used to debug programs executing in any processor mode or at any IPL level. To use XDelta, you must have system privileges,

and you must include XDelta when you boot the system. Since XDelta is not process specific, it is not invoked from a process. To debug with XDelta, you must boot the system with a command to include XDelta in memory. XDelta's existence terminates when you reboot the system without XDelta.

On OpenVMS systems, XDelta supports 64-bit addressing. Quadword display mode displays full quadwords of information. The 64-bit address display mode accepts and displays all addresses as 64-bit quantities. XDelta has predefined command strings for displaying the contents of the page frame number (PFN) database.

You can use Delta/XDelta commands to perform the following debugging tasks:

- Open, display, and change the value of a particular location
- Set, clear, and display breakpoints
- Set, display modes in byte, word, longword, or ASCII
- Display instructions
- Execute the program in a single step with the option to step over a subroutine
- Set base registers
- List the names and locations of all loaded modules of the executive
- Map an address to an executive module

See the *VSI OpenVMS Delta/XDelta Debugger Manual* for complete information about using the Delta/XDelta debugging utility.

1.7. Dump-Off-System-Disk (DOSD)

The OpenVMS system allows you to write the system dump file to a device other than the system disk. This is useful in large memory systems and in clusters with common system disks where sufficient disk space, on one disk, is not always available to support your dump file requirements. To perform this activity, you must correctly enable the DUMPSTYLE system parameter to allow the bugcheck code to write the system dump file to an alternative device.

See the *VSI OpenVMS System Manager's Manual, Volume 2: Tuning, Monitoring, and Complex Systems* for complete information about how to write the system dump file to a disk other than the system disk.

1.8. On-Chip Logic Analyzer (OCLA)

The Alpha EV7 On-chip Logic Analyzer utility (OCLA) enables a user to determine which instructions have executed on an Alpha EV7 CPU. One-seventh of the Alpha EV7 cache is set aside as acquisition memory where the virtual addresses of instructions executed by the Alpha EV7 CPU are stored. The acquisition memory can later be analyzed with SDA. For more information on OCLA, see Chapter 7.

Part I. OpenVMS System Dump Analyzer (SDA)

Part I describes the capabilities and system management of SDA. It describes how to use SDA to perform the following tasks:

- Analyzing a system dump and a running system
- Understanding SDA context and commands
- Investigating system failures
- Inducing system failures
- Understanding the ANALYZE command and qualifiers
- Invoking SDA commands, SDA CLUE extension commands, SDA Spinlock Tracing commands, and SDA extension routines
- Determining which instructions have executed in a specific system CPU, with SDA OCLA commands (Alpha only)

Chapter 2. SDA Description

This chapter describes the functions and the system management of SDA. It describes initialization, operation, and procedures in analyzing a system dump and analyzing a running system. This chapter also describes the SDA context, the command format, and the way both to investigate system failures and induce system failures.

2.1. Capabilities of SDA

When a system failure occurs, the operating system copies the contents of memory to a system dump file or the primary page file, recording the hardware context of each processor in the system as well. The System Dump Analyzer (SDA) is a utility that allows you to interpret the contents of this file, examine the status of each processor at the time of the system failure, and investigate the probable causes of the failure.

You can invoke SDA to analyze a system dump, using the DCL command `ANALYZE/CRASH_DUMP`. You can then use SDA commands to perform the following operations:

- Direct (or echo) the output of an SDA session to a file or device (`SET OUTPUT` or `SET LOG`).
- Display the condition of the operating system and the hardware context of each processor in the system at the time of the system failure (`SHOW CRASH` or `CLUE CRASH`).
- Select a specific processor in a multiprocessing system as the subject of analysis (`SET CPU`).
- Select the default size of address data manipulated by the `EXAMINE` and `EVALUATE` commands (`SET FETCH`).
- Enable or disable the sign extension of 32-bit addresses (`SET SIGN_EXTEND`).
- Display the contents of a specific process stack (`SHOW STACK` or `CLUE STACK`).
- Format a call frame from a stack location (`SHOW CALL_FRAME`).
- Read a set of global symbols into the SDA symbol table (`READ`).
- Define symbols to represent values or locations in memory and add them to the SDA symbol table (`DEFINE`).
- Delete symbols not required from the SDA symbol table (`UNDEFINE`).
- Evaluate an expression in hexadecimal and decimal, interpreting its value as a symbol, a condition value, a page table entry (PTE), a processor status (PS) quadword, or date and time (`EVALUATE`).
- Examine the contents of memory locations, optionally interpreting them as assembler instructions, a PTE, a PS, or date and time (`EXAMINE`).
- Display device status as reflected in system data structures (`SHOW DEVICE`).
- Display the contents of the stored machine check frame (`SHOW MACHINE_CHECK` or `CLUE MCHK`) for selected HP computers.
- Format system data structures (`FORMAT`).
- Validate the integrity of the links in a queue (`VALIDATE QUEUE`).
- Display a summary of all processes on the system (`SHOW SUMMARY`).

- Show the hardware or software context of a process (SHOW PROCESS or CLUE PROCESS).
- Display the OpenVMS RMS data structures of a process (SHOW PROCESS with the /RMS qualifier).
- Display memory management data structures (SHOW POOL, SHOW PFN_DATA, SHOW PAGE_TABLE, or CLUE MEMORY).
- Display lock management data structures (SHOW RESOURCES or SHOW LOCKS).
- Display OpenVMS Cluster management data structures (SHOW CLUSTER, SHOW CONNECTIONS, SHOW RSPID, or SHOW PORTS).
- Display multiprocessor synchronization information (SHOW SPINLOCKS).
- Display the layout of the executive images (SHOW EXECUTIVE).
- Capture and archive a summary of dump file information in a list file (CLUE HISTORY).
- Copy the system dump file (COPY).
- Define keys to invoke SDA commands (DEFINE/KEY).
- Search memory for a given value (SEARCH).

Although SDA provides a great deal of information, it does not automatically analyze all the control blocks and data contained in memory. For this reason, in the event of system failure, it is extremely important that you save not only the output provided by SDA commands, but also a copy of the system dump file written at the time of the failure.

You can also invoke SDA to analyze a running system, using the DCL command ANALYZE/SYSTEM. Most SDA commands generate useful output when entered on a running system.

Caution

Although analyzing a running system may be instructive, you should undertake such an operation with caution. System context, process context, and a processor's hardware context can change during any given display.

In a multiprocessing environment, it is very possible that, during analysis, a process running SDA could be rescheduled to a different processor frequently. Therefore, avoid examining the hardware context of processors in a running system.

2.2. System Management and SDA

The system manager must ensure that the system writes a dump file whenever the system fails. The manager must also see that the dump file is large enough to contain all the information to be saved, and that the dump file is saved for analysis. The following sections describe these tasks.

2.2.1. Writing System Dumps

The operating system attempts to write information into the system dump file only if the system parameter DUMPBUG is set. (The DUMPBUG parameter is set by default. To examine and change its value, consult the *VSI OpenVMS System Manager's Manual, Volume 2: Tuning, Monitoring, and Complex Systems*.) If DUMPBUG is set and the operating system fails, the system manager has the following choices for writing system dumps:

- Have the system dump file written to either SYSDUMP.DMP (the system dump file) or to PAGEFILE.SYS (the primary system page file).
- Set the DUMPSTYLE system parameter to an even number (for dumps containing all physical memory) or to an odd number (for dumps containing only selected virtual addresses). See Section 2.2.1.1 for more information about the DUMPSTYLE parameter values.

2.2.1.1. Dump File Style

There are two types of dump files---a full memory dump (also known as a physical dump), and a dump of selected virtual addresses (also known as a selective dump). Both full and selective dumps may be produced in either compressed or uncompressed form. Compressed dumps save disk space and time taken to write the dump at the expense of a slight increase in time to access the dump with SDA. The SDA commands COPY/COMPRESS and COPY/DECOMPRESS can be used to convert an existing dump.

A dump can be written to the system disk, or to another disk set aside for dumps. When using a disk other than a system disk, the disk name is set in the console environment variable DUMP_DEV. This disk is also known as the "dump off system disk" (DOSD) disk.

When writing a system dump, information about the crash is displayed at the system console. This can be either minimal output (for example, bug check code, process name, and image name), or verbose output (for example, executive layout, stack and register contents).

In an OpenVMS Galaxy system, shared memory is dumped by default. It is sometimes necessary to disable the dumping of shared memory. For more information about shared memory, see *VSI OpenVMS Alpha Partitioning and Galaxy Guide*.

DUMPSTYLE, which specifies the method of writing system dumps, is a 32-bit mask. Table 2.1 shows how the bits are defined. Each bit can be set independently. The value of the SYSGEN parameter is the sum of the values of the bits that have been set. Remaining or undefined values are reserved to VSI.

Table 2.1. Definitions of Bits in DUMPSTYLE

Bit	Value	Description
0	1	0= Full dump. The entire contents of physical memory will be written to the dump file. 1= Selective dump. The contents of memory will be written to the dump file selectively to maximize the usefulness of the dump file while conserving disk space. (Only pages that are in use are written).
1	2	0= Minimal console output. This consists of the bugcheck code; the identity of the CPU, process, and image where the crash occurred; the system date and time; plus a series of dots indicating progress writing the dump. 1= Full console output. This includes the minimal output previously described plus stack and register contents, system layout, and additional progress information such as the names of processes as they are dumped.
2	4	0= Dump to system disk. The dump will be written to SYS\$SYSDEVICE:[SYSn.SYSEXE]SYSDUMP.DMP, or in its absence, SYS\$SYSDEVICE:[SYSn.SYSEXE]PAGEFILE.SYS. 1= Dump to alternate disk. The dump will be written to dump_dev:

Bit	Value	Description
		[SYSn.SYSEXEXE]SYSDUMP.DMP, where dump_dev is the value of the console environment variable DUMP_DEV.
3	8	0= Uncompressed dump. Pages are written directly to the dump file. 1= Compressed dump. Each page is compressed before it is written, providing a saving in space and in the time taken to write the dump, at the expense of a slight increase in time taken to access the dump.
4	16	0= Dump shared memory. 1= Do not dump shared memory.
5	32	0= Write all processes and global pages in a selective dump. 1= Write only key processes and global pages in a selective dump. This bit is ignored when writing a full dump (bit 0 = 0). This bit should be set only if the priority processes have been correctly set up, as described in <i>VSI OpenVMS System Manager's Manual, Volume 2: Tuning, Monitoring, and Complex Systems</i> .
6--31		Reserved to VSI.

The default setting for DUMPSTYLE is 9 (a compressed selective dump, including shared memory, written to the system disk). Unless a value for DUMPSTYLE is specified in MODPARAMS.DAT, AUTOGEN.COM will set DUMPSTYLE either to 1 (an uncompressed selective dump, including shared memory, written to the system disk) if there is less than 128 megabytes of memory on the system, or to 9 (a compressed selective dump, including shared memory, written to the system disk).

2.2.1.2. Comparison of Full and Selective Dumps

A full dump requires that all physical memory be written to the dump file. This ensures the presence of all the page table pages required for SDA to emulate translation of system virtual addresses. Any even-numbered value in the DUMPSTYLE system parameter generates a full dump.

In certain system configurations, it may be impossible to preserve the entire contents of memory in a disk file. For instance, a large memory system or a system with small disk capacity may not be able to supply enough disk space for a full memory dump. If the system dump file cannot accommodate all of memory, information essential to determining the cause of the system failure may be lost.

To preserve those portions of memory that contain information most useful in determining the causes of system failures, a system manager sets the value of the DUMPSTYLE system parameter to specify a dump of selected virtual address spaces. In a selective dump, related pages of virtual address space are written to the dump file as units called logical memory blocks (LMBs). For example, one LMB consists of the page tables for system space; another is the address space of a particular process. Those LMBs most likely to be useful in crash dump analysis are written first. Any odd-numbered value in the DUMPSTYLE system parameter generates a selective dump.

Table 2.2 compares full and selective style dumps.

Table 2.2. Comparison of Full and Selective Dumps

Item	Full	Selective
Available Information	Complete contents of physical memory in use, stored in order of increasing physical address.	System page table, global page table, system space memory, and process and control regions

Item	Full	Selective
		(plus global pages) for all saved processes.
Unavailable Information	Contents of paged-out memory at the time of the system failure.	Contents of paged-out memory at the time of the system failure, process and control regions of unsaved processes, and memory not mapped by a page table.
SDA Command Limitations	None.	The following commands are not useful for unsaved processes: SHOW PROCESS/CHANNELS, SHOW PROCESS/IMAGE, SHOW PROCESS/RMS, SHOW STACK, and SHOW SUMMARY/IMAGE.

2.2.1.3. Controlling the Size of Page Files and Dump Files

You can adjust the size of the system page file and dump file using AUTOGEN (the recommended method) or by using SYSGEN.

AUTOGEN automatically calculates the appropriate sizes for page and dump files. AUTOGEN invokes the System Generation utility (SYSGEN) to create or change the files. However, you can control sizes calculated by AUTOGEN by defining symbols in the MODPARAMS.DAT file. The file sizes specified in MODPARAMS.DAT are copied into the PARAMS.DAT file during AUTOGEN's GETDATA phase. AUTOGEN then makes appropriate adjustments in its calculations.

Although VSI recommends using AUTOGEN to create and modify page and dump file sizes, you can use SYSGEN to directly create and change the sizes of those files.

The sections that follow discuss how you can calculate the size of a dump file.

See the *VSI OpenVMS System Manager's Manual* for detailed information about using AUTOGEN and SYSGEN to create and modify page and dump file sizes.

2.2.1.4. Writing to the System Dump File

OpenVMS writes the contents of the error-log buffers, processor registers, and memory into the system dump file, overwriting its previous contents. If the system dump file is too small, OpenVMS cannot copy all memory to the file when a system failure occurs.

SYSS\$SYSTEM:SYSDUMP.DMP (SYSS\$SPECIFIC:[SYSEXE]SYSDUMP.DMP) is created during installation. To successfully store a crash dump, SYSS\$SYSTEM:SYSDUMP.DMP must be enlarged to hold all of memory (full dump) or all of system space and the key processes (selective dump).

To calculate the correct size for an uncompressed full dump to SYSS\$SYSTEM:SYSDUMP.DMP, use the following formula:

```
size-in-blocks (SYSS$SYSTEM:SYSDUMP.DMP)
    = size-in-pages (physical-memory) * blocks-per-page
    + number-of-error-log-buffers * blocks-per-buffer
    + 10
```

Use the DCL command SHOW MEMORY to determine the total size of physical memory on your system. There is a variable number of error log buffers in any given system, depending on the setting

of the ERRORLOGBUFF_S2 system parameter. The size of each buffer depends on the setting of the ERLBUFFERPAG_S2 parameter. (See the *VSI OpenVMS System Manager's Manual* for additional information about these parameters.)

2.2.1.5. Writing to a Dump File off the System Disk

OpenVMS allows you to write the system dump file to a device other than the system disk. This is useful in large memory systems and in clusters with common system disks where sufficient disk space, on one disk, is not always available to support customer dump file requirements. To perform this activity, the DUMPSTYLE system parameter must be correctly enabled to allow the bugcheck code to write the system dump file to an alternative device.

The requirements for writing the system dump file off the system disk are the following:

- The dump device directory structure must resemble the current system disk structure. The [SYSn.SYSEXE]SYSDUMP.DMP file will reside there, with the same boot time system root.

You can use AUTOGEN to create this file. In the MODPARAMS.DAT file, the following symbol prompts AUTOGEN to create the file:

```
DUMPFILe_DEVICE = $nnn$ddcuuuu
```

- The dump device cannot be part of a volume set or a member of a shadow set.
- You must set up DOSD for SDA CLUE as described in Chapter 5.
- The DUMP_DEV environment variable must exist on your system. You specify the dump device at the console prompt, using the following format:

For Alpha

```
>>> SET DUMP_DEV device-name[,...]
```

For Integrity servers

```
Shell> VMS_SET DUMP_DEV device-name[,...]
```

On some CPU types, you can enter a list of devices. The list can include various alternate paths to the system disk and the dump disk.

By specifying alternate paths in DUMP_DEV, a dump can still be written if the disk fails over to an alternate path while the system is running. When the system crashes, the bugcheck code can use the alternate path by referring to the contents of DUMP_DEV.

When you enter a list of devices, however, the system disk must come last.

For information on how to write the system dump file to an alternative device to the system disk, see the *VSI OpenVMS System Manager's Manual, Volume 2: Tuning, Monitoring, and Complex Systems*.

2.2.1.6. Writing to the System Page File

If SYS\$SYSTEM:SYSDUMP.DMP does not exist, and there is no DOSD device or dump file, the operating system writes the dump of physical memory into SYS\$SYSTEM:PAGEFILE.SYS, the primary system page file, overwriting the contents of that file.

If the SAVEDUMP system parameter is set, the dump file is retained in PAGEFILE.SYS when the system is booted after a system failure. If the SAVEDUMP parameter is not set, which is the default,

OpenVMS uses the entire page file for paging and any dump written to the page file is lost. (To examine or change the value of the `SAVEDUMP` parameter, consult the *VSI OpenVMS System Manager's Manual, Volume 2: Tuning, Monitoring, and Complex Systems.*)

To calculate the minimum size for a full memory dump to `SYS$SYSTEM:PAGEFILE.SYS`, use the following formula:

```
size-in-blocks (SYS$SYSTEM:PAGEFILE.SYS)
    = size-in-pages (physical-memory) * blocks-per-page
    + number-of-error-log-buffers * blocks-per-buffer
    + 10
    + value of the system parameter RSRVPAGCNT * blocks-per-page
```

Note that this formula calculates the minimum size requirement for saving a physical dump in the system's page file. VSI recommends that the page file be a bit larger than this minimum to avoid hanging the system. Also note that you can only write the system dump into the primary page file (`SYS$SYSTEM:PAGEFILE.SYS`). Secondary page files cannot be used to save dump file information.

Note also that OpenVMS will not fill the page file completely when writing a system dump, since the system might hang when rebooting after a system crash. `RSRVPAGCNT` pages are kept unavailable for dumps. This applies to both full dumps and selective dumps.

Writing crash dumps to `SYS$SYSTEM:PAGEFILE.SYS` presumes that you will later free the space occupied by the dump for use by the pager. Otherwise, your system may hang during the startup procedure. To free this space, you can do one of the following:

- Include SDA commands that free dump space in the site-specific startup command procedure (described in Section 2.2.4).
- Use the SDA `COPY` command to copy the dump from `SYS$SYSTEM:PAGEFILE.SYS` to another file. Use the SDA `COPY` command instead of the DCL `COPY` command because the SDA `COPY` command only copies the blocks used by the dump and causes the pages occupied by the dump to be freed from the system's page file.
- If you do not need to copy the dump elsewhere, issue an `ANALYZE/CRASH_DUMP/RELEASE` command. When you issue this command, SDA immediately releases the pages to be used for system paging, effectively deleting the dump. Note that this command does not allow you to analyze the dump before deleting it.

2.2.2. Saving System Dumps

Every time the operating system writes information to the system dump file, it writes over whatever was previously stored in the file. The system writes information to the dump file whenever the system fails. For this reason, the system manager must save the contents of the file after a system failure has occurred.

The system manager can use the SDA `COPY` command or the DCL `COPY` command. Either command can be used in a site-specific startup procedure, but the SDA `COPY` command is preferred because it marks the dump file as copied. As mentioned earlier, this is particularly important if the dump was written into the page file, `SYS$SYSTEM:PAGEFILE.SYS`, because it releases those pages occupied by the dump to the pager. Another advantage of using the SDA `COPY` command is that this command copies only the saved number of blocks and not necessarily the whole allotted dump file. For instance, if the size of the `SYSDUMP.DMP` file is 100,000 blocks and the bugcheck wrote only 60,000 blocks to the dump file, then DCL `COPY` would create a file of 100,000 blocks. However, SDA `COPY` would generate a file of only 60,000 blocks.

Because system dump files are set to NOBACKUP, the Backup utility (BACKUP) does not copy them to tape unless you use the qualifier /IGNORE=NOBACKUP when invoking BACKUP. When you use the SDA COPY command to copy the system dump file to another file, OpenVMS does not set the new file to NOBACKUP.

As created during installation, the file SYS\$SYSTEM:SYSDUMP.DMP is protected against world access. Because a dump file can contain privileged information, VSI recommends that the system manager does not change this default protection.

When a dump is being analyzed, it is useful to have data available that cannot be written to the dump file at the time of the system crash. This data includes the full file specification associated with a file identification, and, on OpenVMS Integrity servers, the unwind data for images activated in processes.

If the dump is being analyzed on the system where it was originally written, this data can be collected for use in the current SDA session by using the COLLECT command. If the dump is being copied for analysis elsewhere, the COPY/COLLECT command can be used to collect the data and append it to the copy being written. If the COPY/COLLECT command is used after a COLLECT command, the data already collected is appended to the dump copy.

By default, a copy of the original dump, as written at the time of the system crash, will include collection. You can use the COPY/NOCOLLECT command to override this. Conversely, a copy of a dump previously copied by SDA without collection (COPY/NOCOLLECT) will not include collection. You can use COPY/COLLECT to override this.

Copying a dump that already contains an appended collection will always include that collection.

For all file and unwind data to be collected successfully, all disks that were mounted at the time of the system crash should be remounted and accessible to the process running SDA. If SDA is invoked early during the startup to save the contents of the dump (for example, using CLUE\$SITE_PROC, as described in Section 2.2.4), but disks are not mounted until a batch job is run, the COPY/NOCOLLECT command should be used in the CLUE\$SITE_PROC command procedure. Once all disks are mounted, you can use a COPY/COLLECT command to save file and unwind data.

If the COPY and COLLECT operations cannot be done as a single step, a COLLECT/SAVE command will write the collection to a separate file that can be used later in conjunction with the dump file. A later COPY will combine the two files.

2.2.3. Partial Dump Copies

Because of the layout of a selective dump, it is often the case that only a small part of the dump is needed to investigate the cause of the system crash. The system manager must save the complete dump locally, as described in the previous section, but has to provide only the key sections of the dump to VSI Services for analysis. This can significantly reduce the time taken to copy the dump over the network. Such a copy is referred to as a Partial Dump Copy. It can only be used when a selective system dump (compressed or uncompressed) has been written, and is not available for full system dumps or for process dumps.

If you require information from a section of the dump that was not copied, it can be extracted from the saved local copy and submitted separately. The ANALYZE /CRASH_DUMP command accepts multiple input files from the same crash and treats them as a single dump.

For an explanation of key processes and key global pages, and the organization of a selective system dump, see the chapter Managing Page, Swap, and Dump Files in the *VSI OpenVMS System Manager's Manual, Volume 2: Tuning, Monitoring, and Complex Systems*.

2.2.3.1. Example - Use of Partial Dump Copies

The following steps describe a typical use of Partial Dump Copies:

1. Save the complete dump:

```
$ ANALYZE/CRASH SYS$SYSTEM:SYSDUMP.DMP

OpenVMS system dump analyzer
...analyzing an I64 compressed selective memory dump...

Dump taken on 22-SEP-2009 18:17:17.99 using version XC4I-J2I
SSRVEXCEPT, Unexpected system service exception

SDA> COPY SSRVEXCEPT.DMP
SDA> EXIT
```

2. Create a partial copy containing only the key sections of the dump:

```
$ ANALYZE/CRASH SSRVEXCEPT

OpenVMS system dump analyzer
...analyzing an I64 compressed selective memory dump...

Dump taken on 22-SEP-2009 18:17:17.99 using version XC4I-J2I
SSRVEXCEPT, Unexpected system service exception

SDA> COPY SSRVKEY /PARTIAL=KEY
SDA> EXIT
```

3. Provide the output of this copy, containing only the key sections, to VSI Services, where it can be analyzed as follows:

```
$ ANALYZE/CRASH SSRVKEY

OpenVMS system dump analyzer
...analyzing an I64 compressed selective memory dump...

Dump taken on 22-SEP-2009 18:17:17.99 using version XC4I-J2I
SSRVEXCEPT, Unexpected system service exception

SDA> SHOW CRASH
SDA> !
```

4. During analysis of the crash, VSI Services determines that the CLUSTER_SERVER process, not included in the partial dump copy, is required and requests that part of the dump. Extract the process from the saved complete copy, as follows:

```
$ ANALYZE/CRASH SSRVEXCEPT

OpenVMS system dump analyzer
...analyzing an I64 compressed selective memory dump...

Dump taken on 22-SEP-2009 18:17:17.99 using version XC4I-J2I
SSRVEXCEPT, Unexpected system service exception

SDA> COPY SSRVCSP /PARTIAL=PROCESS=NAME=CLUSTER_SERVER
SDA> EXIT
```

5. Provide the output of this copy to VSI Services for analysis, where it can be analyzed as follows:

```
$ ANALYZE/CRASH SSRVKEY,SSRVCSP
```

```
OpenVMS system dump analyzer
...analyzing an I64 compressed selective memory dump...
```

```
Dump taken on 22-SEP-2009 18:17:17.99 using version XC4I-J2I
SSRVEXCEPT, Unexpected system service exception
```

```
SDA> SHOW PROCESS CLUSTER_SERVER
SDA> ! etc.
```

2.2.3.2. Additional notes on Partial Dump Copies

This section provides additional notes on Partial Dump Copies.

- In Step 4 of the preceding example, the COPY command cannot be given as shown:

```
SDA> COPY /PARTIAL=PROCESS=NAME=CLUSTER_SERVER SSRVCSP
```

This is because SDA must treat the combined string "CLUSTER SERVER SSRVCSP" as the process name, since spaces are valid in a process name. Alternative formats that can be used are as follows:

```
SDA> COPY /PARTIAL=PROCESS=NAME=CLUSTER_SERVER SSRVCSP
SDA> COPY /PARTIAL=PROCESS=NAME=(CLUSTER_SERVER) SSRVCSP
SDA> COPY /PARTIAL=(PROCESS=NAME=CLUSTER_SERVER) SSRVCSP
```

- In Step 5 of the preceding example, the input files cannot be specified as "SSRV*". In that case, SSRVCSP.DMP can be opened before SSRVKEY.DMP. The file that contains the section PT must be opened first.
- In a selective system dump, processes are dumped in two sections:
 - Process Page Table Space
 - Process Memory

If a process is copied as part of a COPY /PARTIAL, the two sections are always copied together.

- In a selective system dump from an Alpha system with Resource Affinity Domains (RADs) enabled, there is a Replicated System Space section for each RAD other than the base RAD. If replicated system space is copied as part of a COPY /PARTIAL, all replicated system space sections are always copied together.
- See the description of the COPY command in Chapter 4 for a complete list of the possible section names.

2.2.4. Invoking SDA When Rebooting the System

When the system reboots after a system failure, SDA is automatically invoked by default. SDA archives information from the dump in a history file. In addition, a listing file with more detailed information about the system failure is created in the directory pointed to by the logical name CLUE\$COLLECT. (Note that the default directory is SYSS\$ERRORLOG unless you redefine the logical name CLUE\$COLLECT in the procedure SYSS\$MANAGER:SYLOGICALS.COM.) The file name is in the form CLUE\$node_ddmmyy_hhmm.LIS where the timestamp (*hhmm*) corresponds to the system failure time and not the time when the file was created.

Directed by commands in a site-specific file, SDA can take additional steps to record information about the system failure. They include the following:

- Supplementing the contents of the list file containing the output of specific SDA commands.
- Copying the contents of the dump file to another file. This information is otherwise lost at the next system failure when the system saves information only about that failure.

If the logical name CLUE\$SITE_PROC points to a valid and existing command file, it will be executed as part of the CLUE HISTORY command when you reboot. If used, this file should contain only valid SDA commands.

Generated by a set sequence of commands, the CLUE list file contains only an overview of the failure and is unlikely to provide enough information to determine the cause of the failure. VSI, therefore, recommends that you always copy the dump file.

The following example shows SDA commands that can make up your site-specific command file to produce a more complete SDA listing after each system failure, and to save a copy of the dump file:

```
!  
! SDA command file, to be executed as part of the system  
! bootstrap from within CLUE. Commands in this file can  
! be used to save the dump file after a system bugcheck, and  
! to execute any additional SDA commands.  
!  
! Note that the logical name DMP$ must have been defined  
! within SYS$MANAGER:SYLOGICALS.COM  
!  
READ/EXEC           ! read in the executive images' symbol tables  
SHOW STACK          ! display the stack  
COPY DMP$:SAVEDUMP.DMP ! copy and save dump file  
!
```

The CLUE HISTORY command is executed first, followed by the SDA commands in this site-specific command file. See the reference section on CLUE HISTORY for details on the summary information that is generated and stored in the CLUE list file by the CLUE HISTORY command. Note that the SDA COPY command must be the last command in the command file. If the dump has been written to PAGEFILE.SYS, then the space used by the dump will be automatically returned for use for paging as soon as the COPY is complete and no more analysis is possible. You might need to include the / NOCOLLECT qualifier on the COPY command. See Section 2.2.2 for details.

To point to your site-specific file, add a line such as the following to the file SYS \$MANAGER:SYLOGICALS.COM:

```
$ DEFINE/SYSTEM CLUE$SITE_PROC SYS$MANAGER:SAVEDUMP.COM
```

In this example, the site-specific file is named SAVEDUMP.COM.

The CLUE list file can be printed immediately or saved for later examination.

SDA is invoked and executes the specified commands only when the system boots for the first time after a system failure. If the system is booting for any other reason (such as a normal system shutdown and reboot), SDA exits.

If CLUE files occupy more space than the threshold allows (the default is 5000 blocks), the oldest files will be deleted until the threshold limit is reached. The threshold limit can be customized with the CLUE \$MAX_BLOCK logical name.

To prevent the running of CLUE at system startup, define the logical CLUE\$INHIBIT in the SYLOGICALS.COM file as TRUE in the system logical name table.

2.3. Analyzing a System Dump

SDA performs certain tasks before bringing a dump into memory, presenting its initial displays, and accepting command input. These tasks include the following:

- Verifying that the process invoking it is suitably privileged to read the dump file
- Using RMS to read in pages from the dump file
- Building the SDA symbol table from the files SDA\$READ_DIR:SYS\$BASE_IMAGE.EXE and SDA\$READ_DIR:REQSYSDEF.STB
- Executing the commands in the SDA initialization file

For detailed information on investigating system failures, see Section 2.7.

2.3.1. Requirements

To analyze a dump file, your process must have read access both to the file that contains the dump and to copies of SDA\$READ_DIR:SYS\$BASE_IMAGE.EXE and SDA\$READ_DIR:REQSYSDEF.STB (the required subset of the symbols in the file SYSDEF.STB). SDA reads these tables by default.

2.3.2. Invoking SDA

If your process can access the files listed in Section 2.3.1, you can issue the DCL command ANALYZE/CRASH_DUMP to invoke SDA. If you do not specify the name of a dump file in the command, and SYSSYSTEM:SYSDUMP.DMP cannot be opened, SDA prompts you:

```
$ ANALYZE/CRASH_DUMP
_Dump File:
```

If any part of the file name is specified, the default file specification is as follows:

```
@ @ @ @SYSS$DISK:[default-dir]SYSDUMP.DMP
```

SYSS\$DISK and [default-dir] represent the disk and directory specified in your last SET DEFAULT command.

If you are rebooting after a system failure, SDA is automatically invoked. See Section 2.2.4.

2.3.3. Mapping the Contents of the Dump File

SDA first attempts to map the contents of memory as stored in the specified dump file. To do this, it must first locate the page tables for system space among its contents. The system page tables contain one entry for each page of system virtual address space.

- If SDA cannot find the system page tables in the dump file, it displays the following message:

```
%SDA-E-SPTNOTFND, system page table not found in dump file
```


If that error message is displayed, you cannot analyze the crash dump, but must take steps to ensure that any subsequent dump can be analyzed. To do this, you must either adjust the DUMPSTYLE system parameter as discussed in Section 2.2.1.1 or increase the size of the dump file as indicated in Section 2.2.1.3.

- If SDA finds the system page tables in an incomplete dump, the following message is displayed:

```
%SDA-W-SHORTDUMP, dump file was n blocks too small when dump written;
analysis may not be possible
```

Under certain conditions, some memory locations might not be saved in the system dump file. Additionally, if a bugcheck occurs during system initialization, the contents of the register display may be unreliable. The symptom of such a bugcheck is a SHOW SUMMARY display that shows no processes or only the swapper process.

If you use an SDA command to access a virtual address that has no corresponding physical address, SDA generates the following error message:

```
%SDA-E-NOTINPHYS, 'location': virtual data not in physical memory
```

When analyzing a selective dump file, if you use an SDA command to access a virtual address that has a corresponding physical address not saved in the dump file, SDA generates one of the following error messages:

```
%SDA-E-MEMNOTSVD, memory not saved in the dump file
```

```
%SDA-E-NOREAD, unable to access location n
```

2.3.4. Building the SDA Symbol Table

After locating and reading the system dump file, SDA attempts to read the system symbol table file into the SDA symbol table. If SDA cannot find SDA\$READ_DIR:SYS\$BASE_IMAGE.EXE---or is given a file that is not a system symbol table in the /SYMBOL qualifier to the ANALYZE command---it displays a fatal error and exits. SDA also reads into its symbol table a subset of SDA\$READ_DIR:SYSDEF.STB, called SDA\$READ_DIR:REQSYSDEF.STB. This subset provides SDA with the information needed to access some of the data structures in the dump.

When SDA finishes building its symbol table, SDA displays a message identifying itself and the immediate cause of the system failure. In the following example, the cause of the system failure was the deallocation of a bad page file address.

```
OpenVMS Alpha System Dump Analyzer
```

```
Dump taken on 27-MAR-1993 11:22:33.92
BADPAGFILD, Bad page file address deallocated
```

2.3.5. Executing the SDA Initialization File (SDA\$INIT)

After displaying the system failure summary, SDA executes the commands in the SDA initialization file, if you have established one. SDA refers to its initialization file by using the logical name SDA\$INIT. If SDA cannot find the file defined as SDA\$INIT, it searches for the file SYS\$LOGIN:SDA.INIT.

This initialization file can contain SDA commands that read symbols into SDA's symbol table, define keys, establish a log of SDA commands and output, or perform other tasks. For instance, you may want to use an SDA initialization file to augment SDA's symbol table with definitions helpful in locating

system code. If you issue the following command, SDA includes those symbols that define many of the system's data structures, including those in the I/O database:

```
READ SDA$READ_DIR:filename
```

You may also find it helpful to define those symbols that identify the modules in the images that make up the executive by issuing the following command:

```
READ/EXECUTIVE SDA$READ_DIR:
```

After SDA has executed the commands in the initialization file, it displays its prompt as follows:

```
SDA>
```

This prompt indicates that you can use SDA interactively and enter SDA commands.

An SDA initialization file may invoke a command procedure with the @ command. However, such command procedures cannot invoke other command procedures.

2.4. Analyzing a Running System

Occasionally, OpenVMS encounters an internal problem that hinders system performance without causing a system failure. By allowing you to examine the running system, SDA enables you to search for the solution without disturbing the operating system. For example, you may be able to use SDA to examine the stack and memory of a process that is stalled in a scheduler state, such as a miscellaneous wait (MWAIT) or a suspended (SUSP) state.

If your process has change-mode-to-kernel (CMKRNL) privilege, you can invoke SDA to examine the system. Use the following DCL command:

```
$ ANALYZE/SYSTEM
```

SDA attempts to load SDA\$READ_DIR:SYS\$BASE_IMAGE.EXE and SDA \$READ_DIR:REQSYSDEF.STB. It then executes the contents of any existing SDA initialization file, as it does when invoked to analyze a crash dump (see Sections Section 2.3.4 and Section 2.3.5, respectively). SDA subsequently displays its identification message and prompt, as follows:

```
OpenVMS Alpha System Analyzer
```

```
SDA>
```

This prompt indicates that you can use SDA interactively and enter SDA commands. When analyzing a running system, SDA sets its process context to that of the process running SDA.

If you are analyzing a running system, consider the following:

- When used in this mode, SDA does not map the entire system, but instead retrieves only the information it needs to process each individual command. To update any given display, you must reissue the previous command.

Caution

When using SDA to analyze a running system, carefully interpret its displays. Because system states change frequently, it is possible that the information SDA displays may be inconsistent with the current state of the system.

- Certain SDA commands are illegal in this mode, such as SET CPU. Use of these commands results in the following error message:

```
%SDA-E-CMDNOTVLD, command not valid on the running system
```

- The SHOW CRASH command, although valid, does not display the contents of any of the processor's set of hardware registers.

2.5. SDA Context

When you invoke SDA to analyze either a crash dump or a running system, SDA establishes a default context for itself from which it interprets certain commands.

When you are analyzing a uniprocessor system, SDA's context is solely **process context**, which means SDA can interpret its process-specific commands in the context of either the process current on the uniprocessor or some other process in another scheduling state. When SDA is initially invoked to analyze a crash dump, SDA's process context defaults to that of the process that was current at the time of the system failure. When you invoke SDA to analyze a running system, SDA's process context defaults to that of the current process, that is, the one executing SDA. To change SDA's process context, issue any of the following commands:

- SET PROCESS process-name
- SET PROCESS/ADDRESS=pcb-address
- SET PROCESS/INDEX=nn
- SET PROCESS/NEXT
- SET PROCESS/SYSTEM
- SHOW PROCESS process-name
- SHOW PROCESS/ADDRESS=pcb-address
- SHOW PROCESS/INDEX=nn
- SHOW PROCESS/NEXT
- SHOW PROCESS/SYSTEM
- VALIDATE PROCESS/POOL process-name
- VALIDATE PROCESS/POOL/ADDRESS=pcb-address
- VALIDATE PROCESS/POOL/INDEX=nn
- VALIDATE PROCESS/POOL/NEXT
- VALIDATE PROCESS/POOL/SYSTEM

When you invoke SDA to analyze a crash dump from a multiprocessing system with more than one active CPU, SDA maintains a second dimension of context---its **CPU context**---that allows it to display certain processor-specific information. This information includes the reason for the bugcheck exception, the currently executing process, the current IPL, and the spinlocks owned by the processor. When you invoke SDA to analyze a multiprocessor's crash dump, its CPU context defaults to that of the processor

that induced the system failure. When you are analyzing a running system, CPU context is not accessible to SDA. Therefore, the SET CPU command is not permitted.

You can change the SDA CPU context by using any of the following commands:

- SET CPU cpu-id
- SET CPU /FIRST
- SET CPU /NEXT
- SET CPU /PRIMARY
- SHOW CPU cpu-id
- SHOW CPU /FIRST
- SHOW CPU /NEXT
- SHOW CPU /PRIMARY
- SHOW CRASH
- SHOW MACHINE_CHECK cpu-id

Changing CPU context involves an implicit change in process context in either of the following ways:

- If there is a current process on the CPU made current, SDA process context is changed to that of that CPU's current process.
- If there is no current process on the CPU made current, SDA process context is undefined and no process-specific information is available until SDA process context is set to that of a specific process.

Changing process context requires a switch of CPU context as well. For instance, when you issue a SET PROCESS command, SDA automatically changes its CPU context to that of the CPU on which that process was most recently current. The following commands can have this effect:

- SET PROCESS process-name
- SET PROCESS/ADDRESS=pcb-address
- SET PROCESS/INDEX=nn
- SET PROCESS/NEXT
- SHOW PROCESS process-name
- SHOW PROCESS/ADDRESS=pcb-address
- SHOW PROCESS/INDEX=nn
- SHOW PROCESS/NEXT
- VALIDATE PROCESS/POOL process-name
- VALIDATE PROCESS/POOL/ADDRESS=pcb-address
- VALIDATE PROCESS/POOL/INDEX=nn
- VALIDATE PROCESS/POOL/NEXT

2.6. SDA Command Format

The following sections describe the format of SDA commands and the expressions you can use with SDA commands.

SDA uses a command format similar to that used by the DCL interpreter. Issue commands in the following format:

```
command-name[/qualifier...] [parameter][/qualifier...] [!comment]
```

The **command-name** is an SDA command. Each command tells the utility to perform a function. Commands can consist of one or more words, and can be abbreviated to the number of characters that make the command unique. For example, SH stands for SHOW.

The **parameter** is the target of the command. For example, SHOW PROCESS RUSKIN tells SDA to display the context of the process RUSKIN. The command EXAMINE 80104CD0;40 displays the contents of 40 bytes of memory, beginning with location 80104CD0.

When you supply part of a file specification as a parameter, SDA assumes default values for the omitted portions of the specification. The default device is SYSSDISK, the device specified in your most recent SET DEFAULT command. The default directory is the directory specified in the most recent SET DEFAULT command. See the *VSI OpenVMS DCL Dictionary* for a description of the DCL command SET DEFAULT.

The **qualifier** modifies the action of an SDA command. A qualifier is always preceded by a slash (/). Several qualifiers can follow a single parameter or command name, but each must be preceded by a slash. Qualifiers can be abbreviated to the shortest string of characters that uniquely identifies the qualifier.

The **comment** consists of text that describes the command; this comment is not actually part of the command. Comments are useful for documenting SDA command procedures. When executing a command, SDA ignores the exclamation point and all characters that follow it on the same line.

2.6.1. Using Expressions and Operators

You can use expressions as parameters for some SDA commands, such as SEARCH and EXAMINE. To create expressions, use any of the following elements:

- Numerals
- Radix operators
- Arithmetic and logical operators
- Precedence operators
- Symbols

Numerals are one possible component of an expression. The following sections describe the use of the other components.

2.6.1.1. Radix Operators

Radix operators determine which numeric base SDA uses to evaluate expressions. You can use one of the three radix operators to specify the radix of the numeric expression that follows the operator:

- ^X (hexadecimal)

- ^O (octal)
- ^D (decimal)

The default radix is hexadecimal. SDA displays hexadecimal numbers with leading zeros and decimal numbers with leading spaces.

2.6.1.2. Arithmetic and Logical Operators

There are two types of arithmetic and logical operators:

- **Unary operators** affect the value of the expression that follows them. (See Table 2.3.)
- **Binary operators** combine the operands that precede and follow them. (See Table 2.4.)

In evaluating expressions containing binary operators, SDA performs logical AND, OR, and XOR operations, and multiplication, division, and arithmetic shifting before addition and subtraction. Note that the SDA arithmetic operators perform integer arithmetic on 64-bit operands.

Table 2.3. SDA Unary Operators

Operator	Action
#	Performs a logical NOT of the expression.
+	Makes the value of the expression positive.
--	Makes the value of the expression negative.
@	Evaluates the following expression as an address, then uses the contents of that address as its value.
^Q	Specifies that the size of the field to be used as an address is a quadword when used with the unary operator @ 1.
^L	Specifies that the size of the field to be used as an address is a longword when used with the unary operator @ 1.
^W	Specifies that the size of the field to be used as an address is a word when used with the unary operator @ 1.
^B	Specifies that the size of the field to be used as an address is a byte when used with the unary operator @ 1.
^P	Specifies a physical address when used with the unary operator @. The command SET FETCH can be used to change the default FETCH size and/or access method. See the SET FETCH command description in Chapter 4 for more details and examples.
^V	Specifies a virtual address when used with the unary operator @ 1. The command SET FETCH can be used to change the default FETCH size and/or access method. See the SET FETCH command description in Chapter 4 for more details and examples.

Operator	Action
G	Adds FFFFFFFF 80000000 16 to the value of the expression 2. The unary operator G corresponds to the first virtual address in S0 system space. For example, the expression GD40 can be used to represent the address FFFFFFFF 8000D4016.
H	Adds 7FFE0000 16 to the value of the expression 3. The unary operator H corresponds to a convenient base address in P1 space (7FFE000016). You can therefore refer to an address such as 7FFE2A6416 as H2A64
I	Fills the leading digits of the following hexadecimal number with hex value of F. For example:

Table 2.4. SDA Binary Operators

Operator	Action
+	Addition
--	Subtraction
*	Multiplication
&	Logical AND
	Logical OR
\	Logical XOR
/	Division. In division, SDA truncates the quotient to an integer, if necessary, and does not retain a remainder.
@	Arithmetic shifting
"."	Catenates two 32-bit values into a 64-bit value. For example: SDA> eval fe.50000 Hex = 000000FE00050000 Decimal = 1090922020864

2.6.1.3. Precedence Operators

SDA uses parentheses as precedence operators. Expressions enclosed in parentheses are evaluated first. SDA evaluates nested parenthetical expressions from the innermost to the outermost pairs of parentheses.

2.6.1.4. SDA Symbols

An SDA **symbol** can represent several value types. It can represent a constant, a data address, a procedure or function descriptor address, or a routine address. Constants are usually offsets of a particular field in a data structure; however, they can also represent constant values such as the BUG \$_xxx symbols.

Symbols are composed of up to 31 letters and numbers, and can include the dollar sign (\$) and underscore (_) characters. When you invoke SDA, it reads in the global symbols from the symbols table

section of `SY$BASE_IMAGE.EXE`, and from `REQSYSDEF.STB`, a required subset of the symbols in the file `SYSDEF.STB`. You can add other symbols to SDA's symbol table by using the `DEFINE` and `READ` commands.

All address symbols identify memory locations. SDA generally does not distinguish among different types of address symbols. However, for a symbol identified as the name of a procedure descriptor, SDA takes an additional step of creating an associated symbol to name the code entry point address of the procedure. It forms the code entry point symbol name by appending `_C` to the name of the procedure descriptor.

Also, SDA substitutes the code entry point symbol name for the procedure descriptor symbol when you enter the following command:

```
SDA> EXAMINE/INSTRUCTION procedure-descriptor
```

For example, enter the following command:

```
SDA> EXAMINE/INSTRUCTION SCH$QAST
```

SDA displays the following information:

```
SCH$QAST_C:      SUBQ      SP, #X40, SP
```

Now enter the `EXAMINE` command but do not specify the `/INSTRUCTION` qualifier, as follows:

```
SDA> EXAMINE SCH$QAST
```

SDA displays the following information:

```
SCH$QAST:  0000002C.00003009  ".0..,..."
```

This display shows the contents of the first two longwords of the procedure descriptor.

Note that there are no routine address symbols on Alpha systems, except for those in MACRO-64 assembly language modules. Therefore, SDA creates a routine address symbol for every procedure descriptor it has in its symbol table. The new symbol name is the same as for the procedure descriptor except that it has an `_C` appended to the end of the name.

Sources for SDA Symbols

SDA obtains its information from the following:

- Images (.EXE files)
- Image symbol table files (.STB files)
- Object files

SDA also defines symbols to access registers and to access common data structures.

The only images with symbols are shareable images and executive images. These images contain only universal symbols, such as constants and addresses.

The image symbol table files are produced by the linker with the `/SYMBOLS` qualifier. These files normally contain only universal symbols, as do the executable images. However, if the `SYMBOL_TABLE=GLOBALS` linker option is specified, the .STB file also contains all global symbols defined in the image. See the *VSI OpenVMS Linker Utility Manual* for more information.

Object files can contain global constant values. An object file used with SDA typically contains symbol definitions for data structure fields. Such an object file can be generated by compiling a

MACRO-32 source module that invokes specific macros. The macros, which are typically defined in `SYSS$LIBRARY:LIB.MLB` or `STARLET.MLB`, define symbols that correspond to data structure field offsets. The macro `$UCBDEF`, for example, defines offsets for fields within a unit control block (UCB). OpenVMS Alpha and Integrity servers provide several such object modules in `SDA$READ_DIR`, as listed in the table below. For compatibility with OpenVMS VAX, the modules' file types have been renamed to `.STB`.

Table 2.5. Modules Containing SDA Global Symbols and Data Structures

File	Contents
DCLDEF.STB	Symbols for the DCL interpreter
DECDTMDEF.STB	Symbols for transaction processing
GLXDEF.STB	Symbols for OpenVMS Galaxy data structures
IMGDEF.STB	Symbols for the image activator
IODEF.STB	I/O database structure symbols
NETDEF.STB	Symbols for DECnet data structures
REQSYSDEF.STB	Required symbols for SDA
RMSDEF.STB	Symbols that define RMS internal and user data structures and <code>RMS\$_xxx</code> completion codes
SCSDEF.STB	Symbols that define data structures for system communications services
SYSDEF.STB	Symbols that define system data structures, including the I/O database
TCPIP\$NET_GLOBALS.STB 1	Data structure definitions for TCP/IP internet driver, <code>execlet</code> , and ACP data structures. Available only if TCP/IP has been installed.
TCPIP\$NFS_GLOBALS.STB 1	Data structure definitions for TCP/IP NFS server. Available only if TCP/IP has been installed.
TCPIP\$PROXY_GLOBALS.STB 1	Data structure definitions for TCP/IP proxy <code>execlet</code>
TCPIP\$PWIP_GLOBALS.STB 1	Data structure definitions for TCP/IP PWIP driver, and ACP data structures. Available only if TCP/IP has been installed.
TCPIP\$TN_GLOBALS.STB 1	Data structure definitions for TCP/IP TELNET/RLOGIN server driver data structures. Available only if TCP/IP has been installed.

The following table lists symbols that SDA defines automatically on initialization.

Table 2.6. SDA Symbols Defined on Initialization

ASN	Address space number
AST	Both the asynchronous system trap status and enable registers: <code>AST<3:0></code> = AST enable; <code>AST<7:4></code> = AST status
BR0 through BR7	Branch registers (Integrity servers only)
CYCLE_COUNTER	Process cycle counter
ESP	Executive stack pointer

EBSR	Executive register stack pointer (Integrity servers only)
FEN	Floating-point enable
FP	Frame pointer (R29)
FP0 through FP31	Floating-point registers (Alpha only)
FP0 through FP127	Floating point registers (Integrity servers only)
FPCR	Floating-point control register (Alpha only)
FPSR	Floating-point status register (Integrity servers only)
GP	Global pointer (R1) (Integrity servers only)
G	FFFFFFFF.80000000 16, the base address of system space
H	00000000.7FFE0000 16, a base address in P1 space
I	FFFFFFFF.FFFFFFFF 16, also fills the leading digits of a hexadecimal number with the value of F
KSP	Kernel stack pointer
KBSP	Kernel register stack pointer (Integrity servers only)
PAL_RSVD	PAL reserved area in process HWPCB
PC	Program counter
PCC	Process cycle counter
PS	Processor status
PTBR	Page table base register
R0 through R31	Integer registers (Alpha only)
R0 through R127	Integer registers (Integrity servers only)
SCC	System cycle counter
SP	Current stack pointer of a process
SSP	Supervisor stack pointer
SBSP	Supervisor register stack pointer (Integrity servers only)
SYSPTBR	Page table base register for system space
USP	User stack pointer
UBSP	User register stack pointer (Integrity servers only)
VIRBND	Virtual Address Boundary for RADs (Alpha only)

After a SET CPU command is issued (for analyzing a crash dump only), the symbols defined in the table below are set for that CPU.

Table 2.7. SDA Symbols Defined by SET CPU Command

CPUIDB	Address of CPU database
IPL	Interrupt priority level register

MCES	Machine check error summary register
PCBB	Process context block base register
PRBR	Processor base register (CPU database address)
RAD	Address of RAD database
SCBB	System control block base register
SISR	Software interrupt status register
VPTB	Virtual Page Table Base register

After a SET PROCESS command is issued, the symbols listed in the table below are defined for that process.

Table 2.8. SDA Symbols Defined by SET PROCESS Command

ARB	Address of access rights block
FRED	Address of floating-point register and execution data block
JIB	Address of job information block
KTB	Address of the kernel thread block
ORB	Address of object rights block
PCB	Address of process control block
PHD	Address of process header
PSB	Address of persona security block

Other SDA commands, such as SHOW DEVICE and SHOW CLUSTER, predefine additional symbols.

Symbols can include lowercase letters. Commands that manipulate symbols (such as DEFINE, SHOW SYMBOL, UNDEFINE) require these symbols to be enclosed within quotation marks ("*symbol*").

SDA Symbol Initialization

On initialization, SDA reads the universal symbols defined by SYSS\$BASE_IMAGE.EXE. For every procedure descriptor address symbol found, a routine address symbol is created (with `_C` appended to the symbol name).

SDA then reads the object file REQSYSDEF.STB. This file contains data structure definitions that are required for SDA to run correctly. It uses these symbols to access some of the data structures in the crash dump file or on the running system.

Finally, SDA initializes the process registers defined in Table 2.8 and executes a SET CPU command, defining the symbols as well.

Use of SDA Symbols

There are two major uses of the address type symbols. First, the EXAMINE command employs them to find the value of a known symbol. For example, EXAMINE CTL\$GL_PCB finds the PCB for the current process. Then, certain SDA commands (such as EXAMINE, SHOW STACK, and FORMAT) use them to symbolize addresses when generating output.

When the code for one of these commands needs a symbol for an address, it calls the SDA symbolize routine. The symbolize routine tries to find the symbol in the symbol table whose address is closest to, but not greater than the requested address. This means, for any given address, the routine may return a

symbol of the form `symbol_name+offset`. If, however, the offset is greater than `0FFF16`, it fails to find a symbol for the address.

As a last resort, the symbolize routine checks to see if this address falls within a known memory range. Currently, the only known memory ranges are those used by the OpenVMS executive images and those used by active images in a process. SDA searches through the executive loaded image list (LDRIMG data structure) and activated image list (IMCB data structures) to see if the address falls within any of the image sections. If SDA does find a match, it returns one of the following types of symbols:

```
@@@@executive_image_name+offset activated_image_name+offset
```

The offset is the same as the image offset as defined in the map file.

The constants in the SDA symbol table are usually used to display a data structure with the `FORMAT` command. For example, the PHD offsets are defined in `SYSDEF.STB`; you can display all the fields of the PHD by entering the following commands:

```
SDA> READ SDA$READ_DIR:SYSDEF.STB
```

```
SDA> FORMAT/TYPE=PHD phd_address
```

Symbols and Address Resolution

In OpenVMS, executive and user images are loaded into dynamically assigned address space. To help you associate a particular virtual address with the image whose code has been loaded at that address, SDA provides several features:

- The `SHOW EXECUTIVE` command
- The symbolization of addresses, described in the previous section
- The `READ` command
- The `SHOW PROCESS` command with the `/IMAGES` qualifier
- The `MAP` command

The OpenVMS executive consists of two base images, `SYS$BASE_IMAGE.EXE` and `SYS$PUBLIC_VECTORS.EXE`, and a number of other separately loadable images. Some of these images are loaded on all systems, while others support features unique to particular system configurations. Executive images are mapped into system space during system initialization.

By default, a typical executive image is not mapped at contiguous virtual addresses. Instead, its nonpageable image sections are loaded into a reserved set of pages with other executive images' nonpageable sections. The pageable sections of a typical executive image are mapped contiguously into a different part of system space. An image mapped in this manner is said to be **sliced**. A particular system may have system parameters defined that disable executive image slicing altogether.

Each executive image is described by a data structure called a **loadable image data block** (LDRIMG). The LDRIMG specifies whether the image has been sliced. If the image is sliced, the LDRIMG indicates the beginning of each image section and the size of each section. All the LDRIMGs are linked together in a list that SDA scans to determine what images have been loaded and into what addresses they have been mapped. The `SHOW EXECUTIVE` command displays a list of all images that are included in the OpenVMS executive.

Each executive image is a shareable image whose universal symbols are defined in the `SYS$BASE_IMAGE.EXE` symbol vector. On initialization, SDA reads this symbol vector and adds its universal symbols to the SDA symbol table.

Executive image .STB files define additional symbols within an executive image that are not defined as universal symbols and thus are not in the SYS\$BASE_IMAGE.EXE symbol vector (see *Sources for SDA Symbols Section 2.6.1.4 [26]* in this section). You can enter a READ/EXECUTIVE command to read symbols defined in all executive image .STB files into the SDA symbol table, or a READ/IMAGE filespec command to read the .STB for a specified image only.

To obtain a display of all images mapped within a process, execute a SHOW PROCESS/IMAGE command. See the description of the SHOW PROCESS command for additional information about displaying the hardware and software context of a process.

You can also identify the image name and offset that correspond to a specified address with the MAP command. With the information obtained from the MAP command, you can then examine the image map to locate the source module and program section offset corresponding to an address.

2.6.2. SDA Display Mode

Some SDA commands produce more output than will fit on one screen. In this situation, SDA enters **display mode**, and outputs the **screen overflow prompt** at the bottom of the screen:

```
Press RETURN for more.  
SDA>
```

If the RETURN key is pressed, SDA will continue the output of the command it was processing. If an EXIT command is entered, SDA will leave display mode, abort the command it was processing and output a regular SDA prompt. If any other command is entered, SDA will leave display mode, abort the command it was processing, and begin processing the new command.

SDA will leave display mode once a continued command completes.

2.7. Investigating System Failures

This section discusses how the operating system handles internal errors, and suggests procedures that can help you determine the causes of these errors. It illustrates, through detailed analysis of a sample system failure, how SDA helps you find the causes of operating system problems.

For a complete description of the commands discussed in the sections that follow, refer to Chapter 4 and Chapter 5 of this document, where all the SDA and CLUE commands are presented in alphabetical order.

2.7.1. Procedure for Analyzing System Failures

When the operating system detects an internal error so severe that normal operation cannot continue, it signals a condition known as a fatal bugcheck and shuts itself down. A specific bugcheck code describes each fatal bugcheck.

To resolve the problem, you must find the reason for the bugcheck. Many failures are caused by errors in user-written device drivers or other privileged code not supplied by VSI. To identify and correct these errors, you need a listing of the code in question.

Occasionally, a system failure is the result of a hardware failure or an error in code supplied by VSI. A hardware failure requires the attention of VSI Services. To diagnose an error in code supplied by VSI, you need listings of that code, which are available from VSI.

Start the search for the error by analyzing the CLUE list file that was created by default when the system failed. This file contains an overview of the system failure, which can assist you in finding the line of

code that signaled the bugcheck. CLUE CRASH displays the content of the program counter (PC) in the list file. The content of the PC is the address of the next instruction after the instruction that signaled the bugcheck.

However, some bugchecks are caused by unexpected exceptions. In such cases, the address of the instruction that *caused* the exception is more informative than the address of the instruction that signaled the bugcheck.

The address of the instruction that caused the exception is located on the stack. You can obtain this address either by using the SHOW STACK command to display the contents of the stack or by using the SHOW CRASH or CLUE CRASH command to display the system state at time of exception. See Section 2.7.2 for information on how to proceed for several types of bugchecks.

Once you have found the address of the instruction that caused the bugcheck or exception, find the module in which the failing instruction resides. Use the MAP command to determine whether the instruction is part of a device driver or another executive image. Alternatively, the SHOW EXECUTIVE command shows the location and size of each of the images that make up the OpenVMS executive.

If the instruction that caused the bugcheck is not part of a driver or executive image, examine the linker's map of the module or modules you are debugging to determine whether the instruction that caused the bugcheck is in your program.

To determine the general cause of the system failure, examine the code that signaled the bugcheck or the instruction that caused the exception.

2.7.2. Fatal Bugcheck Conditions

There are many possible conditions that can cause OpenVMS to issue a bugcheck. Normally, these occasions are rare. When they do occur, they are often fatal exceptions or illegal page faults occurring within privileged code. This section describes the symptoms of several common bugchecks. A discussion of other exceptions and condition handling in general appears in the *VSI OpenVMS Programming Concepts Manual*.

An exception is fatal when it occurs while either of the following conditions exists:

- The process is executing above IPL 2 (IPL\$_ASTDEL).
- The process is executing in a privileged (kernel or executive) processor access mode and has not declared a condition handler to deal with the exception.

When the system fails, the operating system reports the approximate cause of the system failure on the console terminal. SDA displays a similar message when you issue a SHOW CRASH command. For instance, for a fatal exception, SDA can display one of these messages:

```
FATALEXCPT, Fatal executive or kernel mode exception
```

```
INVEXCEPTN, Exception while above ASTDEL
```

```
SSRVEXCEPT, Unexpected system service exception
```

```
UNXSIGNAL, Unexpected signal name in ACP
```

When a FATALEXCPT, INVEXCEPTN, SSRVEXCEPT, or UNXSIGNAL bugcheck occurs, two argument lists, known as the mechanism and signal arrays, are placed on the stack.

Section 2.7.2.1 to Section 2.7.2.6 describe these arrays and related data structures, and Section 2.7.2.7 shows example output from SDA for an SSRVEXCEPT bugcheck.

A page fault is illegal when it occurs while the interrupt priority level (IPL) is greater than 2 (IPL $\$_ASTDEL$). When OpenVMS fails because of an illegal page fault, it displays the following message on the console terminal:


```
PGFIPLHI, Page fault with IPL too high
```

Section 2.7.2.8 describes the stack contents when an illegal page fault occurs.

2.7.2.1. Alpha Mechanism Array

The figure below illustrates the Alpha mechanism array, which is made up entirely of quadwords. The first quadword of this array indicates the number of quadwords in this array; this value is always 2C16. These quadwords are used by the procedures that search for a condition handler and report exceptions.

Figure 2.1. Alpha Mechanism Array



Symbolic offsets into the mechanism array are defined by using the SDA SHOW STACK command to identify the elements of the mechanism array on the stack using the symbols in the table below.

Table 2.9. Contents of the Alpha Mechanism Array

Offset	Meaning
CHF\$IS_MCH_ARGS	Number of quadwords that follow. In a mechanism array, this value is always 2C 16.

Offset	Meaning
CHF\$IS_MCH_FLAGS	Flag bits for related argument mechanism information.
CHF\$PH_MCH_FRAME	Address of the FP (frame pointer) of the establisher's call frame.
CHF\$IS_MCH_DEPTH	Depth of the OpenVMS search for a condition handler.
CHF\$PH_MCH_DADDR	Address of the handler data quadword, if the exception handler data field is present.
CHF\$PH_MCH_ESF_ADDR	Address of the exception stack frame (see Figure 2.5figure2-5).
CHF\$PH_MCH_SIG_ADDR	Address of the signal array (see Figure 2.3).
CHF\$IH_MCH_SAVRnn	Contents of the saved integer registers at the time of the exception. The following registers are saved: R0, R1, and R16 to R28 inclusive.
CHF\$FH_MCH_SAVFnn	If the process was using floating point, contents of the saved floating-point registers at the time of the exception. The following registers are saved: F0, F1, and F10 to F30 inclusive.
CHF\$PH_MCH_SIG64_ADDR	Address of the 64-bit signal array (see Figure 2.4).

2.7.2.2. Integrity server Mechanism Array

The figure below illustrates the Integrity server mechanism array, which is made up entirely of quadwords. The first quadword of this array indicates the number of quadwords in the array. This value is either 4916, if floating point registers F32 to F127 have not been saved, or 10916, if the floating point registers have been saved. These quadwords are used by the procedures that search for a condition handler and report exceptions.

Figure 2.2. Integrity server Mechanism Array

CHF\$IS_MCH_ARGS	:0
CHF\$IS_MCH_FLAGS	:4
CHF\$PH_MCH_FRAME	:8
CHF\$IG_MCH_DEPTH	:16
CHF\$IS_MCH_RESVD1	:20
CHF\$PH_MCH_DADDR	:24
CHF\$PH_MCH_ESF_ADDR	:32
CHF\$PH_MCH_SIG_ADDR	:40
CHF\$IH_MCH_RETVAL	:48
CHF\$IH_MCH_RETVAL2	:56
CHF\$PH_MCH_SIG64_ADDR	:64
CHF\$PH_MCH_SAVF32_SAVF127	:72
CHF\$FH_MCH_RETVAL_FLOAT	:80
CHF\$FH_MCH_RETVAL2_FLOAT	:96
CHF\$FH_MCH_SAVF2	:112
CHF\$FH_MCH_SAVF5	:120
CHF\$FH_MCH_SAVF12	:176
CHF\$FH_MCH_SAVF31	:184
CHF\$IH_MCH_SAVB1	:496
CHF\$IH_MCH_SAVB5	:528
CHF\$IH_MCH_AR_LC	:536
CHF\$IH_MCH_AR_EC	:544
CHF\$PH_MCH_OGSD	:552
CHF\$PH_MCH_INVO_HANDLE	:560
CHF\$PH_MCH_UWR_START	:568
CHF\$IH_MCH_FPSR	:576
CHF\$IH_MCH_FPSS	:584

Symbolic offsets into the mechanism array are defined by using the SDA SHOW STACK command to identify the elements of the mechanism array on the stack using the symbols in the table below.

Table 2.10. Contents of the Integrity server Argument Mechanism Array


Field Name	Contents
CHF\$IS_MCH_ARGS	Count of quadwords in this array starting from the next quadword, CHF\$PH_MCH_FRAME (not counting the first quadword that contains this longword). This value is 73 if CHF \$V_FPREGS2_VALID is clear, and 265 if CHF \$V_FPREGS2_VALID is set.
CHF\$IS_MCH_FLAGS	Flag bits for related argument-mechanism information.
CHF\$PH_MCH_FRAME	Contains the Previous Stack Pointer, PSP, (the value of the SP at procedure entry) for the procedure context of the establisher.

Field Name	Contents
CHF\$IS_MCH_DEPTH	Positive count of the number of procedure activation stack frames between the frame in which the exception occurred and the frame depth that established the handler being called.
CHF\$PH_MCH_DADDR	Address of the handler data quadword (start of the Language Specific Data area, LSDA), if the exception handler data field is present in the unwind information block (as indicated by OSSD \$V_HANDLER_DATA_VALID); otherwise, contains 0.
CHF\$PH_MCH_ESF_ADDR	Address of the exception stack frame.
CHF\$PH_MCH_SIG_ADDR	Address of the 32-bit form of signal array. This array is a 32-bit wide (longword) array. This is the same array that is passed to a handler as the signal argument vector.
CHF\$IH_MCH_RETVAL	Contains a copy of R8 at the time of the exception.
CHF\$IH_MCH_RETVAL2	Contains a copy of R9 at the time of the exception.
CHF\$PH_MCH_SIG64_ADDR	Address of the 64-bit form of signal array. This array is a 64-bit wide (quadword) array.
CHF\$FH_MCH_SAVF32_SAVF127	Address of the extension to the mechanism array that contains copies of F32 to F127 at the time of the exception.
CHF\$FH_MCH_RETVAL_FLOAT	Contains a copy of F8 at the time of the exception.
CHF\$FH_MCH_RETVAL2_FLOAT	Contains a copy of F9 at the time of the exception.
CHF\$FH_MCH_SAVFnn	Contain copies of floating-point registers F2 to F5 and F12 to F31. Registers F6, F7 and F10, F11 are implicitly saved in the exception frame.
CHF\$IH_MCH_SAVBnn	Contain copies of branch registers B1 to B5 at the time of the exception.
CHF\$IH_MCH_AR_LC	Contains a copy of the Loop Count Register (AR65) at the time of the exception.
CHF\$IH_MCH_AR_EC	Contains a copy of the Epilog Count Register (AR66) at the time of the exception.
CHF\$PH_MCH_OSSD	Address of the operating-system specific data area.
CHF\$PH_MCH_INVO_HANDLE	Contains the invocation handle of the procedure context of the establisher.
CHF\$PH_MCH_UWR_START	Address of the unwind region.
CHF\$IH_MCH_FPSR	Contains a copy of the hardware floating-point status register (AR.FPSR) at the time of the exception.
CHF\$IH_MCH_FPSS	Contains a copy of the software floating-point status register (which supplements CHF \$IH_MCH_FPSR) at the time of the exception.

2.7.2.3. Signal Array

The **signal array** appears somewhat further down the stack. This array comprises all longwords so that the structure is VAX compatible. A signal array describes the exception that occurred. It contains an argument count, the exception code, zero or more exception parameters, the PC, and the PS. Therefore, the size of a signal array can vary from exception to exception. Although there are several possible exception conditions, access violations are most common. the figure below shows the signal array for an access violation.

Figure 2.3. Signal Array



For access violations, the signal array is set up as follows:


Table 2.11.

Value	Meaning
Vector list length	Number of longwords that follow. For access violations, this value is always 5.
Condition value	Exception code. The value 0C 16 represents an access violation. You can identify the exception code by using the SDA command EVALUATE/CONDITION_VALUE or SHOW CRASH.
Additional arguments	<p>These can include a reason mask and a virtual address.</p> <p>In the longword mask if bit 0 of the longword is set, the failing instruction (at the PC saved below) caused a length violation. If bit 1 is set, it referred to a location whose page table entry is in a "no access" page. Bit 2 indicates the type of access used by the failing instruction: it is set for write and modify operations and clear for read operations.</p> <p>The virtual address represents the low-order 32 bits of the virtual address that the failing instruction tried to reference.</p>
PC	PC whose execution resulted in the exception.
PS	PS at the time of the exception.

2.7.2.4. 64-Bit Signal Array

The **64-bit signal array** also appears further down the stack. This array comprises all quadwords and is not VAX compatible. It contains the same data as the signal array, and Figure 2.4 shows the 64-bit signal array for an access violation. The SDA SHOW STACK command uses the CHF64\$ symbols listed in the figure to identify the 64-bit signal array on the stack.

Figure 2.4. 64-Bit Signal Array




For access violations, the 64-bit signal array is set up as follows:

Value	Meaning
Vector list length	Number of quadwords that follow. For access violations, this value is always 5.
Condition value	Exception code. The value 0C 16 represents an access violation. You can identify the exception code by using the SDA command EVALUATE/CONDITION_VALUE or SHOW CRASH.
Additional arguments	These can include a reason mask and a virtual address. In the quadword mask if bit 0 of the quadword is set, the failing instruction (at the PC saved below) caused a length violation. If bit 1 is set, it referred to a location whose page table entry is in a "no access" page. Bit 2 indicates the type of access used by the failing instruction: it is set for write and modify operations and clear for read operations.
PC	PC whose execution resulted in the exception.
PS	PS at the time of the exception.

2.7.2.5. Alpha Exception Stack Frame

The figure below illustrates the Alpha exception stack frame, which comprises all quadwords.

Figure 2.5. Alpha Exception Stack Frame

The values contained in the exception stack frame are defined as follows:

Table 2.12. Alpha Exception Stack Frame Values

Value	Contents
INTSTK\$Q_R2	Contents of R2 at the time of the exception
INTSTK\$Q_R3	Contents of R3 at the time of the exception
INTSTK\$Q_R4	Contents of R4 at the time of the exception
INTSTK\$Q_R5	Contents of R5 at the time of the exception
INTSTK\$Q_R6	Contents of R6 at the time of the exception
INTSTK\$Q_R7	Contents of R7 at the time of the exception
INTSTK\$Q_PC	PC whose execution resulted in the exception
INTSTK\$Q_PS	PS at the time of the exception (except high-order bits)

The SDA SHOW STACK command identifies the elements of the exception stack frame on the stack using these symbols.

2.7.2.6. Integrity server Exception Stack Frame

Two figures below illustrate the Integrity servers exception stack frame.

Figure 2.6. Integrity servers Exception Stack Frame





Figure 2.7. Integrity servers Exception Stack Frame (cont.)



The values contained in the exception stack frame are defined in the table below.

Table 2.13. Integrity servers Exception Stack Frame Values

Field	Use
INTSTK\$B_FLAGS	Indicates if certain registers have been saved.
INTSTK\$B_PPREVMODE	Save interrupted context's PREVMODE.
INTSTK\$B_PREVSTACK	Indicates which mode of stack (register and memory) we return to.
INTSTK\$B_IPL	SWIS IPL state
INTSTK\$L_STKALIGN	How much allocated on this stack for exception frame.
INTSTK\$W_NATMASK	Mask of bits 3-9 of the exception frame address.
INTSTK\$B_TYPE	Standard VMS structure type.
INTSTK\$B_SUBTYPE	Standard VMS structure subtype.
INTSTK\$L_TRAP_TYPE	Trap type.
INTSTK\$Q_IIP	Interruption Instruction Pointer (CR19).
INTSTK\$Q_RSC	Register Stack Control register.
INTSTK\$Q_BSP	Backing store pointer.
INTSTK\$Q_BSPSTORE	User BSP store pointer for next spill.
INTSTK\$Q_RNAT	RNAT register.
INTSTK\$Q_BSPBASE	Base of backing store for the inner mode.
INTSTK\$Q_PFS	Previous function state.
INTSTK\$Q_CONTEXT	Bookkeeping data for exception processing.
INTSTK\$Q_AST_F12 through INTSTK\$Q_AST_F15	F12 to F15 - temporary FP registers; sometimes saved by AST.
INTSTK\$Q_FPSR	Floating point status register.
INTSTK\$B_INTERRUPT_DEPTH	Interrupt depth.
INTSTK\$Q_PREDS	Predication registers.
INTSTK\$Q_IPSR	Interruption Processor Status (CR16).
INTSTK\$Q_ISR	Interruption Status Register (CR17).
INTSTK\$Q_CR18	Reserved control register.
INTSTK\$Q_IFA	Interruption Fault Address (CR20).
INTSTK\$Q_ITIR	Interruption TLB Insertion Register (CR21).
INTSTK\$Q_IIPA	Interruption immediate register (CR22).
INTSTK\$Q_IFS	Interruption Function State (CR23).
INTSTK\$Q_IIM	Interruption immediate (CR24).
INTSTK\$Q_IHA	Interruption Hash Address (CR25).
INTSTK\$Q_UNAT	User NAT collection register.
INTSTK\$Q_CCV	CCV register.
INTSTK\$Q_DCR	Default control register.

Field	Use
INTSTK\$Q_LC	Loop counter.
INTSTK\$Q_EC	Epilogue counter.
INTSTK\$Q_NATS	NATs for registers saved in this structure.
INTSTK\$Q_REGBASE	Used to index into registers.
INTSTK\$Q_GP	r1 - Used as global pointer.
INTSTK\$Q_R2	r2 - temporary register.
INTSTK\$Q_R3	r3 - temporary register.
INTSTK\$Q_R4 through R7	r4 through r7 - preserved registers (not saved by interrupt).
INTSTK\$Q_R8	r8 - return value.
INTSTK\$Q_R9	r9 - argument pointer.
INTSTK\$Q_R10	r10 - temporary register.
INTSTK\$Q_R11	r11 - temporary register.
INTSTK\$Q_SSD	For future use.
INTSTK\$Q_R13	r13 - Thread Pointer.
INTSTK\$Q_R14 through R31	r14 through r31 - temporary registers.
INTSTK\$Q_B0	Return pointer on kernel entry.
INTSTK\$Q_B1 through B5	b1 through b5 - Preserved branch registers (not saved by interrupt).
INTSTK\$Q_B6	b6 - temporary branch register.
INTSTK\$Q_B7	b7 - temporary branch register.
INTSTK\$L_IVT_OFFSET	Offset in IVT.
INTSTK\$Q_F6 through F11	f6 through f11 - temporary FP registers.

2.7.2.7. SSRVEXCEPT Example

If OpenVMS encounters a fatal exception, you can find the code that signaled it by examining the PC in the signal array. Use the `SHOW CRASH` or `CLUE CRASH` command to display the PC and the instruction stream around the PC to locate the exception.

The following display shows the SDA output in response to the `SHOW CRASH` and `SHOW STACK` commands for an Alpha `SSRVEXCEPT` bugcheck. It illustrates the mechanism array, signal arrays, and the exception stack frame previously described.

Example 2.1. SHOW CRASH

```
OpenVMS (TM) Alpha system dump analyzer
...analyzing a selective memory dump...

Dump taken on 30-AUG-2000 13:13:46.83
SSRVEXCEPT, Unexpected system service exception

SDA> SHOW CRASH
Time of system crash: 30-AUG-1996 13:13:46.83
```


Version of system: OpenVMS (TM) Alpha Operating System, Version V7.3

System Version Major ID/Minor ID: 3/0

System type: DEC 3000 Model 400

Crash CPU ID/Primary CPU ID: 00/00

Bitmask of CPUs active/available: 00000001/00000001

CPU bugcheck codes:

CPU 00 -- SSRVEXCEPT, Unexpected system service exception

System State at Time of Exception

 Exception Frame:

```

R2 = 00000000.00000003
R3 = FFFFFFFF.80C63460 EXCEPTION_MON_NPRW+06A60
R4 = FFFFFFFF.80D12740 PCB
R5 = 00000000.000000C8
R6 = 00000000.00030038
R7 = 00000000.7FFA1FC0
PC = 00000000.00030078
PS = 00000000.00000003
  
```

```

00000000.00030068: STQ R27, (SP)
00000000.0003006C: BIS R31, SP, FP
00000000.00030070: STQ R26, #X0010 (SP)
00000000.00030074: LDA R28, (R31)
PC => 00000000.00030078: LDL R28, (R28)
00000000.0003007C: BEQ R28, #X000007
00000000.00030080: LDQ R26, #XFFE8 (R27)
00000000.00030084: BIS R31, R26, R0
00000000.00030088: BIS R31, FP, SP
  
```

PS =>

```

MBZ SPAL MBZ IPL VMM MBZ CURMOD INT PRVMOD
0 00 000000000000 00 0 0 KERN 0 USER
  
```

Signal Array

```

-----
Length = 00000005
Type = 0000000C
Arg = 00000000.00010000
Arg = 00000000.00000000
Arg = 00000000.00030078
Arg = 00000000.00000003
%SYSTEM-F-ACCVIO, access violation, reason mask=00, virtual
address=0000000000000000,
PC=00000000000030078, PS=00000003
  
```

Saved Scratch Registers in Mechanism Array

```
R0 = 00000000.00020000 R1 = 00000000.00000000 R16 =
00000000.00020004
R17 = 00000000.00010050 R18 = FFFFFFFF.FFFFFFFF R19 =
00000000.00000000
R20 = 00000000.7FFA1F50 R21 = 00000000.00000000 R22 =
00000000.00010050
R23 = 00000000.00000000 R24 = 00000000.00010051 R25 =
00000000.00000000
R26 = FFFFFFFF.8010ACA4 R27 = 00000000.00010050 R28 =
00000000.00000000
```

CPU 00 Processor crash information

CPU 00 reason for Bugcheck: SSRVEXCEPT, Unexpected system service exception

Process currently executing on this CPU: SYSTEM

Current image file: \$31\$DKB0:[SYS0.][SYSMGR]X.EXE;1

Current IPL: 0 (decimal)

CPU database address: 80D0E000

CPUs Capabilities: PRIMARY, QUORUM, RUN

General registers:

```
R0 = 00000000.00000000 R1 = 00000000.7FFA1EB8 R2 =
FFFFFFFF.80D0E6C0
R3 = FFFFFFFF.80C63460 R4 = FFFFFFFF.80D12740 R5 =
00000000.000000C8
R6 = 00000000.00030038 R7 = 00000000.7FFA1FC0 R8 =
00000000.7FFAC208
R9 = 00000000.7FFAC410 R10 = 00000000.7FFAD238 R11 =
00000000.7FFCE3E0
R12 = 00000000.00000000 R13 = FFFFFFFF.80C6EB60 R14 =
00000000.00000000
R15 = 00000000.009A79FD R16 = 00000000.000003C4 R17 =
00000000.7FFA1D40
R18 = FFFFFFFF.80C05C38 R19 = 00000000.00000000 R20 =
00000000.7FFA1F50
R21 = 00000000.00000000 R22 = 00000000.00000001 R23 =
00000000.7FFF03C8
R24 = 00000000.7FFF0040 AI = 00000000.00000003 RA =
FFFFFFFF.82A21080
PV = FFFFFFFF.829CF010 R28 = FFFFFFFF.8004B6DC FP =
00000000.7FFA1CA0
PC = FFFFFFFF.82A210B4 PS = 18000000.00000000
```

Processor Internal Registers:

```

ASN = 00000000.0000002F          ASTSR/ASTEN =
0000000F
IPL =          00000000  PCBB = 00000000.003FE080  PRBR =
FFFFFFFF.80D0E000
PTBR = 00000000.00001136  SCBB = 00000000.000001DC  SISR =
00000000.00000000
VPTB = FFFFFFFC.00000000  FPCR = 00000000.00000000  MCES =
00000000.00000000

```

CPU 00 Processor crash information

```

KSP = 00000000.7FFA1C98
ESP = 00000000.7FFA6000
SSP = 00000000.7FFAC100
USP = 00000000.7AFFBAD0

```

No spinlocks currently owned by CPU 00

Example 2.2. SHOW STACK

SDA> SHOW STACK

Current Operating Stack (KERNEL):

```

00000000.7FFA1C78      18000000.00000000
00000000.7FFA1C80      00000000.7FFA1CA0
00000000.7FFA1C88      00000000.00000000
00000000.7FFA1C90      00000000.7FFA1D40
SP => 00000000.7FFA1C98      00000000.00000000
00000000.7FFA1CA0      FFFFFFFF.829CF010  EXE$EXCPTN
00000000.7FFA1CA8      FFFFFFFF.82A2059C
EXCEPTION_MON_PRO+0259C
00000000.7FFA1CB0      00000000.00000000
00000000.7FFA1CB8      00000000.7FFA1CD0
00000000.7FFA1CC0      FFFFFFFF.829CEDA8  EXE
$SET_PAGES_READ_ONLY+00948
00000000.7FFA1CC8      00000000.00000000
00000000.7FFA1CD0      FFFFFFFF.829CEDA8  EXE
$SET_PAGES_READ_ONLY+00948
00000000.7FFA1CD8      00000000.00000000
00000000.7FFA1CE0      FFFFFFFF.82A1E930  EXE
$CONTSIGNAL_C+001D0
00000000.7FFA1CE8      00000000.7FFA1F40
00000000.7FFA1CF0      FFFFFFFF.80C63780  EXE$ACVIOLAT
00000000.7FFA1CF8      00000000.7FFA1EB8
00000000.7FFA1D00      00000000.7FFA1D40
00000000.7FFA1D08      00000000.7FFA1F00
00000000.7FFA1D10      00000000.7FFA1F40
00000000.7FFA1D18      00000000.00000000
00000000.7FFA1D20      00000000.00000000
00000000.7FFA1D28      00000000.00020000  SYS
$K_VERSION_04
00000000.7FFA1D30      00000005.00000250  BUG
$_NETRCVPKT

```

Chapter 2. SDA Description

	00000000.7FFA1D38	829CE050.000008F8	BUG
\$_SEQ_NUM_OVF			
CHF\$IS_MCH_ARGS	00000000.7FFA1D40	00000000.0000002C	
CHF\$PH_MCH_FRAME	00000000.7FFA1D48	00000000.7AFFBAD0	
CHF\$IS_MCH_DEPTH	00000000.7FFA1D50	FFFFFFFF.FFFFFFFD	
CHF\$PH_MCH_DADDR	00000000.7FFA1D58	00000000.00000000	
CHF\$PH_MCH_ESF_ADDR	00000000.7FFA1D60	00000000.7FFA1F00	
CHF\$PH_MCH_SIG_ADDR	00000000.7FFA1D68	00000000.7FFA1EB8	
CHF\$IH_MCH_SAVR0	00000000.7FFA1D70	00000000.00020000	SYS
\$K_VERSION_04			
CHF\$IH_MCH_SAVR1	00000000.7FFA1D78	00000000.00000000	
CHF\$IH_MCH_SAVR16	00000000.7FFA1D80	00000000.00020004	UCB
\$M_LCL_VALID+00004			
CHF\$IH_MCH_SAVR17	00000000.7FFA1D88	00000000.00010050	SYS
\$K_VERSION_16+00010			
CHF\$IH_MCH_SAVR18	00000000.7FFA1D90	FFFFFFFF.FFFFFFFF	
CHF\$IH_MCH_SAVR19	00000000.7FFA1D98	00000000.00000000	
CHF\$IH_MCH_SAVR20	00000000.7FFA1DA0	00000000.7FFA1F50	
CHF\$IH_MCH_SAVR21	00000000.7FFA1DA8	00000000.00000000	
CHF\$IH_MCH_SAVR22	00000000.7FFA1DB0	00000000.00010050	SYS
\$K_VERSION_16+00010			
CHF\$IH_MCH_SAVR23	00000000.7FFA1DB8	00000000.00000000	
CHF\$IH_MCH_SAVR24	00000000.7FFA1DC0	00000000.00010051	SYS
\$K_VERSION_16+00011			
CHF\$IH_MCH_SAVR25	00000000.7FFA1DC8	00000000.00000000	
CHF\$IH_MCH_SAVR26	00000000.7FFA1DD0	FFFFFFFF.8010ACA4	AMAC
\$EMUL_CALL_NATIVE_C+000A4			
CHF\$IH_MCH_SAVR27	00000000.7FFA1DD8	00000000.00010050	SYS
\$K_VERSION_16+00010			
CHF\$IH_MCH_SAVR28	00000000.7FFA1DE0	00000000.00000000	
	00000000.7FFA1DE8	00000000.00000000	
	00000000.7FFA1DF0	00000000.00000000	
	00000000.7FFA1DF8	00000000.00000000	
	00000000.7FFA1E00	00000000.00000000	
	00000000.7FFA1E08	00000000.00000000	
	00000000.7FFA1E10	00000000.00000000	
	00000000.7FFA1E18	00000000.00000000	
	00000000.7FFA1E20	00000000.00000000	
	00000000.7FFA1E28	00000000.00000000	
	00000000.7FFA1E30	00000000.00000000	
	00000000.7FFA1E38	00000000.00000000	
	00000000.7FFA1E40	00000000.00000000	
	00000000.7FFA1E48	00000000.00000000	
	00000000.7FFA1E50	00000000.00000000	
	00000000.7FFA1E58	00000000.00000000	
	00000000.7FFA1E60	00000000.00000000	
	00000000.7FFA1E68	00000000.00000000	
	00000000.7FFA1E70	00000000.00000000	
	00000000.7FFA1E78	00000000.00000000	
	00000000.7FFA1E80	00000000.00000000	
	00000000.7FFA1E88	00000000.00000000	
	00000000.7FFA1E90	00000000.00000000	
	00000000.7FFA1E98	00000000.00000000	
CHF\$PH_MCH_SIG64_ADDR	00000000.7FFA1EA0	00000000.7FFA1ED0	
	00000000.7FFA1EA8	00000000.00000000	
	00000000.7FFA1EB0	00000000.7FFA1F50	
	00000000.7FFA1EB8	0000000C.00000005	

Chapter 2. SDA Description

\$K_VERSION_07	00000000.7FFA1EC0	00000000.00010000	SYS
	00000000.7FFA1EC8	00000003.00030078	SYS
\$K_VERSION_01+00078			
CHF\$L_SIG_ARGS	00000000.7FFA1ED0	00002604.00000005	UCB
\$M_TEMPLATE+00604			
CHF\$L_SIG_ARG1	00000000.7FFA1ED8	00000000.0000000C	
	00000000.7FFA1EE0	00000000.00010000	SYS
\$K_VERSION_07			
	00000000.7FFA1EE8	00000000.00000000	
	00000000.7FFA1EF0	00000000.00030078	SYS
\$K_VERSION_01+00078			
	00000000.7FFA1EF8	00000000.00000003	
INTSTK\$Q_R2	00000000.7FFA1F00	00000000.00000003	
INTSTK\$Q_R3	00000000.7FFA1F08	FFFFFFFF.80C63460	
EXCEPTION_MON_NPRW+06A60			
INTSTK\$Q_R4	00000000.7FFA1F10	FFFFFFFF.80D12740	PCB
INTSTK\$Q_R5	00000000.7FFA1F18	00000000.000000C8	
INTSTK\$Q_R6	00000000.7FFA1F20	00000000.00030038	SYS
\$K_VERSION_01+00038			
INTSTK\$Q_R7	00000000.7FFA1F28	00000000.7FFA1FC0	
INTSTK\$Q_PC	00000000.7FFA1F30	00000000.00030078	SYS
\$K_VERSION_01+00078			
INTSTK\$Q_PS	00000000.7FFA1F38	00000000.00000003	
Prev SP (7FFA1F40) ==>	00000000.7FFA1F40	00000000.00010050	SYS
\$K_VERSION_16+00010			
	00000000.7FFA1F48	00000000.00010000	SYS
\$K_VERSION_07			
	00000000.7FFA1F50	FFFFFFFF.8010ACA4	AMAC
\$EMUL_CALL_NATIVE_C+000A4			
	00000000.7FFA1F58	00000000.7FFA1F70	
	00000000.7FFA1F60	00000000.00000001	
	00000000.7FFA1F68	FFFFFFFF.800EE81C	RM_STD
\$DIRCACHE_BLKAST_C+005AC			
	00000000.7FFA1F70	FFFFFFFF.80C6EBA0	SCH\$CHSEP
+001E0			
	00000000.7FFA1F78	00000000.829CEDE8	EXE\$SIGTORET
	00000000.7FFA1F80	00010050.00000002	SYS
\$K_VERSION_16+00010			
	00000000.7FFA1F88	00000000.00020000	SYS
\$K_VERSION_04			
	00000000.7FFA1F90	00000000.00030000	SYS
\$K_VERSION_01			
	00000000.7FFA1F98	FFFFFFFF.800A4D64	
EXCEPTION_MON_NPRO+00D64			
	00000000.7FFA1FA0	00000000.00000003	
	00000000.7FFA1FA8	FFFFFFFF.80D12740	PCB
	00000000.7FFA1FB0	00000000.00010000	SYS
\$K_VERSION_07			
	00000000.7FFA1FB8	00000000.7AFFBAD0	
	00000000.7FFA1FC0	00000000.7FFCF880	MMG
\$IMGHDRBUF+00080			
	00000000.7FFA1FC8	00000000.7B0E9851	
	00000000.7FFA1FD0	00000000.7FFCF818	MMG
\$IMGHDRBUF+00018			
	00000000.7FFA1FD8	00000000.7FFCF938	MMG
\$IMGHDRBUF+00138			
	00000000.7FFA1FE0	00000000.7FFAC9F0	

```


00000000.7FFA1FE8      00000000.7FFAC9F0
00000000.7FFA1FF0      FFFFFFFF.80000140  SYS
$PUBLIC_VECTORS_NPRO+00140
00000000.7FFA1FF8      00000000.0000001B
.
.
.

```

2.7.2.8. Illegal Page Faults

When an illegal page fault occurs, the stack appears as pictured in the figure below.

Figure 2.8. Stack Following an Illegal Page-Fault Error



The stack contents are as follows:

MMG\$PAGEFAULT Stack Frame	Stack frame built at entry to MMG\$PAGEFAULT, the page fault exception service routine. On Alpha, the frame includes the contents of the following registers at the time of the page fault: R3, R8, R11 to R15, R29 (frame pointer)
SCH\$PAGEFAULT Saved Scratch Registers (Alpha only)	Contents of the following registers at the time of the page fault: R0, R1, R16 to R28
Exception Stack Frame	Exception stack frame ---see Figure 2.5, Figure 2.6 and Figure 2.7.
Previous Stack Content	Contents of the stack prior to the illegal page-fault error

When you analyze a dump caused by a PGFIPLHI bugcheck, the SHOW STACK command identifies the exception stack frame using the symbols shown in Table 2.12 or Table 2.13. The SHOW CRASH or CLUE CRASH command displays the instruction that caused the page fault and the instructions around it.

2.8. Page Protections and Access Rights

Page protections and access rights are different on Alpha and Integrity server systems. They are visible in output from the following commands:

- SHOW PAGE
- SHOW PROCESS/PAGE

- EXAMINE/PTE
- EVALUATE/PTE

Due to system differences, there is a need to distinguish "Write+Read+Execute" from "Write+Read" and to distinguish "Read+Execute" from "Read".

On an Alpha system, W=W+R+E and R=R+E but on an IA64 system, additional w and r indicators are introduced for non-execute cases.

On Alpha, page protection is described by 8 bits--- one Read bit for each mode, and one Write Bit. Therefore in the "Read" column, there might be KESU (read access in all modes) or K--- (read access in Kernel mode only) or NONE (no read access). Similarly in the "Writ" column. Not all combinations of the 8 bits are possible (for example, Write access for a mode implies Read access at that mode and both Read and Write access for all inner modes).

On Integrity servers, page protection is described by 5 bits, a combination of the Access Rights and Privilege Level fields. SDA interprets these with a single character to describe access in each mode, as shown in the table below.

Table 2.14. Integrity server Access Codes for Page Protections

Code	Meaning
r	Read
w	Read, Write
R	Read, Execute
W	Read, Write, Execute
X	Execute
K	Promote to Kernel
E	Promote to Executive
S	Promote to Supervisor
-	No access

For example WRRR means Kernel mode has Read+Write+Execute access; all other modes have Read+Execute access.

2.9. Inducing a System Failure

If the operating system is not performing well and you want to create a dump you can examine, you must induce a system failure. Occasionally, a device driver or other user-written, kernel-mode code can cause the system to execute a loop of code at a high priority, interfering with normal system operation. This loop can occur even though you have set a breakpoint in the code if the loop is encountered before the breakpoint. To gain control of the system in such circumstances, you must cause the system to fail and then reboot it.

If the system has suspended all noticeable activity and is hung, see the examples of causing system failures in Section 2.9.2.

If you are generating a system failure in response to a system hang, be sure to record the PC and PS as well as the contents of the integer registers at the time of the system halt.

2.9.1. Meeting Crash Dump Requirements

The following requirements must be met before the operating system can write a complete crash dump:

- You must not halt the system until the console dump messages have been printed in their entirety and the memory contents have been written to the crash dump file. Be sure to allow sufficient time for these events to take place or make sure that all disk activity has stopped before using the console to halt the system.
- There must be a crash dump file in `SYSS$SPECIFIC:[SYSEXE]`: named either `SYSDUMP.DMP` or `PAGEFILE.SYS`.

This dump file must be either large enough to hold the entire contents of memory (as discussed in Section 2.2.1.1) or, if the `DUMPSTYLE` system parameter is set, large enough to accommodate a subset or compressed dump (also discussed in Section 2.2.1.1).

If `SYSDUMP.DMP` is not present, the operating system attempts to write crash dumps to `PAGEFILE.SYS`. In this case, the `SAVEDUMP` system parameter must be 1 (the default is 0).

- Alternatively, the system must be set up for DOSD. See Section 2.2.1.5, and the *VSI OpenVMS System Manager's Manual, Volume 2: Tuning, Monitoring, and Complex Systems* for details.
- The `DUMPBUG` system parameter must be 1 (the default is 1).

2.9.2. Procedure for Causing a System Failure

This section tells you how to enter the XDelta utility (`XDELTA`) to force a system failure.

Before you can use XDelta, it must be loaded at system startup. To load XDelta during system bootstrap, you must set bit 1 in the boot flags. See the *VSI OpenVMS Version 8.4 Upgrade and Installation Manual* for information about booting with the XDelta utility.

On Alpha, put the system in console mode by pressing `Ctrl/P` or the Halt push button. Enter the following commands at the console prompt to enter XDelta:

```
>>> DEPOSIT SIRR E
>>> CONTINUE
```

On Integrity servers, enter XDelta by pressing `Ctrl/P` at the console.

Once you have entered XDelta, use any valid XDelta commands to examine register or memory locations, step through code, or force a system failure (by entering `;C` under XDelta). See the *VSI OpenVMS Delta/XDelta Debugger Manual* for more information about using XDelta.

On Alpha, if you did not load XDelta, you can force a system crash by entering console commands that make the system incur an exception at high IPL. At the console prompt, enter commands to set the program counter (PC) to an invalid address and the PS to kernel mode at IPL 31 before continuing. This results in a forced `INVEXCEPTN`-type bugcheck. Some VSI Alpha computers employ the console command `CRASH` (which will force a system failure) while other systems require that you manually enter the commands.

Enter the following commands at the console prompt to force a system failure:

```
>>> DEPOSIT PC FFFFFFFFFFFFFFFF00
>>> DEPOSIT PS 1F00
```


>>> CONTINUE

For more information, refer to the hardware manuals that accompanied your Alpha computer.

On Integrity servers, pressing Ctrl/P when XDelta is not loaded causes the OpenVMS system to output the following:

Crash (y/n) :

A response of Y forces a system crash; entering any other character lets the system continue processing.

Chapter 3. ANALYZE Usage

This chapter describes the format, usage, and qualifiers of the System Dump Analyzer (SDA) utility.


The System Dump Analyzer (SDA) utility helps determine the causes of system failures. This utility is also useful for examining the running system.

3.1. ANALYZE

ANALYZE

ANALYZE

Format



Parameters

collection-file-name

Name of the file that contains the file ID translation data or unwind data to be used by SDA.

device-name

The device containing the system dump.

filespec

Name of the file(s) that contain the dump you want to analyze.

If **filespec** is not specified in an ANALYZE/CRASH_DUMP command, the default is the highest version of SYS\$SYSTEM:SYSDUMP.DMP. If this file does not exist or cannot be opened, SDA prompts you for a file name. If any field of **filespec** is provided, the remaining fields default to the highest version of SYSDUMP.DMP in your default directory.

filespec can be a comma-separated list of files, including wildcards, where all the files contain Partial Dump Copies from the same original dump. See Section 2.2.3 for a description of Partial Dump Copies. The following restrictions apply when multiple files are specified:

- Files are opened in the order they are specified.

- The file that contains System Page Tables (section PT) must be the first file opened. This is the Primary dump file.
- If using a wildcard to specify file names, the primary dump file must be the first file to match the wildcard.
- The files specified must be part of the same original crash dump.
- If any section of the dump is found in multiple input files, SDA issues a warning, but continues.
- If the file or unwind data collection is in a separate file, it must have the same name and location as the primary dump file, with file type .COLLECT, or must be specified using the /COLLECTION qualifier.
- The files specified must either be all compressed or all uncompressed. They cannot be mixed.

You cannot specify **filespec** for ANALYZE/SYSTEM.

system-symbol-table

The system symbol table used by SDA.

Qualifiers

The /CRASH_DUMP and /SYSTEM qualifiers (described in this chapter) specify whether the object of an SDA session is a crash dump or a running system. Additional qualifiers used with these help to create the environment of an SDA session. The /SSLOG qualifier specifies that data be collected by the System Service Logging utility, which is documented in Chapter 14.

- /COLLECTION
- /LOG
- /CRASH_DUMP
- /OVERRIDE
- /RELEASE
- /SHADOW_MEMBER
- /SSLOG
- /SYMBOL
- /SYSTEM

The only additional qualifiers that can be used when invoking ANALYZE/SYSTEM are /LOG and /SYMBOL. See Chapter 14 for details of additional qualifiers that can be used when invoking ANALYZE/SSLOG. The following table shows which combinations of additional qualifiers can be used together when invoking ANALYZE/CRASH_DUMP:

	/OVERRIDE	/RELEASE	/SHADOW	/SYMBOL
--	-----------	----------	---------	---------

/COLLECTION	No	No	Yes	yes
/OVERRIDE	--	No	Yes	See note
/RELEASE	--	--	No	See note
/SHADOW	--	--	--	Yes

Note

/LOG can be used with any valid combination of qualifiers. /SYMBOL is ignored if it is specified with /OVERRIDE or /RELEASE.

The qualifiers are described on the following pages.

Description

By default, the System Dump Analyzer is automatically invoked when you reboot the system after a system failure.

To analyze a system dump interactively, invoke SDA by issuing the following command:

```
$ ANALYZE/CRASH_DUMP filespec
```

If you do not specify **filespec**, and SYS\$SYSTEM:SYSDUMP.DMP does not exist or cannot be opened, SDA prompts you for a file name.

To analyze a crash dump, your process must have the privileges necessary for reading the dump file. This usually requires system privilege (SYSPRV), but your system manager can, if necessary, allow less privileged processes to read the dump files. Your process needs change-mode-to-kernel (CMKRNL) privilege to release page file dump blocks, whether you use the /RELEASE qualifier or the SDA COPY command.

Invoke SDA to analyze a running system by issuing the following command:

```
$ANALYZE/SYSTEM
```

To examine a running system, your process must have change-mode-to-kernel (CMKRNL) privilege. Your process must also have the map-by-PFN privilege (PFNMAP) to access memory by physical address on a running system. You cannot specify **filespec** when using the /SYSTEM qualifier.

To send all output from SDA to a file, use the SDA command SET OUTPUT, specifying the name of the output file. The file produced is 132 columns wide and is formatted for output to a printer. To later redirect the output to your terminal, use the following command:

```
SDA> SET OUTPUT SYS$OUTPUT
```

To send a copy of all the commands you type and a copy of all the output those commands produce to a file, use the SDA command SET LOG, specifying the name of the log file. The file produced is 132 columns wide and is formatted for output to a printer.

To exit from SDA, use the EXIT command. Note that the EXIT command also causes SDA to exit from display mode. Thus, if SDA is in display mode, you must use the EXIT command twice: once to exit from display mode, and a second time to exit from SDA. See Section 2.6.2 for a description of display mode.

3.2. /COLLECTION

/COLLECTION

/COLLECTION — Valid for Alpha and Integrity server systems only. Indicates to SDA that the file ID translation data or unwind data is to be found in a separate file.

Format

/COLLECTION = collection-file-name

At least one field of the collection file name must be specified. Other fields default to the highest generation of the same filename and location as the dump file, with a file type of .COLLECT.

Description

SDA can provide additional information when analyzing a dump if a collection has been made of file identification translation data (on both Alpha and Integrity servers) and of unwind data (on Integrity servers only). This data is usually saved when the dump file is copied using the SDA COPY/COLLECT command, but it can be saved to a separate file using the COLLECT/SAVE command.

By default, COLLECT/SAVE creates a .COLLECT file with the same name and in the same directory as the dump file. A subsequent ANALYZE/CRASH_DUMP command automatically uses this file. If the collection file is in a different location or if the collection previously appended to the dump file is incomplete (for example, if a disk was not mounted at the time of the SDA COPY), you can use the /COLLECTION qualifier to specify an alternate collection file.

Example

```
$ ANALYZE/CRASH_DUMP SYS$SYSTEM:SYSDUMP.DMP
...
SDA> COLLECT/SAVE=SYS$LOGIN:NEWCOLL.COLLECT
SDA> EXIT
$ ANALYZE/CRASH_DUMP SYS$SYSTEM:SYSDUMP.DMP /COLLECTION=SYS$LOGIN:NEWCOLL
...
```

3.3. /CRASH_DUMP

/CRASH_DUMP

/CRASH_DUMP — Invokes SDA to analyze the specified dump file.

Format

/CRASH_DUMP [filespec]

Parameter

filespec

Name of the file that contains the dump you want to analyze. If no filespec is given on an ANALYZE/CRASH_DUMP command, the default is the highest version of SYS

`$$SYSTEM:SYSDUMP.DMP`. If this file does not exist, SDA prompts you for a file name. If any field of filespec is given, the remaining fields default to the highest version of `SYSDUMP.DMP` in your default directory.

Description

See Section 2.3 for additional information on crash dump analysis. You cannot specify the `/SYSTEM` qualifier when you include the `/CRASH_DUMP` qualifier in the `ANALYZE` command.

Examples

```
$ ANALYZE/CRASH_DUMP SYS$$SYSTEM:SYSDUMP.DMP
$ ANALYZE/CRASH SYS$$SYSTEM
```

These commands invoke SDA to analyze the crash dump stored in `SYS$$SYSTEM:SYSDUMP.DMP`.

```
$ ANALYZE/CRASH SYS$$SYSTEM:PAGEFILE.SYS
```

This command invokes SDA to analyze a crash dump stored in the system page file.

3.4. /LOG

/LOG

`/LOG` — Causes SDA to display the names of the files opened because SDA initializes itself.

Format

```
/LOG
```

Parameters

None.

Description

SDA displays the names of the files opened because SDA initializes itself. Note that this does not affect the behavior of commands within SDA such as `READ`, but only files opened when SDA is initialized.

`/LOG` can be used on `ANALYZE /CRASH_DUMP` and `ANALYZE /SYSTEM`.

Examples

```
$ ANALYZE/CRASH_DUMP /LOG T*
%SDA-I-OPENED, opened USER$:[SYSMGR]T1.DMP;1 as dump file #1
%SDA-I-OPENED, opened SYS$COMMON:[SYS$LDR]SYS$BASE_IMAGE.EXE;1 as symbol
file
%SDA-I-OPENED, opened USER$:[SYSMGR]T2.DMP;1 as dump file #2

OpenVMS system dump analyzer
...analyzing an I64 compressed selective memory dump...

%SDA-I-OPENED, opened SYS$COMMON:[SYS$LDR]REQSYSDEF.STB;1 as symbol file
Dump taken on 14-DEC-2009 17:16:31.35 using version XC6G-J2I
```

SSRVEXCEPT, Unexpected system service exception

\$ SDA>

This example shows the use of the /LOG qualifier to identify the set of files being used by SDA.

3.5. /OVERRIDE

/OVERRIDE

/OVERRIDE — When used with the /CRASH_DUMP qualifier, invokes SDA to analyze only the structure of the specified dump file when a corruption or other problem prevents normal invocation of SDA with the ANALYZE/CRASH_DUMP command.

Format

/CRASH_DUMP/OVERRIDE [filespec]

Parameter

filespec

Name of the crash dump file to be analyzed. The default file specification is:

`SYSDISK:[default-dir]SYSDUMP.DMP`

SYSDISK and [default-dir] represent the disk and directory specified in your last SET DEFAULT command. If you do not specify filespec, and SYSDISK:SYSDUMP.DMP does not exist or cannot be opened, SDA prompts you for it.

Description

See Section 2.3 for additional information on crash dump analysis. Note that when SDA is invoked with /OVERRIDE, not all the commands in Section 2.3 can be used. Commands that can be used are as follows:

- Output control commands such as SET OUTPUT and SET LOG
- Dump file related commands such as SHOW DUMP and CLUE ERRLOG

Commands that cannot be used are as follows:

- Commands that access memory addresses within the dump file such as EXAMINE and SHOW SUMMARY

Also, the /RELEASE qualifier cannot be used when you include the /OVERRIDE qualifier in the ANALYZE/CRASH_DUMP command.

When /OVERRIDE is used, the SDA command prompt is SDA>>.

Example

```
$ ANALYZE/CRASH_DUMP/OVERRIDE SYSDISK:SYSDUMP.DMP
```



```
$ ANALYZE/CRASH/OVERRIDE SYS$SYSTEM
```

These commands invoke SDA to analyze the crash dump stored in SYS\$SYSTEM:SYSDUMP.DMP.

3.6. /RELEASE

/RELEASE

/RELEASE — Invokes SDA to release those blocks in the specified system page file occupied by a crash dump. Requires CMKRNL (change-mode-to-kernel) privilege.

Format

```
/CRASH_DUMP/RELEASE filespec
```

Parameter

filespec

Name of the system page file (SYS\$SYSTEM:PAGEFILE.SYS). Because the default file specification is SYS\$DISK:[default-dir]SYSDUMP.DMP, you must identify the page file explicitly. SYS\$DISK and [default-dir] represent the disk and directory specified in your last DCL command SET DEFAULT.

If you do not specify **filespec**, and SYS\$SYSTEM:SYSDUMP.DMP does not exist or cannot be opened, SDA prompts you for it. Note that if you do not specify **filespec**, and SYS\$SYSTEM:SYSDUMP.DMP exists and can be opened, SDA will report an error because this is not the primary page file.

Description

Use the /RELEASE qualifier to release from the system page file those blocks occupied by a crash dump. When invoked with the /RELEASE qualifier, SDA immediately deletes the dump from the page file and allows no opportunity to analyze its contents.

When you specify the /RELEASE qualifier in the ANALYZE command, do the following:

1. Use the /CRASH_DUMP qualifier.
2. Include the name of the system page file (SYS\$SYSTEM:PAGEFILE.SYS) as the **filespec**.

If you do not specify the system page file or the specified page file does not contain a dump, SDA generates the following messages:

```
%SDA-E-BLKSNRLSD, no dump blocks in page file to release, or not page file
%SDA-E-NOTPAGFIL, specified file is not the page file
```

You cannot specify the /OVERRIDE or /SHADOW_MEMBER qualifier when you include the /RELEASE qualifier in the ANALYZE/CRASH_DUMP command.

Example

```
$ ANALYZE/CRASH_DUMP/RELEASE SYS$SYSTEM:PAGEFILE.SYS
```

```
$ ANALYZE/CRASH/RELEASE PAGEFILE.SYS
```

These commands invoke SDA to release to the page file those blocks in SYSSYSTEM:PAGEFILE.SYS occupied by a crash dump.

3.7. /SHADOW_MEMBER

/SHADOW_MEMBER

/SHADOW_MEMBER — Valid for Alpha and Integrity server systems only. Specifies which member of a shadow set contains the system dump to be analyzed, or allows the user to determine what system dumps have been written to the members of the shadow set.

Format

```
/CRASH_DUMP/SHADOW_MEMBER [filespec]
```

Description

If the system disk is a shadow set, a system dump is written to only one member of the shadow set (usually the master member at the time the dump is written). By default, if the filespec translates to a file on a shadow set, SDA reads the dump only from the master member. If at analysis time, the master member is different from where the dump was written, the /SHADOW_MEMBER qualifier allows the user to choose the member from which the dump is to be read.

If the correct member is not known, the /SHADOW_MEMBER qualifier may be specified without a device name. SDA will display a one-line summary of the most recent dump written to each member and then prompt the user to determine which member to use. The prompt is:

```
Shadow set action?
```

The possible responses are:

Command	Effect
EXIT	Aborts the SDA session without analyzing a dump.
HELP	Displays simple help text. See Example 3 below.
USE <device_name>	Initiates analysis of the system dump located on the specified shadow set member.

The one-line summary for each member consists of the following fields:

- Member device name
- Bugcheck name
- Date and time of system crash
- Node name
- VMS Version
- Flags—none, one or more of: Bad_Checksum, ErrorLog_Dump, Not_Saved, Old_Dump

If there is no usable dump on a member, SDA output will an explanatory warning message followed by a line giving the member device name and the message "No system or error log dump found."

Note that SDA cannot distinguish a dump on a shadowed system disk from a dump copied to a shadowed data disk. SDA will therefore always read the dump from a single member of a host-based shadow set. (In an OpenVMS Cluster system with multiple shadowed system disks, one system's system disk will be a data disk on other systems.) This does not affect dumps being read directly from a DOSD disk, since DOSD disks cannot be members of a host-based shadow set.

Note

The /SHADOW_MEMBER qualifier is not useful if the system dump has been written to the primary page file on a shadowed system disk. You cannot specify /RELEASE with /SHADOW_MEMBER.

Examples

```
1. $ ANALYZE/CRASH_DUMP DSA777:[SYS0.SYSEXEXE]SYSDUMP.DMP
   %SDA-I-USEMASTER, accessing dump file via _$31$DKB200:, master member of
   shadow set _DSA777:
   OpenVMS (TM) Alpha system dump analyzer
   ...analyzing a compressed selective memory dump...
   Dump taken on 12-DEC-2001 08:23:07.80
   SSRVEXCEPT, Unexpected system service exception
   SDA>
```

This command initiates dump analysis using the master member of the shadow set DSA777 (the default action).

```
2. $ ANALYZE/CRASH_DUMP/SHADOW_MEMBER=DKB0 DSA777:[SYS0.SYSEXEXE]SYSDUMP.DMP
   OpenVMS (TM) Alpha system dump analyzer
   ...analyzing a compressed selective memory dump...

   Dump taken on 12-DEC-2001 08:23:07.80
   SSRVEXCEPT, Unexpected system service exception

   SDA>
```

This command initiates dump analysis using member device \$31\$DKB0 of the shadow set DSA777.

```
3. $ ANALYZE/CRASH_DUMP/SHADOW_MEMBER DSA8888:[SYS1.SYSEXEXE]SYSDUMP.DMP
   _$70$DKA303:      INVEXCEPTN      16-NOV-2001 00:00:25.74 MRVP2
   X96S-FT1
   _$70$DKA202:      INCONSTATE        18-NOV-2001 02:08:45.05 MRVP2
   X96S-FT1

   Shadow set action? HELP

   Shadow set actions:

           EXIT                exit SDA
           HELP                this display
           USE <shadow_set_member> proceed using specified shadow set
           member

   Shadow set action? USE _$70$DKA303:
```

```
OpenVMS (TM) Alpha system dump analyzer
...analyzing a compressed selective memory dump...

%SDA-W-NOTSAVED, global pages not saved in the dump file
Dump taken on 16-NOV-2001 00:00:25.74
INVEXCEPTN, Exception while above ASTDEL

SDA> EXIT
```

This command displays the dumps to be found on the members of shadow set DSA8888: [SYS1.SYSEXEXE]SYSDUMP.DMP and then begins analysis of the dump written to device _\$70\$DKA303.

3.8. /SSLOG

/SSLOG

/SSLOG — Displays data collected by the System Service Logging Utility (SSLOG). For more information about this and associated commands, see Chapter 14, System Service Logging.

Format

```
/SSLOG
```

3.9. /SYMBOL

/SYMBOL

/SYMBOL — Specifies an alternate system symbol table for SDA to use.

Format

```
/SYMBOL = system-symbol-table
```

File specification of the OpenVMS Alpha SDA system symbol table required by SDA to analyze a system dump or running system. The specified **system-symbol-table** must contain those symbols required by SDA to find certain locations in the executive image.

If you do not specify the /SYMBOL qualifier, SDA uses SDA\$READ_DIR:SYS\$BASE_IMAGE.EXE to load system symbols into the SDA symbol table. When you specify the /SYMBOL qualifier, SDA assumes the default disk and directory to be SYS\$DISK:[], that is, the disk and directory specified in your last DCL command SET DEFAULT. If you specify a file for this parameter that is not a system symbol table, SDA exits with a fatal error.

Description

The /SYMBOL qualifier allows you to specify a system symbol table to load into the SDA symbol table. You can use the /SYMBOL qualifier whether you are analyzing a system dump or a running system. It is not normally necessary to use the /SYMBOL qualifier when analyzing the running system, since the default SYS\$BASE_IMAGE.EXE is the one in use in the system. However if SDA\$READ_DIR has been redefined during crash dump analysis, then the /SYMBOL qualifier can be used to ensure that the correct base image is found when analyzing the running system.

The `/SYMBOL` qualifier can be used with the `/CRASH_DUMP` and `/SYSTEM` qualifiers. It is ignored when `/OVERRIDE` or `/RELEASE` is specified.

Example

```
$ ANALYZE/CRASH_DUMP/SYMBOL=SDA$READ_DIR:SYS$BASE_IMAGE.EXE SYS$SYSTEM
```

This command invokes SDA to analyze the crash dump stored in `SYS$SYSTEM:SYSDUMP.DMP`, using the base image in `SDA$READ_DIR`.

3.10. /SYSTEM

/SYSTEM

`/SYSTEM` — Invokes SDA to analyze a running system. Requires `CMKRNL` (change-mode-to-kernel) privilege. Also requires `PFNMAP` (map-by-PFN) privilege to access memory by physical address.

Format

```
/SYSTEM
```

Parameters

None.

Description

See Section 2.4 for information on how to use SDA to analyze a running system. See Chapter 4 for information on SDA commands.

The only other qualifiers you can specify with `/SYSTEM` are `/LOG` and `/SYMBOL`.

Example

```
$ ANALYZE/SYSTEM
```

```
OpenVMS (TM) system analyzer
```

```
SDA>
```

This command invokes SDA to analyze the running system.

Chapter 4. SDA Commands

This chapter describes the SDA commands that you can use to analyze a system dump or a running system. SDA extension commands, such as CLUE and FLT are described in separate chapters.

4.1. @(Execute Command)

Causes SDA to execute SDA commands contained in a file. Use this command to execute a set of frequently used SDA commands.

Format

`@filespec`

Parameter

`filespec`

Name of a file that contains the SDA commands to be executed. The default file type is .COM.

Example

```
SDA> @USUAL
```

The execute (@) command executes the following commands, as contained in a file named USUAL.COM:

```
SET OUTPUT LASTCRASH.LIS
SHOW CRASH
SHOW PROCESS
SHOW STACK
SHOW SUMMARY
```

This command procedure first makes the file LASTCRASH.LIS the destination for output generated by subsequent SDA commands. Next, the command procedure sends information to the file about the system failure and its context, including a description of the process executing at the time of the failure, the contents of the stack on which the failure occurred, and a list of the processes active on the system.

An EXIT command within a command procedure terminates the procedure at that point, as would an end-of-file.

Command procedures cannot be nested.

4.2. ATTACH

Switches control of your terminal from your current process to another process in your job (for example, one created with the SDA SPAWN command).

Format

`ATTACH [/PARENT] process-name`

Parameter

process-name

Name of the process to which you want to transfer control.

Qualifier

/PARENT

Transfers control of the terminal to the parent process of the current process. When you specify this qualifier, you cannot specify the process-name parameter.

Examples

```
SDA> ATTACH/PARENT
```

This ATTACH command attaches the terminal to the parent process of the current process.

```
SDA> ATTACH DUMPER
```

This ATTACH command attaches the terminal to a process named DUMPER in the same job as the current process.

4.3. COLLECT

Collect file identification to file name translation data on both OpenVMS Alpha and OpenVMS for Integrity servers, and process unwind data only on OpenVMS for Integrity servers.

Format

```
COLLECT [qualifiers]
```

Parameters

None.

Qualifiers

/LOG

Displays information on the progress of the COLLECT command, for example, the name of the process being scanned, or (on Integrity servers) the name of an image whose unwind data is being collected.

/SAVE [= file name]

Writes collection data to a separate file. By default, a file of type .COLLECT with the same name as the dump file will be created in the same directory as the dump file.

/UNDO

Removes all the file or unwind data from an earlier COLLECT command from SDA's memory. COLLECT/UNDO does not affect the file or unwind data already appended to the dump file being analyzed, or already written to a separate collection file.

Description

When a dump is being analyzed, it is useful to have data available that cannot be written to the dump file at the time of the system crash. This data includes the full file specification associated with a file identification. On OpenVMS for Integrity servers, it also includes the unwind data for images activated in processes.

If the dump is being analyzed on the system where it was originally written, this data can be collected for use in the current SDA session using the COLLECT command. If the dump is being copied for analysis elsewhere, the COPY/COLLECT command may be used to collect the data and append it to the copy being written. If the COPY/COLLECT command is used after a COLLECT command, the data already collected is appended to the dump copy.

For all file or unwind data to be collected successfully, all disks that were mounted at the time of the system crash should be remounted and accessible to the process running SDA.

If the COPY and the COLLECT cannot be done as a single step, a COLLECT/SAVE command writes the collection to a separate file that can be used later with the dump file. A later COPY will combine the two files.

Example

```
SDA> COLLECT
%SDA-W-DISKNOACC, no access to _$30$DKB100: for file and/or unwind data
%SDA-W-FILENOACC, no access to _$30$DKB0:(7709,1,0) for unwind data
-SYSTEM-W-NOSUCHFILE, no such file
```

In this example, the disk \$30\$DKB100, which was mounted at the time the system crashed, is not available when file and/or unwind data is being collected. In addition, unwind data cannot be collected for the image with file identification (7709,1,0) on _\$30\$DKB0: since it no longer exists.

4.4. COPY

Copies the contents of the dump file to another file.

Format

```
COPY [/qualifier...] output-filespec
```

Parameter

output-filespec

Name of the device, directory, and file to which SDA copies the dump file. The default file specification is:

```
SYS$DISK:[default-dir]filename.DMP
```

SYS\$DISK and [default-dir] represent the disk and directory specified in your last DCL command SET DEFAULT. You must specify a file name.

Qualifiers

/COLLECT

/NOCOLLECT

Causes SDA to collect (or not collect) file identification or unwind data from the current system and append it to the copy being created. For more details, see the Description section.

/COMPRESS

Causes SDA to compress dump data as it is writing a copy. If the dump being analyzed is already compressed, then SDA does a direct COPY, and issues an informational message indicating that it is ignoring the /COMPRESS qualifier.

/CONFIRM

Causes SDA to prompt for which processes to copy when performing a Partial Dump Copy. This qualifier can only be used when /PARTIAL=PROCESS=option is specified. For each possible process in the set, SDA prompts as follows, where the default response is No and only a single character response is needed otherwise:

Copy process "process-name"? (Y/[N]/A/Q) :

Where the response:

YES Includes the process in the copy.
 NO Excludes the process from the copy.
 ALL Includes the process and all remaining processes in the copy.
 QUIT Excludes the process and all remaining processes from the copy.

/DECOMPRESS

Causes SDA to decompress dump data as it is writing a copy. If the dump being analyzed is already decompressed, then SDA does a direct COPY, and issues an informational message indicating that it is ignoring the /DECOMPRESS qualifier.

/LOG

Displays information about the progress of the COPY command, for example, the name of the process being copied in a selective dump, or, in the case of COPY/COLLECT on Integrity servers, the name of an image whose unwind data is being appended to the dump copy.

/PARTIAL=(section,...)

Causes SDA to copy only the specified sections of the dump. The /PARTIAL qualifier can only be used with a selective system dump (compressed or uncompressed). It is not available for full system dumps or for process dumps. Also, the /PARTIAL qualifier cannot be combined with /COMPRESS, /DECOMPRESS, or /[NO]COLLECT. Such a copy must be performed as two separate COPY commands, and requires exiting from SDA and then re-invoking SDA on the intermediate copy.

See Section 2.2.3 for a description of Partial Dump Copies. For an explanation of key processes and key global pages, and the organization of a selective system dump, see the *VSI OpenVMS System Manager's Manual, Volume 2: Tuning, Monitoring, and Complex Systems*.

Multiple sections must be separated by commas. If only one section is given, the parentheses may be omitted. Possible sections are as follows:

PT	System Page Table Space
SOS1	32-bit System Space

S2	64-bit System Space	
REPLICATED_SYS	Replicated System Space (only applies to Alpha systems with RADs enabled)	
PROCESS=option	Process Space for one or more processes. Options are:	
	ALL	All processes. This is the default.
	KEY	All key processes.
	OTHER	All other (not key) processes.
GLOBAL=option	Global Pages. Options are:	
	ALL	All global pages mapped by processes. This is the default.
	KEY	All global pages mapped by key processes.
	OTHER	All other (not key) global pages mapped by processes.
KEY	Equivalent to: PT, S0S1, S2, REPLICATED_SYS, PROCESS = KEY, GLOBAL = KEY	
OTHER	Equivalent to: PROCESS = OTHER, GLOBAL = OTHER	
SYSTEM	Equivalent to: PT, S0S1, S2, REPLICATED_SYS	

Note

If /PARTIAL=PROCESS=NAME=(list) is specified:

- Multiple process names must be separated by commas. If only one process name is given, the parentheses may be omitted.
- Process names can include "%" and "*" wildcards.
- The comparison of the given name to actual process names in the dump is performed case-blind, and trailing spaces and tabs are ignored.
- Process names can include characters, such as "," and "/". You can enclose the process name in quotes to include some of these special characters in the name you specify, or you can use the "%" wildcard instead of characters.

Description

Each time the system fails, the contents of memory and the hardware context of the current process (as directed by the DUMPSTYLE parameter) are copied into the file SYS\$SYSTEM:SYSDUMP.DMP (or the page file), overwriting its contents. If you do not save this crash dump elsewhere, it will be overwritten the next time that the system fails.

The COPY command allows you to preserve a crash dump by copying its contents to another file. It is generally useful to invoke SDA during system initialization to execute the COPY command. This ensures that a copy of the dump file is made only after the system has failed. The preferred method for doing this, using the logical name CLUE\$SITE_PROC, is described in Section 2.2.4.

The COPY command does not affect the contents of the file containing the dump being analyzed.

If you are using the page file (SYS\$SYSTEM:PAGEFILE.SYS) as the dump file instead of SYSDUMP.DMP, successful completion of the COPY command will automatically cause the blocks of the page file containing the dump to be released, thus making them available for paging. Even if the copy operation succeeds, the release operation requires that your process have change-mode-to-kernel (CMKRNL) privilege. When the dump pages have been released from the page file, the dump information in these pages will be lost and SDA will immediately exit. You must perform subsequent analysis upon the copy of the dump created by the COPY command.

If you press Ctrl/T while using the COPY command, the system displays how much of the file has been copied.

When a dump is being analyzed, it is useful to have data available that cannot be written to the dump file at the time of the system crash. This data includes the full file specification associated with a file identification, and, on OpenVMS Integrity servers, the unwind data for images activated in processes.

If the dump is being analyzed on the system where it was originally written, this data can be collected for use in the current SDA session using the COLLECT command. If the dump is being copied for analysis elsewhere, the COPY/COLLECT command can be used to collect the data and append it to the copy being written. If the COPY/COLLECT command is used after a COLLECT command, the data already collected is appended to the dump copy.

By default, a copy of the original dump, as written at the time of the system crash, includes collection. You can use COPY/NOCOLLECT to override this default. Conversely, a copy of a dump previously copied by SDA without collection (COPY/NOCOLLECT) does not include collection. You can use COPY/COLLECT to override this setting.

When you copy a dump that already contains an appended collection, the copy will always include that collection.

For all file and unwind data to be collected successfully, all disks that were mounted at the time of the system crash should be remounted and be accessible to the process running SDA. If SDA is invoked early in the startup procedure to save the contents of the dump (for example, using CLUE\$SITE_PROC as described in Section 2.2.4), but disks are not mounted until a batch job is run, you should use the COPY/NOCOLLECT command in the CLUE\$SITE_PROC command procedure. Once all disks are mounted, you can use a COPY/COLLECT command to save file or unwind data.

If the COPY and the COLLECT procedures cannot be done as a single step, you can execute a COLLECT/SAVE command to write the collection to a separate file that can be used later in conjunction with the dump file. A later COPY operation can combine the two files.

Example

```
SDA> COPY SYS$CRASH:SAVEDUMP
```

The COPY command copies the dump file into the file SYS\$CRASH:SAVEDUMP.DMP.

4.5. DEFINE

Assigns a value to a symbol.

Format

```
DEFINE [/qualifier...] symbol-name [=] expression
```

Parameters

symbol-name

Name, containing from 1 to 31 alphanumeric characters, that identifies the symbol. Symbols that include lowercase letters must be enclosed in quotation marks ("symbol"). See Section 2.6.1.4 for a description of SDA symbol syntax and a list of default symbols.

expression

Definition of the symbol's value. See Section 2.6.1 for a discussion of the components of SDA expressions.

Qualifier

/FD

/PD

Defines a symbol as a function descriptor (FD) or procedure descriptor (PD). It also defines the routine address symbol corresponding to the defined symbol (the routine address symbol has the same name as the defined symbol, only with `_C` appended to the symbol name). See Section 2.6.1.4 for more information about symbols. `/FD` and `/PD` are completely interchangeable. SDA interprets them based on the architecture of the system or dump being analyzed.

Description

The `DEFINE` command causes SDA to evaluate an expression and then assign its value to a symbol. Both the `DEFINE` and `EVALUATE` commands perform computations to evaluate expressions. `DEFINE` adds symbols to the SDA symbol table but does not display the results of the computation. `EVALUATE` displays the result of the computation but does not add symbols to the SDA symbol table.

Examples

```
SDA> DEFINE BEGIN = 80058E00
SDA> DEFINE END = 80058E60
SDA> EXAMINE BEGIN:END
```

In this example, `DEFINE` defines two addresses, called `BEGIN` and `END`. These symbols serve as reference points in memory, defining a range of memory locations for the `EXAMINE` command to inspect.

```
SDA> DEFINE NEXT = @PC
SDA> EXAMINE/INSTRUCTION NEXT
NEXT:   HALT
```

The symbol `NEXT` defines the address contained in the program counter, so that the symbol can be used in an `EXAMINE/INSTRUCTION` command.

```
SDA> DEFINE VEC SCH$GL_PCBVEC
SDA> EXAMINE VEC
SCH$GL_PCBVEC:  00000000.8060F2CC  "İð`....."
SDA>
```

After the value of global symbol SCH\$GL_PCBVEC has been assigned to the symbol VEC, the symbol VEC is used to examine the memory location or value represented by the global symbol.

```
SDA> DEFINE/PD VEC SCH$QAST
SDA> EXAMINE VEC
SCH$QAST: 0000002C.00003008 ".0.,..."
SDA> EXAMINE VEC_C
SCH$QAST_C: B75E0008.43C8153E ">.ÈC..^."
SDA>
```

In this example, the DEFINE/PD command defines not only the symbol VEC, but also the corresponding routine address symbol (VEC_C).

4.6. DEFINE/KEY

Associates an SDA command with a terminal key. Once you have associated a command with a key, you can just press the defined key, followed by the Return key to issue the command. If you specify the /TERMINATE qualifier when you define the key, you do not have to press the Return key to issue the command.

Format

DEFINE/KEY [/qualifier...] **key-name** **command**

Parameters

key-name

Name of the key to be defined. You can define the following keys under SDA:

Key Name	Key Designation
PF1	LK201, VT100
PF2	LK201, VT100
PF3	LK201, VT100
PF4	LK201, VT100
KP0...KP9	Keypad 0--9
PERIOD	Keypad period
COMMA	Keypad comma
MINUS	Keypad minus
ENTER	Keypad ENTER
UP	Up arrow
DOWN	Down arrow
LEFT	Left arrow
RIGHT	Right arrow
E1	LK201 Find
E2	LK201 Insert Here
E3	LK201 Remove

Key Name	Key Designation
E4	LK201 Select
E5	LK201 Prev Screen
E6	LK201 Next Screen
HELP	LK201 Help
DO	LK201 Do
F7...F20	LK201 Function keys

command

SDA command to define a key. You must enclose the command in quotation marks (" ").

Qualifiers**/IF_STATE=state_list****/NOIF_STATE**

Specifies a list of one or more states, one of which must be in effect for the key definition to work. The /NOIF_STATE qualifier has the same meaning as /IF_STATE=current_state. The state name is an alphanumeric string. States are established with the /SET_STATE qualifier. If you specify only one state name, you can omit the parentheses. By including several state names, you can define a key to have the same function in all the specified states.

/LOCK_STATE**/NOLOCK_STATE**

Specifies that the state set by the /SET_STATE qualifier remains in effect until explicitly changed. By default, the /SET_STATE qualifier is in effect only for the next definable key you press or the next read-terminating character that you type. You can specify this qualifier only with the /SET_STATE qualifier.

The default is /NOLOCK_STATE.

/SET_STATE=state-name**/NOSET_STATE**

Causes the key being defined to create a key state change instead of or in addition to issuing an SDA command. When you use the /SET_STATE qualifier, you supply the name of a key state to be used with the /IF_STATE qualifier in other key definitions.

For example, you can define the PF1 key as the GOLD key and use the /IF_STATE=GOLD qualifier to allow two definitions for the other keys, one in the GOLD state and one in the non-GOLD state. For more information on using the /IF_STATE qualifier, see the DEFINE/KEY command in the *VSI OpenVMS DCL Dictionary* or online help.

The default is /NOSET_STATE.

/TERMINATE

/NOTERMINATE

Causes the key definition to include termination of the command, which causes SDA to execute the command when the defined key is pressed. Therefore, you do not have to press the Return key after you press the defined key if you specify the /TERMINATE qualifier.

Description

The DEFINE/KEY command causes an SDA command to be associated with the specified key, in accordance with any of the specified qualifiers described previously.

If the symbol or key is already defined, SDA replaces the old definition with the new one. Symbols and keys remain defined until you exit from SDA.

Examples

```
SDA> DEFINE/KEY PF1 "SHOW STACK"
SDA> [PF1] SHOW STACK [RETURN]
Process stacks (on CPU 00)
-----
Current operating stack (KERNEL):
.
```

The DEFINE/KEY command defines PF1 as the SHOW STACK command. When you press the PF1 key, SDA displays the command and waits for you to press the Return key.

```
SDA> DEFINE/KEY/TERMINATE PF1 "SHOW STACK"
SDA> [PF1] SHOW STACK
Process stacks (on CPU 00)
-----
Current operating stack (KERNEL):
00000000.7FF95D00 00000000.00000000
00000000.7FF95D08 FFFFFFFF.804395C8 MMG$TBI_DATA_64+000B8
00000000.7FF95D10 00000000.00000000
00000000.7FF95D18 0000FE00.00007E04
SP => 00000000.7FF95D20 00000000.00000800 IRP$M_EXTEND
00000000.7FF95D28 00000001.000002F7 UCB$B_PI_FKB+0000B
00000000.7FF95D30 FFFFFFFF.804395C8 MMG$TBI_DATA_64+000B8
00000000.7FF95D38 00000002.00000000
.
```

The DEFINE/KEY command defines PF1 as the SDA SHOW STACK command. The /TERMINATE qualifier causes SDA to execute the SHOW STACK command without waiting for you to press the Return key.

```
SDA> DEFINE/KEY/SET_STATE="GREEN" PF1 ""
SDA> DEFINE/KEY/TERMINATE/IF_STATE=GREEN PF3 "SHOW STACK"
SDA> [PF1] [PF3] SHOW STACK
Process stacks (on CPU 00)
-----
Current operating stack (KERNEL):
.
```


The first DEFINE/KEY command defines PF1 as a key that sets a command state GREEN. The trailing pair of quotation marks is required syntax, indicating that no command is to be executed when this key is pressed.

The second DEFINE command defines PF3 as the SHOW STACK command, but using the /IF_STATE qualifier makes the definition valid only when the command state is GREEN. Thus, you must press PF1 before pressing PF3 to issue the SHOW STACK command. The /TERMINATE qualifier causes the command to execute as soon as you press the PF3 key.

4.7. DUMP

Displays the contents of a range of memory formatted as a comma-separated variable (CSV) list, suitable for inclusion in a spreadsheet.

Format

DUMP range

```
[/BYTE | /WORD | /LONGWORD (default) | /QUADWORD]
[/DECIMAL | /HEXADECIMAL (default)]
[/FORWARD (default) | /REVERSE]
[/RECORD_SIZE=size ] (default = 512)
[/INDEX_ARRAY [= {LONGWORD (default) | QUADWORD} ] ]
[/INITIAL_POSITION = {ADDRESS=address | RECORD=number } ]
[/COUNT = {ALL | records } ] (default = all records)
[/PHYSICAL]
[/BYTE | /WORD | /NOSUPPRESS]
```

Parameter

range

The range of locations to be displayed. The range is specified in one of the following formats:

<i>m:n</i>	Range from address <i>m</i> to address <i>n</i> inclusive
<i>m;n</i>	Range from address <i>m</i> for <i>n</i> bytes

The length of the range must be an exact multiple of the data item size --- or of the index array size if /INDEX_ARRAY is specified.

Qualifiers

/BYTE

Outputs each data item as a byte.

/COUNT = [{ALL | records}]

Gives the number of records to be displayed. The default is to display all records.

/DECIMAL

Outputs data as decimal values.

/FORWARD

Causes SDA to display the records in the history buffer in ascending address order. This is the default.

/HEXADECIMAL

Outputs data as hexadecimal values. This is the default.

/INDEX_ARRAY [= {LONGWORD (default) | QUADWORD}]

Indicates to SDA that the range of addresses given is a vector of pointers to the records to be displayed. The vector can be a list of longwords (default) or quadwords. The size of the range must be an exact number of longwords or quadwords as appropriate.

/INITIAL_POSITION = {ADDRESS=address | RECORD=number}

Indicates to SDA which record is to be displayed first. The default is the lowest addressed record if /FORWARD is used, and the highest addressed record if /REVERSE is used. The initial position may be given as a record number within the range, or the address at which the record is located.

/LONGWORD

Outputs each data item as a longword. This is the default.

/NOSUPPRESS

Indicates that SDA should not suppress leading zeroes when displaying data in hexadecimal format.

/PHYSICAL

Indicates to SDA that all addresses (range and/or start position) are physical addresses. By default, virtual addresses are assumed.

/QUADWORD

Outputs each data item as a quadword.

/RECORD_SIZE=*size*

Indicates the size of each record within the history buffer, the default being 512 bytes. This size must exactly divide into the total size of the address range to be displayed, unless you specify /INDEX_ARRAY. If no record size is given, and the length of the range is not more than 512 bytes, a single record is output containing the range specified, with no record number field. The length of the range must be an exact multiple of the data item size --- or of the index array size if /INDEX_ARRAY is specified.

/REVERSE

Causes SDA to display the records in the history buffer in descending address order.

/WORD

Outputs each data item as a word.

Description

The DUMP command displays the contents of a range of memory formatted as a comma-separated variable (CSV) list, suitable for inclusion in a spreadsheet. It is intended for use with a history buffer containing records of information of which the most recently written entry is in the middle of the memory range.

Note

See SET OUTPUT/NOHEADER for related information.

Examples

1. SDA> DUMP dump g;200/initial_position=record=5/record_size=20/reverse
05,A77B0010,A79B0008,6B9C4001,47FF041F,A03E0000,47DF041C,201F0016,083
04,A03E0000,47DF041C,201F0058,083,A77B0010,A79B0008,6B9C4001,47FF041F
03,A03E0000,47DF041C,201F0075,083,A03E0000,47DF041C,201F001B,083
02,A77B0010,A79B0008,6B9C4001,47FF041F,A03E0000,47DF041C,201F0074,083
01,43E05120,083,6BFA8001,47FF041F,A77B0010,A79B0008,6B9C4001,47FF041F
0,201F0104,6BFA8001,47FF041F,47FF041F,201F0001,6BFA8001,47FF041F,47FF041F
0F,A03E0000,47DF041C,201F0065,083,A03E0000,47DF041C,201F0006,083
0E,A03E0000,47DF041C,201F001C,083,A03E0000,47DF041C,201F001A,083
0D,A03E0000,47DF041C,201F0077,083,A03E0000,47DF041C,201F0057,083
0C,A03E0000,47DF041C,201F002B,083,A03E0000,47DF041C,201F003A,083
0B,A03E0000,47DF041C,201F007D,083,A77B0010,A79B0008,6B9C4001,47FF041F
0A,A03E0000,47DF041C,201F005A,083,A03E0000,47DF041C,201F0078,083
09,A03E0000,47DF041C,201F0002,082,A03E0000,47DF041C,201F0037,083
08,A03E0000,47DF041C,201F0035,083,A03E0000,47DF041C,201F007A,083
07,A03E0000,47DF041C,201F0019,083,A03E0000,47DF041C,201F0034,083
06,A77B0010,A79B0008,6B9C4001,47FF041F,A03E0000,47DF041C,201F0018,083

This example shows the dump of an area of memory treated as 16 records of 32 bytes each, beginning at record 5, and dumped in reverse order. Note the record number in the first field, and that the dump wraps to the end of the memory area after the first record has been output.

2. SDA> EXAMINE SMP\$GL_CPU_DATA;80
00000000 00000000 8FE26000 8FE14000 00000000 00000000 8FE02000 811FE000
...
00000000 00000000 00000000 00000000 00000000 00000000 00000000 00000000
...
00000000 00000000 00000000 00000000 00000000 00000000 00000000 00000000
...
00000000 00000000 00000000 00000000 00000000 00000000 00000000 00000000
...
SDA> DUMP SMP\$GL_CPU_DATA;80/index_array/record_size=20/count=5
0,810C17C0,8EC7C180,026A09C0,02,0,FFFFFFFF,0,0
01,810C17C0,8EC7C400,026A09C0,02,0,FFFFFFFF,0,01
04,810C17C0,8EC7CB80,026A09C0,02,0,FFFFFFFF,0,04

This example shows the contents of the CPU database vector, then dumps the first 32 bytes of each CPU database entry. Only the first five entries in the array are requested, and those containing zero are ignored.

4.8. EVALUATE

Computes and displays the value of the specified expression in both hexadecimal and decimal. Alternative evaluations of the expression are available with the use of the qualifiers defined for this command.

Format

```
EVALUATE [ {/CONDITION_VALUE | /FPSR | /IFS  
| /ISR | /PFS | /PS | /PSR  
| /PTE  
| /[NO]SYMBOLS [=filter] | /TIME}] expression
```

Parameter

expression

SDA expression to be evaluated. Section 2.6.1 describes the components of SDA expressions.

Qualifiers

/CONDITION_VALUE

Displays the message that the \$GETMSG system service obtains for the value of the expression.

/FPSR

(Integrity servers only) Evaluates the specified expression in the format of a floating-point status register.

/IFS

(Integrity servers only) Evaluates the specified expression in the format of an interruption function state.

/ISR

(Integrity servers only) Evaluates the specified expression in the format of an interruption status register.

/PFS

(Integrity servers only) Evaluates the specified expression in the format of a previous function state.

/PS

Evaluates the specified expression in the format of a processor status

/PSR

(Integrity servers only) Evaluates the specified expression in the format of a processor status register.

/PTE

Interprets and displays the expression as a page table entry (PTE). The individual fields of the PTE are separated and an overall description of the PTE's type is provided.

/SYMBOLS[=filter]**/NOSYMBOLS**

The default behavior of the EVALUATE command is to display up to five symbols that are known to be equal to the evaluated expression. If /SYMBOLS is specified with no filter, all symbols are listed in alphabetical order. If /NOSYMBOLS is specified, only the hexadecimal and decimal values are displayed. If /SYMBOLS is specified with a filter, only symbols that match the filter are displayed. The filter is a string containing wildcards, such as PCB\$*.

/TIME

Interprets and displays the expression as a 64-bit time value. Positive values are interpreted as absolute time; negative values are interpreted as delta time.

Description

If you do not specify a qualifier, the EVALUATE command interprets and displays the expression as hexadecimal and decimal values. In addition, if the expression is equal to the value of a symbol in the SDA symbol table, that symbol is displayed. If no symbol with this value is known, the next lower valued symbol is displayed with an appropriate offset unless the offset is extremely large. (See Section 2.6.1.4 for a description of how SDA displays symbols and offsets.) The DEFINE command adds symbols to the SDA symbol table but does not display the results of the computation. EVALUATE displays the result of the computation but does not add symbols to the SDA symbol table.

Examples

1. SDA> EVALUATE -1
Hex = FFFFFFFF.FFFFFFFF Decimal = -1 I

The EVALUATE command evaluates a numeric expression, displays the value of that expression in hexadecimal and decimal notation, and displays a symbol that has been defined to have an equivalent value.

2. SDA> EVALUATE 1
Hex = 00000000.00000001 Decimal = 1 CHF\$M_CALEXT_CANCEL
CHF\$M_FPREGS_VALID
CHF\$V_CALEXT_LAST
IRP\$M_BUFIO
IRP\$M_CLN_READY
|
(remaining symbols suppressed by default)

The EVALUATE command evaluates a numeric expression and displays the value of that expression in hexadecimal and decimal notation. This example also shows the symbols that have the displayed value. A maximum of five symbols are displayed by default.

3. SDA> DEFINE TEN = A
SDA> EVALUATE TEN
Hex = 00000000.0000000A Decimal = 10 IRP\$B_TYPE

```

IRP$$_FMOD
IRP$_V_MBXIO
TEN
UCB$_B_TYPE
|

```

(remaining symbols suppressed by default)

This example shows the definition of a symbol named TEN. The EVALUATE command then shows the value of the symbol.

Note that A, the value assigned to the symbol by the DEFINE command, could be a symbol. When SDA evaluates a string that can be either a symbol or a hexadecimal numeral, it first searches its symbol table for a definition of the symbol. If SDA finds no definition for the string, it evaluates the string as a hexadecimal number.

4. SDA> EVALUATE (((TEN * 6) + (-1/4)) + 6)
Hex = 00000000.00000042 Decimal = 66

This example shows how SDA evaluates an expression of several terms, including symbols and rational fractions. SDA evaluates the symbol, substitutes its value in the expression, and then evaluates the expression. The fraction -1/4 is truncated to 0.

5. SDA> EVALUATE/CONDITION 80000018
%SYSTEM-W-EXQUOTA, exceeded quota

This example shows the output of an EVALUATE/CONDITION command.

6. SDA> EVALUATE/PFS 00000000.000013AF
- | | PPL | PEC | RRB.PR | RRB.FR | RRB.GR | SOR | SOL |
|-----|---------|-----|--------|--------|--------|-----|-------------|
| SOF | 0 | 0. | 0. | 0. | 0. | 0. | 39. (32-70) |
| 47. | (32-78) | | | | | | |

This example shows the output of an EVALUATE/PFS command on an Integrity server system.

7. SDA> EVALUATE/PS 0B03
- | MBZ | SPAL | MBZ | IPL | VMM | MBZ | CURMOD | INT | PRVMOD |
|-----|------|--------------|-----|-----|-----|--------|-----|--------|
| 0 | 00 | 000000000000 | 0B | 0 | 0 | KERN | 0 | USER |

In this EVALUATE/PS command on an Alpha system, SDA interprets the entered value 0B03 as though it were a processor status (PS) and displays the resulting field values.

8. SDA> EVALUATE/PSR 00001410.0A026010
- | RT | TB | LP | DB | SI | DI | PP | SP | DFH | DFL | DT | PK | I | IC | MFH | MFL |
|----|----|----|----|----|----|----|----|-----|-----|----|-----|---|----|-----|-----|
| AC | BE | | | | | | | | | | | | | | |
| 1 | 0 | 1 | 0 | 0 | 0 | 0 | 0 | 0 | 0 | 1 | 0 | 1 | 1 | 0 | 1 |
| 0 | 0 | | | | | | | | | | | | | | |
| IA | BN | ED | RI | SS | DD | DA | ID | IT | MC | IS | CPL | | | | |
| 0 | 1 | 0 | 2 | 0 | 0 | 0 | 0 | 1 | 0 | 0 | 0 | | | | |

This example shows the output of an EVALUATE/PSR command on an Integrity server system.

9. SDA> EVALUATE/PTE 0BCDFEED
- | 3 | 3 | 2 | 2 | | 2 | 1 | 1 | 1 | 1 | | | | | | |
|---|---|---|---|------|-----|---|---|---|----|--|---|---|---|---|---|
| 1 | 0 | 9 | 7 | | 0 | 9 | 8 | 6 | 5 | | 7 | 6 | 4 | 3 | 0 |
| +--+---+-----+--+---+--+-----+--+---+--+-----+--+ | | | | | | | | | | | | | | | |
| 0 0 | 0 | | | 005E | 0 1 | 2 | 1 | | FF | | 1 | 3 | 0 | 7 | 0 |
| +--+---+-----+--+---+--+-----+--+---+--+-----+--+ | | | | | | | | | | | | | | | |

```

|                               00000000                               |
+-----+
Global PTE:  Owner = S, Read Prot = KESU, Write Prot = KESU, CPY = 0
             GPT Index = 00000000

```

The EVALUATE/PTE command displays the expression 0BCDFFEE as a page table entry (PTE) and labels the fields. It also describes the status of the page. For more information on interpreting information in this output, see Section 2.8.

```

10. SDA> EVALUATE/TIME 009A9A4C.843DBA9F
10-OCT-1996 15:59:44.02

```

This example shows the use of the EVALUATE/TIME command.

```

11. SDA> EVALUATE 2F0/SYMBOL=PCB*
Hex = 00000000.000002F0   Decimal = 752           PCB$L_INITIAL_KTB
                                           PCB$L_PCB

```

This example shows the use of the symbol filter. Only those symbols whose value is 2F0 and whose names begin with PCB are displayed.

4.9. EXAMINE

Displays either the contents of a location or of a range of locations in physical memory, or the contents of a register. Use location parameters to display specific locations or use qualifiers to display the entire process and system regions of memory.

Format

```

EXAMINE [location [/PHYSICAL] | /ALL | /P0 | /P1 | /SYSTEM]
[/CONDITION_VALUE | /FPSR | /IFS | /ISR | /PFS
| /PS | /PSL | /PSR | /PTE | /TIME | /[[NO]FD | /[[NO]PD]
[/NOSUPPRESS]
[/INSTRUCTION]

```

Parameter

location

Location in memory to be examined. A location can be represented by any valid SDA expression. (See Section 2.6.1 for additional information about expressions.) To examine a range of locations, use the following syntax:

<i>m:n</i>	Range of locations to be examined, from <i>m</i> to <i>n</i>
<i>m;n</i>	Range of locations to be examined, starting at <i>m</i> and continuing for <i>n</i> bytes

The default location that SDA uses is initially 0 in the program region (P0) of the process that was executing at the time the system failed (if you are examining a crash dump) or your process (if you are examining the running system). Subsequent uses of the EXAMINE command with no parameter specified increase the last address examined by eight. Use of the /INSTRUCTION qualifier increases

the default address by four (for Alpha) or 16 (for Integrity server). To examine memory locations of other processes, you must use the `SET PROCESS` command.

Qualifiers

/ALL

Examines all the locations in the program, and control regions and system space, displaying the contents of memory in hexadecimal longwords and ASCII characters. Do not specify parameters when you use this qualifier.

/CONDITION_VALUE

Examines the specified longword, displaying the message that the `$GETMSG` system service obtains for the value in the longword.

/FD

/NOFD

See the description of `/PD`.

/FPSR

(Integrity servers only) Examines the specified expression in the format of a floating-point status register.

/IFS

(Integrity servers only) Examines the specified expression in the format of an interruption function state.

/INSTRUCTION

Translates the specified range of memory locations into assembly instruction format. Each symbol in the `EXAMINE` expression that is defined as a procedure descriptor is replaced with the code entry point address of that procedure, unless you also specify the `/NOPD` qualifier. For Integrity servers only, SDA always displays entire bundles of instructions, not individual slots.

/ISR

(Integrity servers only) Examines the specified expression in the format of an interruption status register.

/NOSUPPRESS

Inhibits the suppression of zeros when displaying memory with one of the following qualifiers: `/ALL`, `/P0`, `/P1`, `/SYSTEM`, or when a range is specified.

/P0

Displays the entire program region for the default process. Do not specify parameters when you use this qualifier.

/P1

Displays the entire control region for the default process. Do not specify parameters when you use this qualifier.

/PD**/NOPD**

Functionally equivalent to /FD and /NOFD.

Causes the EXAMINE command to treat the location specified in the EXAMINE command as a function descriptor (FD) or procedure descriptor (PD), depending on the architecture of the system or dump being analyzed. /PD can also be used to qualify symbols.

You can use the /PD and /NOPD qualifiers with the /INSTRUCTION qualifier to override treating symbols as function or procedure descriptors. Placing the qualifier right after a symbol overrides how the symbol is treated. /PD forces it to be a procedure descriptor, and /NOPD forces it to not be a procedure descriptor.

If you place the /PD qualifier right after the /INSTRUCTION qualifier, SDA treats the calculated value as a function or procedure descriptor. /NOPD has the opposite effect.

In the following examples, TEST_ROUTINE is a PD symbol. Its value is 500 and the code address in this procedure descriptor is 1000. The first example displays instructions starting at 520.

```
EXAMINE/INSTRUCTION TEST_ROUTINE/NOPD+20
```

The next example fetches code address from TEST_ROUTINE PD, adds 20 and displays instructions at that address. In other words, it displays code starting at location 1020.

```
EXAMINE/INSTRUCTION TEST_ROUTINE+20
```

The final example treats the address TEST_ROUTINE+20 as a procedure descriptor, so it fetches the code address out of a procedure descriptor at address 520. It then uses that address to display instructions.

```
EXAMINE/INSTRUCTION/PD TEST_ROUTINE/NOPD+20
```

/PFS

(Integrity servers only) Examines the specified expression in the format of a previous function state.

/PHYSICAL

Examines physical addresses. You cannot use the /PHYSICAL qualifier in combination with the /P0, /P1, or /SYSTEM qualifiers.

/PS**/PSL**

Examines the specified quadword, displaying its contents in the format of a processor status. This qualifier must precede any parameters used in the command line.

/PSR

(Integrity servers only) Examines the specified expression in the format of a processor status register.

/PTE

Interprets and displays the specified quadword as a page table entry (PTE). The display separates individual fields of the PTE and provides an overall description of the PTE's type.

/SYSTEM

Displays portions of the writable system region. Do not specify parameters when you use this qualifier.

/TIME

Examines the specified quadword, displaying its contents in the format of a system-date-and-time quadword.

Description

The following sections describe how to use the EXAMINE command.

Examining Locations

When you use the EXAMINE command to look at a location, SDA displays the location in symbolic notation (symbolic name plus offset), if possible, and its contents in hexadecimal and ASCII formats:

```
SDA> EXAMINE G6605C0
806605C0:  64646464.64646464  "ddddddd"
```

If the ASCII character that corresponds to the value contained in a byte is not printable, SDA displays a period (.). If the specified location does not exist in memory, SDA displays this message:

```
%SDA-E-NOTINPHYS, address : virtual data not in physical memory
```

To examine a range of locations, you can designate starting and ending locations separated by a colon. For example:

```
SDA> EXAMINE G40:G200
```

Alternatively, you can specify a location and a length, in bytes, separated by a semicolon. For example:

```
SDA> EXAMINE G400;16
```

When used to display the contents of a range of locations, the EXAMINE command displays six or ten columns of information. Ten columns are used if the terminal width is 132 or greater, or if a SET OUTPUT has been entered; six columns are used otherwise. An explanation of the columns is as follows:

- Each of the first four or eight columns represents a longword of memory, the contents of which are displayed in hexadecimal format.
- The fifth or ninth column lists the ASCII value of each byte in each longword displayed in the previous four or eight columns.
- The sixth or tenth column contains the address of the first, or rightmost, longword in each line. This address is also the address of the first, or leftmost, character in the ASCII representation of the longwords. Thus, you read the hexadecimal dump display from right to left, and the ASCII display from left to right.

If a series of virtual addresses does not exist in physical memory, SDA displays a message specifying the range of addresses that were not translated.

If a range of virtual locations contains only zeros, SDA displays this message:

```
Zeros suppressed from 'loc1' to 'loc2'
```

Decoding Locations

You can translate the contents of memory locations into instruction format by using the `/INSTRUCTION` qualifier. This qualifier causes SDA to display the location in symbolic notation (if possible) and its contents in instruction format. The operands of decoded instructions are also displayed in symbolic notation. The location must be longword aligned (for Alpha) or octaword aligned (for Integrity servers).

Examining Memory Regions

You can display an entire region of virtual memory by using one or more of the qualifiers `/ALL`, `/SYSTEM`, `/P0`, and `/P1` with the `EXAMINE` command.

Other Uses

Other uses of the `EXAMINE` command appear in the following examples.

Note

When examining individual locations, addresses are usually symbolized, as described previously. If the `SET SYMBOLIZE OFF` command is issued, addresses are not symbolized. See the `SET SYMBOLIZE` command for further details.

Examples

```
1. SDA> EXAMINE/PFS 7FF43C10
      PPL   PEC   RRB.PR   RRB.FR   RRB.GR   SOR   SOL
SOF
      0     0.    0.      0.      0.      0.    23. (32-54)
31. (32-62)
```

This example shows the display produced by the `EXAMINE/PFS` command. Headings refer to previous privilege level (PPL), previous epilog count (PEC), Register Rename Base (RRB) for Predicate (PR), Floating (FR), and General (GR) Registers, Size of Rotating (SOR) or Local (SOL) portion of the stack frame or Size of the Stack Frame (SOF). For more information, see the *Intel IA-64 Architecture Software Developer's Manual*.

```
2. SDA> EXAMINE/PS 7FF95E78
      MBZ SPAL      MBZ   IPL VMM MBZ CURMOD INT PRVMOD
      0  00  000000000000 08  0  0  KERN  0  EXEC
```

This example shows the display produced by the `EXAMINE/PS` command.

```
3. SDA> EXAMINE/PSR 7FF43C78
      RT  TB  LP  DB  SI  DI  PP  SP  DFH DFL DT  PK  I  IC  MFH MFL
AC  BE
      1  0  1  0  0  0  0  0  1  0  1  0  1  1  0  1
0  0
      IA  BN  ED  RI  SS  DD  DA  ID  IT  MC  IS  CPL
      0  1  0  1  0  0  0  0  1  0  0  0
```

This example shows the display produced by the `EXAMINE/PSR` command

```
4. SDA> EXAMINE/PTE @^QMMG$GQ_L1_BASE
      3 3 2  2          2 1 1  1 1
      1 0 9  7          0 9 8  6 5          7 6  4 3  0
      +--+---+-----+--+---+-----+--+---+-----+--+
```

```

|0|1| 0 |      0000   |0|0| 0 |0|      11      |0| 0 |0|  4 |1|
+---+---+-----+---+---+---+-----+---+---+---+---+
|                                     00007090                                     |
+-----+
Valid PTE: Owner = K, Read Prot = K---, Write Prot = K---
          Fault on = -E--, ASM = 00, Granularity Hint = 00 (8KB)
          CPY = 00, PFN = 00007090

```

The EXAMINE/PTE command displays and formats the level 1 page table entry at FFFFFEFD.BF6FC000. For more information on interpreting this display, see Section 2.8.

- SDA> EXAMINE/CONDITION_VALUE R0
%SYSTEM-F-NOPRIV, insufficient privilege or object protection violation

This example shows the text associated with the condition code in R0.

- SDA> EXAMINE/TIME EXE\$GQ_SYSTIME
12-DEC-2001 08:23:07.80

This example displays the current system as an ASCII absolute time.

4.10. EXIT

Exits from an SDA display or exits from the SDA utility.

Format

EXIT

Parameters

None.

Qualifiers

None.

Description

If SDA is displaying information on a video display terminal---and if that information extends beyond one screen---SDA enters display mode and displays a **screen overflow prompt** at the bottom of the screen:

```

Press RETURN for more.
SDA>

```

If you want to discontinue the current display at this point, enter the EXIT command. If you want SDA to execute another command, enter that command. SDA discontinues the display as if you entered EXIT, and then executes the command you entered.

When the SDA> prompt is not immediately preceded by the screen overflow prompt, entering EXIT causes your process to cease executing the SDA utility. When issued within a command procedure (either the SDA initialization file or a command procedure invoked with the execute (@) command), EXIT causes SDA to terminate execution of the procedure and return to the SDA prompt.

See Section 2.6.2 for a description of SDA display mode.

4.11. FORMAT

Displays a formatted list of the contents of a block of memory.

Format

```
FORMAT [/TYPE=block-type] location [/NOSYMBOLIZE][/PAGE][/PHYSICAL] [/POSITIVE]
```

Parameters

location

Location of the beginning of the data block. The location can be given as any valid SDA expression.

Qualifiers

/NOSYMBOLIZE

If /NOSYMBOLIZE is specified, no attempt is made to symbolize the contents of any field in a structure. This is useful if the loaded execllet or activated image lists are corrupted, since symbolization relies on these lists.

/PAGE

If the output of the formatted structure does not fit on one screen, SDA enters display mode. (For information on this topic, see Section 2.6.2.) By default, SDA displays the formatted structure without screen overflow prompts.

/PHYSICAL

Specifies that the location given is a physical address.

/POSITIVE

Symbols that describe negative offsets from the start of the structure are ignored. By default, all symbols for the block type are processed.

/TYPE=block-type

Forces SDA to characterize and format a data block at **location** as the specified type of data structure. The /TYPE qualifier thus overrides the default behavior of the FORMAT command in determining the type and/or subtype of a data block, as described in the Description section. The *block-type* can be the symbolic prefix of any data structure defined by the operating system.

Description

The FORMAT command performs the following actions:

- Characterizes a range of locations as a system data
- Assigns, if possible, a symbol to each item of data within the block
- Displays all the data within the block, up to a quadword per line
- Whenever successive quadword fields with no symbolic name containing the same value occur, only the first occurrence is output. Ellipses replace all subsequent occurrences.

Most OpenVMS control blocks include two bytes that indicate the block type and/or subtype at offsets 0A16 and 0B16, respectively. The type and/or subtype associate the block with a set of symbols that have a common prefix. Each symbol's name describes a field within the block, and the value of the symbol represents the offset of the field within the block.

If the type and/or subtype bytes contain a valid block type/subtype combination, SDA retrieves the symbols associated with that type of block (see \$DYNDEF) and uses their values to format the block.

For a given block type, all associated symbols have the following form:

```
<block_type>${<field>}_<name>
```

where field is one of the following:

```
B  Byte
W  Word
L  Longword
Q  Quadword
O  Octaword
A  Address
C  Constant
G  Global Longword
P  Pointer
R  Structure (variable size)
T  Counted ASCII string (up to 31 characters)
```

If SDA cannot find the symbols associated with the block type specified in the block-type byte or by the /TYPE qualifier, it issues the following message:

```
%SDA-E-NOSYMBOLS, no <block type> symbols found to format this block
```

If you receive this message, you may want to read additional symbols into the SDA symbol table and retry the FORMAT command. Many symbols that define OpenVMS data structures are contained within SDA\$READ_DIR:SYSDEF.STB. Thus, you would issue the following command:

```
SDA> READ SDA$READ_DIR:SYSDEF.STB
```

If SDA issues the same message again, try reading additional symbols. Section 2.5 lists additional modules provided by the OpenVMS operating system. Alternatively, you can create your own object modules with the MACRO-32 Compiler for OpenVMS. See the READ command description for instructions on creating such an object module.

Certain OpenVMS data structures do not contain a block type and/or subtype. If bytes contain information other than a block type/subtype---or do not contain a valid block type/subtype--- SDA either formats the block in a totally inappropriate way, based on the contents of offsets 0A16 and 0B16, or displays the following message:

```
%SDA-E-INVBLKTYP, invalid block type in specified block
```

To format such a block, you must reissue the FORMAT command, using the /TYPE qualifier to designate a *block-type*.

The FORMAT command produces a three-column display containing the following information:

- The first column shows the virtual address of each item within the block.
- The second column lists each symbolic name associated with a location within the block.
- The third column shows the contents of each item in hexadecimal format, including symbolization if a suitable symbol exists.

Examples

```

1. SDA> READ SYSDEF
SDA> format 81475D00
FFFFFFFF.81475D00  UCB$L_FQFL          8104EA58          EXE
$GL_FKWAITFL+00078
                    UCB$L_MB_MSGQFL
                    UCB$L_RQFL
                    UCB$W_MB_SEED
                    UCB$W_UNIT_SEED
FFFFFFFF.81475D04  UCB$L_FQBL          81412038
                    UCB$L_MB_MSGQBL
                    UCB$L_RQBL
FFFFFFFF.81475D08  UCB$W_SIZE          0380
FFFFFFFF.81475D0A  UCB$B_TYPE          10
FFFFFFFF.81475D0B  UCB$B_FLCK          3A
FFFFFFFF.81475D0C  UCB$L_ASTQFL        81223888          SYS$DKDRIVER
+19A88
                    UCB$L_FPC
                    UCB$L_MB_W_AST
                    UCB$T_PARTNER
.
.
.

```

In this example on an OpenVMS Alpha system, the READ command loads the symbols from SDA \$READ_DIR:SYSDEF.STB into SDA's symbol table. The FORMAT command displays the data structure that begins at 81475D0016, a unit control block (UCB). If a field has more than one symbolic name, all such names are displayed. Thus, the field that starts at 81475D0C16 has four designations: UCB\$L_ASTQFL, UCB\$L_FPC, UCB\$L_MB_W_AST, and UCB\$T_PARTNER.

The contents of each field appear to the right of the symbolic name of the field. Thus, the contents of UCB\$L_FQBL are 8104EA5816

```

2. SDA> read sysdef
SDA> read/exec
SDA> format 84191D00
FFFFFFFF.84191D00  SPL$L_OWN_CPU          00000000
FFFFFFFF.84191D04  SPL$L_OWN_CNT          FFFFFFFF
FFFFFFFF.84191D08  SPL$W_SIZE             0100
FFFFFFFF.84191D0A  SPL$B_TYPE             4F
FFFFFFFF.84191D0B  SPL$B_SUBTYPE          01
FFFFFFFF.84191D0C  SPL$L_SPINLOCK         00000000
FFFFFFFF.84191D10  SPL$L_RANK             00000000
FFFFFFFF.84191D14  SPL$B_IPL              1F
                    SPL$L_IPL
FFFFFFFF.84191D15  SPL$L_IPL              000000
FFFFFFFF.84191D18  SPL$L_RLS_PC           00000000
FFFFFFFF.84191D1C  SPL$L_BUSY_WAITS       00000000
FFFFFFFF.84191D20  SPL$L_WAIT_CPUS        00000000
FFFFFFFF.84191D24  SPL$L_WAIT_PC          00000000
FFFFFFFF.84191D28  SPL$Q_SPINS            00000000.00000000
FFFFFFFF.84191D30  SPL$Q_ACQ_COUNT        00000000.00008E08
FFFFFFFF.84191D38  SPL$L_TIMO_INT         000186A0          UCB
$M_FLOPPY_MEDIA+006A0
FFFFFFFF.84191D3C  SPL$PS_SHARE_ARRAY     00000000
FFFFFFFF.84191D40  SPL$PS_SHARE_LINK      00000000

```

```

FFFFFFFF.84191D44  SPL$T_NAME          ""
FFFFFFFF.84191D45                                000000
FFFFFFFF.84191D48                                00000000.00000000
FFFFFFFF.84191D50  SPL$Q_RELEASE_COUNT 00000000.00008E08
FFFFFFFF.84191D58  SPL$Q_HISTORY_BITMASK 00000000.00000000
FFFFFFFF.84191D60  SPL$Q_ABUSE_THRESHOLD 00000000.00000000
FFFFFFFF.84191D68  SPL$Q_FLAGS          00000000.00000000
FFFFFFFF.84191D70                                00000000.00000000
...
FFFFFFFF.84191D80  SPL$Q_ABUSE_BITMASK 00000000.00000000
FFFFFFFF.84191D88                                00000000.00000000
...
FFFFFFFF.84191DB8                                00000000
FFFFFFFF.84191DBC  SPL$L_VEC_INX       00000010
FFFFFFFF.84191DC0  SPL$L_OWN_PC_VEC   8016B7A0      ERL
$WAKE_C+00370
FFFFFFFF.84191DC4                                8016BF50      ERL
$WAKE_C+00B20
FFFFFFFF.84191DC8                                8016BF50.8016B7A0
...
FFFFFFFF.84191DD8                                8016B8C0.8016B7A0
FFFFFFFF.84191DE0                                000231E0.00022C20
FFFFFFFF.84191DE8                                00023BF0.000238D0
FFFFFFFF.84191DF0                                000231E0.00022C20

FFFFFFFF.84191DF8                                00023BF0.000238D0
SPL$C_LENGTH
.
.
.
```

In this example on an OpenVMS Integrity server system, the READ command loads the symbols from SYSDEF and the loaded executive images into SDA's symbol table. The FORMAT command displays the data structure that begins at 84191D0016, a spinlock control block (SPL). If a field has more than one symbolic name, all such names are displayed. Thus, the field that starts at 84191D1416 has two designations: SPL\$B_IPL and SPL\$L_IPL.

The contents of each field appear to the right of the symbolic name of the field. Thus, the contents of SPL\$B_IPL is 1F16.

4.12. HELP

Displays information about the SDA utility, its operation, and the format of its commands.

Format

HELP [**topic-name**]

Parameters

topic-name

Topic for which you need information. A topic can be an SDA command name such as ATTACH or COPY, the name of an SDA extension such as CLUE or FLT, or a keyword such as Extensions or Process_Context.

If you enter `HELP` with no topic name, a list of all topics is displayed.

Qualifiers

None.

Description

The `HELP` command displays brief descriptions of SDA commands and concepts on the terminal screen (or sends these descriptions to the file designated in a `SET OUTPUT` command). You can request additional information by specifying the name of a topic in response to the `Topic?` prompt.

If you do not specify a parameter in the `HELP` command, it lists the features of SDA and those commands and topics for which you can request help, as follows:

Examples

1. `SDA> HELP`
`HELP`

The System Dump Analyzer (SDA) allows you to inspect the contents of memory as saved in the dump taken at crash time or as exists in a running system. You can use SDA interactively or in batch mode. You can send the output from SDA to a listing file. You can use SDA to perform the following operations:

- Assign a value to a symbol
- Examine memory of any process
- Format instructions and blocks of data
- Display device data structures
- Display memory management data structures
- Display a summary of all processes on the system
- Display the SDA symbol table
- Copy the system dump file
- Read global symbols from any object module
- Search memory for a given value
- Send output to a file or device

For help on performing these functions, use the `HELP` command and specify a topic.

Format

```
HELP [topic-name]
```

Additional information available:

.
.
.

Topic?

4.13. MAP

Transforms an address into an offset in a particular image.

Format

MAP address

Parameters

address

Address to be identified.

Qualifiers

None.

Description

The MAP command identifies the image name and offset corresponding to an address. With this information, you can examine the image map to locate the source module and program section offset corresponding to an address.

If the address is in system space, MAP searches for the specified address in executive images first. It then checks activated images in process space to search those images installed using the /RESIDENT qualifier of the Install utility. Finally, it checks all image-resident sections in system space. If the address is in process space, MAP searches the activated images for the process.

If the address cannot be found, MAP displays the following message:

```
%SDA-E-NOTINIMAGE, Address not within a system/installed image
```

On Integrity servers, the MAP command can also provide additional data for addresses in system space. If the address is determined to be in a code section of an executive loaded image or a resident shareable image, and if the image file is accessible and was linked using /TRACEBACK, the traceback data is used to obtain and display the module name and routine name information.

Examples

1. SDA> MAP G90308

Image	Base	End	Image Offset
SYSSVM			
Nonpaged read only	80090000	800ABA00	00000308

Examining the image map identified by this MAP command (SYSSVM.MAP) shows that image offset 308 falls within psect EXEC\$HI_USE_PAGEABLE_CODE because the psect goes from offset 0 to offset 45D3:

```
.
.
.
```

```

EXEC$HI_USE_PAGEABLE_CODE      00000000 000045D3 000045D4 ( 17876.) 2
** 5...
      SYSCREDEL      00000000 0000149B 0000149C (  5276.) 2
** 5
      SYSCRMPS      000014A0 000045D3 00003134 ( 12596.) 2
** 5

EXEC$NONPAGED_CODE            000045E0 0001B8B3 000172D4 ( 94932.) 2
** 5...
      EXECUTE_FAULT  000045E0 0000483B 0000025C (   604.) 2
** 5
      IOLOCK         00004840 000052E7 00000AA8 (  2728.) 2
** 5
      LOCK_SYSTEM_PAGES
      .
      .
      .

```

Specifically, image offset 308 is located within source module SYSCREDEL. Therefore, to locate the corresponding code, you would look in SYSCREDEL for offset 308 in psect EXEC \$HI_USE_PAGEABLE_CODE.

2. SDA> MAP G550000

```

Image              Base          End          Image Offset
SYS$DKDRIVER      80548000    80558000    00008000

```

In this example, the MAP command identifies the address as an offset into an executive image that is not sliced. The base and end addresses are the boundaries of the image.

3. SDA> MAP G550034

```

Image              Base          End          Image Offset
SYS$DUDRIVER
  Nonpaged read/write 80550000    80551400    00008034

```

In this example, the MAP command identifies the address as an offset into an executive image that is sliced. The base and end addresses are the boundaries of the image section that contains the address of interest.

4. SDA> MAP GF0040

```

Image Resident Section  Base          End          Image Offset
MAILSHR             800F0000     80119000    00000040

```

The MAP command identifies the address as an offset into an image-resident section residing in system space.

5. SDA> MAP 12000

```

Activated Image      Base          End          Image Offset
MAIL                 00010000     000809FF    00002000

```

The MAP command identifies the address as an offset into an activated image residing in process-private space.

6. SDA> MAP B2340

```

Compressed Data Section  Base          End          Image Offset
LIBRTL                000B2000     000B6400    00080340

```

The MAP command identifies the address as being within a compressed data section. When an image is installed with the Install utility using the /RESIDENT qualifier, the code sections are

mapped in system space. The data sections are compressed into process-private space to reduce null pages or holes in the address space left by the absence of the code section. The `SHOW PROCESS/IMAGE=ALL` display shows how the data has been compressed; the `MAP` command searches this information to map an address in a compressed data section to an offset in an image.

```
7. SDA> MAP 7FC06000
Shareable Address Data Section      Base      End      Image Offset
LIBRTL                             7FC06000 7FC16800 00090000
```

The `MAP` command identifies the address as an offset into a shareable address data section residing in P1 space.

```
8. SDA> MAP 7FC26000
Read-Write Data Section            Base      End      Image Offset
LIBRTL                             7FC26000 7FC27000 000B0000
```

The `MAP` command identifies the address as an offset into a read-write data section residing in P1 space.

```
9. SDA> MAP 7FC36000
Shareable Read-Only Data Section   Base      End      Image Offset
LIBRTL                             7FC36000 7FC3F600 000C0000
```

The `MAP` command identifies the address as an offset into a shareable read-only data section residing in P1 space.

```
10. SDA> MAP 7FC56000
Demand Zero Data Section           Base      End      Image Offset
LIBRTL                             7FC56000 7FC57000 000E0000
```

The `MAP` command identifies the address as an offset into a demand zero data section residing in P1 space.

```
11. SDA> MAP FFFFFFFF.8042FE00
Image                               Base      End
Image Offset
EXCEPTION_MON
Code                                FFFFFFFF.8041FE00 FFFFFFFF.804E3DFF
00000000.00028000

Module:    IPF_DECODE +00005380
Routine:   process_i_unit + 00000840
```

This example shows the additional module and routine offset information that is displayed for system space code sections.

4.14. MODIFY DUMP

Allows a given byte, word, longword, or quadword in the dump file to be modified.

Format

```
MODIFY DUMP value {/BLOCK=n/OFFSET=n | /NEXT}
{/BYTE | /WORD | /LONGWORD (d) | /QUADWORD}
```

[/CONFIRM=*n*]

Parameters

value

New value deposited in the specified location in the dump file.

Qualifiers

/BLOCK=*n*

Indicates block number to be modified. Required unless the /NEXT qualifier is given.

/OFFSET=*n*

Indicates byte offset within block to be modified. Required unless the /NEXT qualifier is given.

/NEXT

Indicates that the byte or bytes immediately following the location altered by the previous MODIFY DUMP command are to be modified. Used instead of the /BLOCK=*n* and /OFFSET=*n* qualifiers.

/BYTE

Indicates that only a single byte is to be replaced

/WORD

Indicates that a word is to be replaced.

/LONGWORD

Indicates that a longword is to be replaced. This is the default.

/QUADWORD

Indicates that a quadword is to be replaced.

/CONFIRM=*n*

Checks existing contents of location to be modified.

Description

The MODIFY DUMP command is used on a dump file that cannot be analyzed without specifying the /OVERRIDE qualifier on the ANALYZE/CRASH_DUMP command. You can use the MODIFY DUMP command to correct the problem that prevents normal analysis of a dump file. You can only use the MODIFY DUMP command when you have invoked SDA with the ANALYZE/CRASH_DUMP/OVERRIDE command.

Important

This command is not intended for general use. It is provided for the benefit of VSI support personnel when investigating crash dumps that cannot be analyzed in other ways.

If the block being modified is part of either the dump header, the error log buffers, or the compression map, the changes made are not seen when you issue the appropriate `SHOW DUMP` command, unless you first exit from SDA and then reissue the `ANALYZE/CRASH_DUMP` command.

The `MODIFY DUMP` command sets a bit in the dump header to indicate that the dump has been modified. Subsequent `ANALYZE/CRASH_DUMP` commands issued to that file produce the following warning message:

```
%SDA-W-DUMPMOD, dump has been modified
```

Examples

1. `SDA>> MODIFY DUMP/BLOCK=10/OFFSET=100/WORD FF`

This example shows the dump file modified with the word at offset 100 in block 00000010 replaced by 00FF.

2. `SDA>> MODIFY DUMP/BLOCK=10/OFFSET=100/WORD 0/CONFIRM=EE`
`%SDA-E-NOMATCH, expected value does not match value in dump; dump not updated`

This example shows what happens when the actual word value of 00FF at offset 100 in block 00000010 does not match the given value of 00EE.

3. `SDA>> MODIFY DUMP/BLOCK=10/OFFSET=100/WORD 0/CONFIRM=FF`

This example shows the dump file modified with a word value of 00FF at offset 100 in block 00000010 replaced by 0000

4.15. READ

Loads the global symbols contained in the specified file into the SDA symbol table.

Format

```
READ {/EXECUTIVE [directory spec]  
| /FORCE filespec [/RELOCATE =expression | /SYMVA=expression]  
| /IMAGE filespec  
| filespec}  
[ /[NO]LOG]
```

Parameters

directory-spec

Name of the directory containing the loadable images of the executive. This parameter defaults to `SDA$READ_DIR`, which is a search list of `SYSS$LOADABLE_IMAGES`, `SYSS$LIBRARY`, and `SYSS$SYSTEM`.

filespec

Name of the device, directory, and file from which you want to read global symbols. The **filespec** defaults to SYSSDISK:[default-dir]filename.type, where SYSSDISK and [default-dir] represent the disk and directory specified in your last DCL command SET DEFAULT. If no type has been given in **filespec**, SDA first tries .STB and then .EXE.

If no device or directory is given in the file specification, and the file specification is not found in SYSSDISK:[default_dir], then SDA attempts to open the file SDA\$READ_DIR:filename.type. If no type has been given in **filespec**, SDA first tries .STB and then .EXE.

If the file name is the same as that of an executable or image, but the symbols in the file are not those of the executable or image, then you must use the /FORCE qualifier, and optionally /RELOCATE and /SYMVA qualifiers, to tell SDA how to interpret the symbols in the file.

The READ command accepts quoted filenames for access to images on ODS-5 disks with lowercase or compound characters in their names.

Qualifiers

/EXECUTIVE directory-spec

Reads into the SDA symbol table all global symbols and global entry points defined within all loadable images that make up the executive. For all the executables in the system, SDA reads the .STB or .EXE files in the requested directory.

/FORCE filespec

Forces SDA to read the symbols file, regardless of what other information or qualifiers are specified. If you do not specify the /FORCE qualifier, SDA may not read the symbols file if the specified **filespec** matches the image name in either the executive loaded images or the current processes activated image list, and one of the following conditions is true:

- The image has a symbols vector (is a shareable image), and a symbols vector was not specified with the /SYMVA or /IMAGE qualifier.
- The image is sliced, and slicing information was not provided with the /IMAGE qualifier.
- The shareable or executive image is not loaded at the same address it was linked at, and the relocation information was not provided with either the /IMAGE or /RELOCATE qualifier.

The use of /FORCE [/SYMVA=*addr*]/[RELOCATE=*addr*] **filespec** is a variant of the /IMAGE qualifier and avoids fixing up the symbols to match an image of the same name.

/IMAGE filespec

Searches the executive loaded image list and the current process activated image list for the image specified by filespec. If the image is found, the symbols are read in using the image symbol vector (if there is one) and either slicing or relocation information.

This is the preferred way to read in the .STB files produced by the linker. These .STB files contain all universal symbols, unless SYMBOL_TABLE=GLOBAL is in the linker options file, in which case the .STB file contains all universal and global symbols.

/LOG

/NOLOG (D)

The /LOG qualifier causes SDA to output the %SDA-I-READSYM message for each symbol table file it reads. By default, these messages are suppressed. You can specify /LOG and /NOLOG with any other combination of parameters and qualifiers.

/RELOCATE=*expression*

Changes the relative addresses of the symbols to absolute addresses by adding the value of **expression** to the value of each symbol in the symbol table file to be read. This qualifier changes those addresses to absolute addresses in the address space into which the dump is mapped.

The relocation only applies to symbols with the relocate flag set. All universal symbols must be found in the symbol vector for the image. All constants are read in without any relocation.

If the image is sliced (image sections are placed in memory at different relative offsets than how the image is linked), then the /RELOCATE qualifier does not work. SDA compares the file name used as a parameter to the READ command against all the image names in the executive loaded image list and the current processes activated image list. If a match is found, and that image contains a symbol vector, an error results. At this point you can either use the /FORCE qualifier or the /IMAGE qualifier to override the error.

/SYMVA=*expression*

Informs SDA whether the absolute symbol vector address is for a shareable image (SYS\$PUBLIC_VECTORS.EXE) or base system image (SYS\$BASE_IMAGE.EXE). All symbols found in the file with the universal flag are found by referencing the symbol vector (that is, the symbol value is a symbol vector offset).

Description

The READ command symbolically identifies locations in memory and the definitions used by SDA for which the default files (SDA\$READ_DIR:SYS\$BASE_IMAGE.EXE and SDA\$READ_DIR:REQSYSDEF.STB) provide no definition. In other words, the required global symbols are located in modules and symbol tables that have been compiled and/or linked separately from the executive. SDA extracts no local symbols from the files.

The file specified in the READ command can be the output of a compiler or assembler (for example, an .OBJ file).

Note

The READ command can read both OpenVMS Alpha and OpenVMS Integrity servers format files. Do not use READ to read files that contain symbols specific to another architecture, as this might change the behavior of other SDA commands for the current architecture.

Most often the file is provided in SYS\$LOADABLE_IMAGES. Many SDA applications, for instance, need to load the definitions of system data structures by issuing a READ command specifying SYSDEF.STB. Others require the definitions of specific global entry points within the executive image.

The files in SYS\$LOADABLE_IMAGES define global locations within executive images, including those listed in the table below. The actual list of executive images used varies, depending on platform type, devices, and the settings of several system parameters.

Table 4.1. Modules Defining Global Locations Within Executive Images

File	Contents
ACME.EXE	\$ACM system service
CNX\$DEBUG.EXE	Connection Manager trace routines
DDIF\$RMS_EXTENSION.EXE	Support for Digital Document Interchange Format (DDIF) file operations
ERRORLOG.STB	Error-logging routines and system services
EXCEPTION.STB	Bugcheck and exception-handling routines and those system services that declare condition and exit handlers. Variations of these files also exist, for example, where the file name ends in "_MON." System parameters such as SYSTEM_CHECK determine which image is loaded.
EXEC_INIT.STB	Initialization code
F11BXQP.STB	File system support
FC\$GLOGALS.STB	Fibrechannel symbols
IMAGE_MANAGEMENT.STB	Image activator and the related system services
IO_ROUTINES.STB	\$QIO system service, related system services (for example, \$CANCEL and \$ASSIGN), and supporting routines. Variations of these files also exist, for example, where the file name ends in "_MON." System parameters such as SYSTEM_CHECK determine which image is loaded.
LAT\$RATING.EXE	CPU load-balancing routines for LAT
LCK\$DEBUG.EXE	Lock manager trace routines
LMF\$GROUP_TABLE.EXE	Data structures for licensed product groups. Alpha only.
LOCKING.STB	Lock management routines and system services
LOGICAL_NAMES.STB	Logical name routines and system services
MESSAGE_ROUTINES.STB	System message routines and system services (including \$SNDJBC and \$GETTIM)
MSCP.EXE	Disk MSCP server
MULTIPATH.STB	Fibrechannel multipath support routines Variations of these files also exist, for example, where the file name ends in "_MON." System parameters such as SYSTEM_CHECK determine which image is loaded.
NET\$CSMACD.EXE	CSMA/CD LAN management module
NET\$FDDI.EXE	FDDI LAN management module
NT_EXTENSION.EXE	NT extensions for persona system services
PROCESS_MANAGEMENT.STB	Scheduler, report system event, and supporting routines and system services. Variations of these files also exist, for example, where the file name

File	Contents
	ends in "_MON." System parameters such as SYSTEM_CHECK determine which image is loaded.
RECOVERY_UNIT_SERVICES.STB	Recovery unit system services
RMS.EXE	Global symbols and entry points for RMS
SECURITY.STB	Security management routines and system services. Variations of these files also exist, for example, where the file name ends in "_MON." System parameters such as SYSTEM_CHECK determine which image is loaded.
SHELL <i>xx</i> K.STB	Process shell
SPL\$DEBUG.EXE	Spinlock trace routines
SSPI.EXE	Security Support Provider Interface
SYSS\$ <i>xx</i> DRIVER.EXE	Run-time device drivers
SYSS\$ACPI.EXE	Advanced Configuration and Power Interface routines. Integrity servers only.
SYSS\$ATMWORKS351.EXE	PCI-ATM driver
SYSS\$CLUSTER.EXE	OpenVMS Cluster support routines
SYSS\$CPU_ROUTINES_ <i>xxxx</i> .EXE	Processor-specific data and initialization routines. Alpha only.
SYSS\$EW1000A.EXE	Gigabit Ethernet driver
SYSS\$EW5700.EXE	Gigabit Ethernet driver. Integrity servers only.
SYSS\$GALAXY.STB	OpenVMS Galaxy support routines
SYSS\$HWP <i>nnnn</i> .EXE	PCI support routines. Integrity servers only.
SYSS\$IPC_SERVICES.EXE	Interprocess communication for DECdtm and Batch/Print
SYSS\$IPI <i>nnnn</i> .EXE	PCI support routines. Integrity servers only.
SYSS\$LAN.EXE	Common LAN routines
SYSS\$LAN_ATM.EXE	LAN routines for ATM
SYSS\$LAN_ATM4.EXE	LAN routines for ATM (ForeThought)
SYSS\$LAN_CSMACD.EXE	LAN routines for CSMA/CD
SYSS\$LAN_FDDI.EXE	LAN routines for FDDI
SYSS\$LAN_TR.EXE	LAN routines for Token Ring
SYSS\$MME_SERVICES.STB	Media Management Extensions
SYSS\$NETWORK_SERVICES.EXE	DECnet support
SYSS\$NTA.STB	NT affinity routines and services
SYSS\$ <i>xxxx</i> _SUPPORT.EXE	Processor-specific data and initialization routines. Integrity servers only.
SYSS\$PUBLIC_VECTORS.EXE	System service vector base image. This file is located in SYS\$LIBRARY.
SYSS\$SCS.EXE	System Communication Services

File	Contents
SYSS\$TRANSACTION_SERVICES.EXE	DECdtm services
SYSS\$UTC_SERVICES.EXE	Universal Coordinated Time services
SYSS\$VCC.STB	Virtual I/O cache. Variations of these files also exist, for example, where the file name ends in "_MON." System parameters such as SYSTEM_CHECK determine which image is loaded. Alpha only.
SYSS\$VM.STB	System pager and swapper, along with their supporting routines, and management system services
SYSS\$XFCACHE.STB	Extented File Cache. Variations of these files also exist, for example, where the file name ends in "_MON." System parameters such as SYSTEM_CHECK determine which image is loaded.
SYSDEVICE.STB	Mailbox driver and null driver
SYSGETSYI.STB	Get System Information system service (\$GETSYI)
SYSLDR_DYN.STB	Dynamic executive image loader
SYSLICENSE.STB	Licensing system service (\$LICENSE)
SYSTEM_DEBUG.EXE	XDelta and SCD routines
SYSTEM_PRIMITIVES.STB	Miscellaneous basic system routines, including those that allocate system memory, maintain system time, create fork processes, and control mutex acquisition. Variations of these files also exist, for example, where the file name ends in "_MON." System parameters such as SYSTEM_CHECK determine which image is loaded.
SYSTEM_SYNCHRONIZATION.STB	Routines that enforce synchronization. Variations of these files also exist, for example, where the file name ends in "_MON." System parameters such as SYSTEM_CHECK determine which image is loaded.
TCPIP\$BGDRIVER.STB	TCP/IP internet driver. Available only if TCP/IP has been installed.
TCPIP\$INETACP.STB	TCP/IP internet ACP Available only if TCP/IP has been installed.
TCPIP\$INETDRIVER.STB	TCP/IP internet driver. Available only if TCP/IP has been installed.
TCPIP\$INTERNET_SERVICES.STB	TCP/IP internet execler
TCPIP\$NFS_SERVICES.STB	Symbols for the TCP/IP NFS server. Available only if TCP/IP has been installed.
TCPIP\$PROXY_SERVICES.STB	Symbols for the TCP/IP proxy execler. Available only if TCP/IP has been installed.

File	Contents
TCPIP\$PWIPACP.STB	TCP/IP PWIP ACP. Available only if TCP/IP has been installed.
TCPIP\$PWIPDRIVER.STB	TCP/IP PWIP driver. Available only if TCP/IP has been installed.
TCPIP\$TNDRIVER.STB	TCP/IP TELNET/RLOGIN server driver. Available only if TCP/IP has been installed.
TMSCP.EXE	Tape MSCP server
VMS_EXTENSION.EXE	VMS extensions for persona system services

SDA can also read symbols from an image .EXE or .STB produced by the linker. The STB and EXE files only contain universal symbols. The STB file, however, can be forced to have global symbols for the image if you use the SYMBOL_TABLE=GLOBAL option in the linker options file.

A number of ready-built symbol table files ship with OpenVMS. They can be found in the directory SYS\$LOADABLE_IMAGES, and all have names of the form xyzDEF.STB. Of these files, SDA automatically reads REQSYSDEF.STB on activation. You can add the symbols in the other files to SDA's symbol table using the READ command. Table 2.5 lists the files that OpenVMS provides in SYS\$LOADABLE_IMAGES that define data structure offsets.

The following MACRO program, GLOBALS.MAR, shows how to obtain symbols in addition to those in SYS\$BASE_IMAGE.EXE, other executive images listed in Table 4.1, and the symbol table files that are listed in Table 2.5:

```
.TITLE GLOBALS
; n.b. on following lines GLOBAL must be capitalized
$PHDDEF GLOBAL      ; Process header definitions
$DDBDEF GLOBAL      ; Device data block
$UCBDEF GLOBAL      ; Unit control block
$VCBDEF GLOBAL      ; Volume control block
$ACBDEF GLOBAL      ; AST control block
$IRPDEF GLOBAL      ; I/O request packet
; more can be inserted here
.END
```

Use the following command to generate an object module file containing the globals defined in the program:

```
$MACRO GLOBALS+SYS$LIBRARY:LIB/LIBRARY /OBJECT=GLOBALS.STB
```

Examples

1. SDA> READ SDA\$READ_DIR:SYSDEF.STB/LOG
%SDA-I-READSYM, 10010 symbols read from SYS\$COMMON:[SYSEXE]SYSDEF.STB;1

The READ command causes SDA to add all the global symbols in SDA\$READ_DIR:SYSDEF.STB to the SDA symbol table. Such symbols are useful when you are formatting an I/O data structure, such as a unit control block or an I/O request packet.

2. SDA> SHOW STACK
Process stacks (on CPU 00)

Current operating stack (KERNEL):

```

00000000.7FF95CD0 FFFFFFFF.80430CE0 SCH$STATE_TO_COM+00040
00000000.7FF95CD8 00000000.00000000
00000000.7FF95CE0 FFFFFFFF.81E9CB04 LNM$SEARCH_ONE_C+000E4
00000000.7FF95CE8 FFFFFFFF.8007A988 PROCESS_MANAGEMENT_NPRO
+0E988
SP =>00000000.7FF95CF0 00000000.00000000
00000000.7FF95CF8 00000000.006080C1
00000000.7FF95D00 FFFFFFFF.80501FDC
00000000.7FF95D08 FFFFFFFF.81A5B720
.
.
.

```

```

SDA> READ/IMAGE SYS$LOADABLE_IMAGES:PROCESS_MANAGEMENT/LOG
%SDA-I-READSYM, 767 symbols read from SYS$COMMON:[SYS
$LDR]PROCESS_MANAGEMENT.STB;1
SDA> SHOW STACK
Process stacks (on CPU 00)
-----

```

Current operating stack (KERNEL):

```

00000000.7FF95CD0 FFFFFFFF.80430CE0 SCH$FIND_NEXT_PROC
00000000.7FF95CD8 00000000.00000000
00000000.7FF95CE0 FFFFFFFF.81E9CB04 LNM$SEARCH_ONE_C+000E4
00000000.7FF95CE8 FFFFFFFF.8007A988 SCH$INTERRUPT+00068
SP =>00000000.7FF95CF0 00000000.00000000
00000000.7FF95CF8 00000000.006080C1
00000000.7FF95D00 FFFFFFFF.80501FDC
00000000.7FF95D08 FFFFFFFF.81A5B720
.
.
.

```

The initial SHOW STACK command contains an address that SDA resolves into an offset from the PROCESS_MANAGEMENT executive image. The READ command loads the corresponding symbols into the SDA symbol table such that the reissue of the SHOW STACK command subsequently identifies the same location as an offset within a specific process management routine.

4.16. REPEAT

Repeats execution of the last command issued. On terminal devices, the KP0 key performs the same function as the REPEAT command with no parameter or qualifier.

Format

```
REPEAT [count | /UNTIL=condition]
```

Parameter

count

Number of times the previous command is to be repeated. The default is a single repeat.

Qualifier

/UNTIL=condition

Defines a condition that terminates the REPEAT command. By default, there is no terminating condition.

Description

The REPEAT command is useful for stepping through a linked list of data structures, or for examining a sequence of memory locations. When used with ANALYZE/SYSTEM, it allows the changing state of a system location or data structure to be monitored.

You can also use the REPEAT command to provide a convenient method of either displaying a series of data structures in a linked list or examining a sequence of locations. For example:

```
FORMAT @IOC$GGL_DEVLIST      ! Start at first DDB in system
FORMAT @.                    ! Skip to next entry in list
<KP0>                        ! Repeat FORMAT @. command
.
.
.
```

Examples

```
1. SDA> SPAWN CREATE SDATEMP.COM
SEARCH 0:3FFFFFFF 12345678
SET PROCESS/NEXT
^Z
SDA> SET PROCESS NULL
SDA> @SDATEMP
SDA> REPEAT/UNTIL = BADPROC
```

This example demonstrates how to search the address space of each process in a system or dump a given pattern.

```
2. SDA> SPAWN CREATE SDATEMP2.COM
FORMAT CPUDB
SET CPU /NEXT
^Z
SDA> READ SYSDEF
SDA> SET CPU /FIRST
SDA> @SDATEMP2
SDA> REPEAT/UNTIL = BADCPU
```

This example demonstrates how to format the CPU database for every CPU in a dump.

```
3. SDA> SHOW CALL_FRAME
Call Frame Information
-----
          Stack Frame Procedure Descriptor
Flags:   Base Register = FP, Jacket, Native
          Procedure Entry: FFFFFFFF.80080CE0          MMG$RETRANGE_C
+00180
          Return address on stack = FFFFFFFF.8004CF30 EXCEPTION_NPRO
+00F30
```

Registers saved on stack

```
-----
7FF95E80 FFFFFFFF.FFFFFFFD Saved R2
7FF95E88 FFFFFFFF.8042DBC0 Saved R3      EXCEPTION_NPRW+03DC0
7FF95E90 FFFFFFFF.80537240 Saved R4
7FF95E98 00000000.00000000 Saved R5
7FF95EA0 FFFFFFFF.80030960 Saved R6      MMG$IMGRESET_C+00200
7FF95EA8 00000000.7FF95EC0 Saved R7
7FF95EB0 FFFFFFFF.80420E68 Saved R13     MMG$ULKGBLWSL E
7FF95EB8 00000000.7FF95F70 Saved R29
```

.
.
.

SDA> SHOW CALL_FRAME/NEXT_FRAME

Call Frame Information

```
-----
          Stack Frame Procedure Descriptor
Flags:   Base Register = FP, Jacket, Native
          Procedure Entry: FFFFFFFF.80F018D0
          IMAGE_MANAGEMENT_PRO+078D0
          Return address on stack = FFFFFFFF.8004CF30      EXCEPTION_NPRO
+00F30
```

Registers saved on stack

```
-----
7FF95F90 FFFFFFFF.FFFFFFFB Saved R2
7FF95F98 FFFFFFFF.8042DBC0 Saved R3      EXCEPTION_ NPRW+03DC0
7FF95FA0 00000000.00000000 Saved R5
7FF95FA8 00000000.7FF95FC0 Saved R7
7FF95FB0 FFFFFFFF.80EF8D20 Saved R13     ERL$DEVINF O+00C20
7FF95FB8 00000000.7FFA0450 Saved R29
```

.
.
.

SDA> REPEAT

Call Frame Information

```
-----
          Stack Frame Procedure Descriptor
Flags:   Base Register = FP, Jacket, Native
          Procedure Entry: FFFFFFFF.80F016A0
          IMAGE_MANAGEMENT_PRO+076A0
          Return address on stack = 00000000.7FF2451C
```

Registers saved on stack

```
-----
7FFA0470 00000000.7FEEA890 Saved R13
7FFA0478 00000000.7FFA0480 Saved R29
```

.
.
.

The first `SHOW CALL_FRAME` displays the call frame indicated by the current FP value. Because the `/NEXT_FRAME` qualifier to the instruction displays the call frame indicated by the saved frame in the current call frame, you can use the `REPEAT` command to repeat the `SHOW CALL_FRAME/NEXT_FRAME` command and follow a chain of call frames.

4.17. SEARCH

Scans a range of memory locations for all occurrences of a specified value or string.

Format

```
SEARCH [/qualifier] range [=] {expression | string}
```

Parameters

range

Location in memory to be searched. A location can be represented by any valid SDA expression. To search a range of locations, use the following syntax:

<i>m:n</i>	Range of locations to be searched, from <i>m</i> to <i>n</i>
<i>m;n</i>	Range of locations to be searched, starting at <i>m</i> and continuing for <i>n</i> bytes

You must use either an equals sign or a blank to separate **range** from **expression** or **string**.

expression

Value for which SDA is to search. SDA evaluates the expression and searches the specified range of memory for the resulting value. For a description of SDA expressions, see Section 2.6.1.

string

Character sequence for which SDA is to search. If all characters in the sequence are printable characters, the string is enclosed in quotes, for example, "My_String". If the character sequence contains non-printable characters, it must be specified as a comma-separated list composed of quoted strings and hexadecimal numbers; for example, ("My_String",0C00,"More") would specify a search for "My_String<NUL><FF>More". Each hexadecimal number can be no more than 8 digits (4 bytes) in length. Non-printable sequences of more than 4 bytes must be split into multiple hexadecimal numbers. The maximum length of a search string is 127 bytes. Note that the quote character itself cannot be included in a quoted string and must be specified as a hexadecimal number.

Qualifiers

/IGNORE_CASE

Specifies that searches for strings are not to be case-specific. (By default, searches look for an exact match.) This qualifier is ignored for value searches.

/LENGTH={*QUADWORD* | *LONGWORD* | *WORD* | *BYTE*}

Specifies the size of the expression value that the SEARCH command uses for matching. If you do not specify the /LENGTH qualifier, the SEARCH command uses a longword length by default. This qualifier is ignored for string searches.

/MASK=*n*

Allows the SEARCH command finer granularity in its matches. It compares only the given bits of a byte, word, longword, or quadword. To compare bits when matching, you set the bits in the mask;

to ignore bits when matching, you clear the bits in the mask. This qualifier is ignored for string searches.

/PHYSICAL

Specifies that the addresses used to define the range of locations to be searched are physical addresses.

/STEPS = {*QUADWORD* | *LONGWORD* | *WORD* | *BYTE* | *value*}

Specifies the step factor of the search through the specified memory **range**. After the SEARCH command has performed the comparison between the value of **expression** or the given **string** and memory location, it adds the specified step factor to the address of the memory location. The resulting location is the next location to undergo the comparison. If you do not specify the /STEPS qualifier, the SEARCH command uses a step factor of a longword for value searches, and a step factor of a byte for string searches.

Description

SEARCH displays each location as each value or string is found. If you press Ctrl/T while using the SEARCH command, the system displays how far the search has progressed. The progress display is always output to the terminal even if a SET OUTPUT <file> command has previously been entered.

Examples

1. SDA> SEARCH GB81F0;500 B41B0000
Searching from FFFFFFFF.800B81F0 to FFFFFFFF.800B86EF in LONGWORD steps for B41B0000...
Match at FFFFFFFF.800B86E4 B41B0000

This SEARCH command finds the value B41B0000 in the longword at FFFFFFFF.800B86E4.

2. SDA> SEARCH 80000000;200/STEPS=BYTE 82
Searching from FFFFFFFF.80000000 to FFFFFFFF.800001FF in BYTE steps for 00000082...
Match at FFFFFFFF.8000012C 00000082

This SEARCH command finds the value 00000082 in the longword at FFFFFFFF.8000012C.

3. SDA> SEARCH/LENGTH=WORD 80000000;100 10
Match at FFFFFFFF.80000030 0010
Match at FFFFFFFF.80000040 0010
Match at FFFFFFFF.80000090 0010
Match at FFFFFFFF.800000A0 0010
Match at FFFFFFFF.800000C0 0010
5 matches found

This SEARCH command finds the value 0010 in the words at FFFFFFFF.80000030, FFFFFFFF.80000040, FFFFFFFF.80000090, FFFFFFFF.800000A0, FFFFFFFF.800000C0.

4. SDA> SEARCH/MASK=FF000000 80000000;40 20000000
Searching from FFFFFFFF.80000000 to FFFFFFFF.8000003F in LONGWORD steps for 20000000...
(Using search mask of FF000000)
Match at FFFFFFFF.80000000 201F0104
Match at FFFFFFFF.80000010 201F0001

2 matches found

This SEARCH command finds the value 20 in the upper byte of the longwords at FFFFFFFF.80000000 and FFFFFFFF.80000010, regardless of the contents of the lower 3 bytes.

5. SDA> SEARCH g:i ("test",01020304,"this",05060708,"again")
 Searching from FFFFFFFF.80000000 to FFFFFFFF.FFFFFFFF in byte steps for
 "test....this....again"....
 (74,65,73,74,04,03,02,01,74,68 ,69,73,08,07,06,05,61,67,61,69,6E)
 No matches found

This example combines quoted strings and hexadecimal values to form a character sequence to be used in a search. Note the order in which the bytes within each hexadecimal number are inserted into the search sequence: the least significant byte of the hexadecimal number is the first byte added to the search sequence.

4.18. SET CPU

When analyzing a system dump, selects a processor to become the current CPU for SDA. When invoked under ANALYZE/SYSTEM, SET CPU lists the database address for the specified CPU before exiting with the message: %SDA-E-CMDNOTVLD command not valid on the running system

Format

```
SET CPU {cpu-id | /FIRST | /NEXT | /PRIMARY } [/NOLOG]
```

Parameter

cpu-id

Numeric value indicating the identity of the processor to be made the current CPU. If you specify the **cpu-id** of a processor that was not active at the time of the system failure, SDA displays the following message:

```
%SDA-E-CPUNOTVLD, CPU not booted or CPU number out of range
```

Qualifiers

/FIRST

The lowest numbered CPU (not necessarily the primary CPU) is set as the current CPU.

/NEXT

The next higher numbered CPU is set as the current CPU. SDA skips CPUs not in the configuration at the time of the system failure. If there are no further CPUs, SDA returns an error.

/NOLOG

Use the /NOLOG qualifier to inhibit output of the database address for the CPU being set.

/PRIMARY

The primary CPU is set as the current CPU.

Description

When you invoke SDA to examine a system dump, the current CPU context for SDA defaults to that of the processor that caused the system to fail. When analyzing a system failure from a multiprocessing system, you may find it useful to examine the context of another processor in the configuration.

The SET CPU command changes the current CPU context for SDA to that of the processor indicated by **cpu-id**. The CPU specified by this command becomes the current CPU for SDA until you either exit from SDA or change the CPU context for SDA by issuing one of the following commands:

SET CPU **cpu-id**

SET CPU /FIRST

SET CPU /NEXT

SET CPU /PRIMARY

SHOW CPU **cpu-id**

SHOW CPU /FIRST

SHOW CPU /NEXT

SHOW CPU /PRIMARY

SHOW CRASH

SHOW MACHINE_CHECK **cpu-id**

Changing CPU context can cause an implicit change in process context under the following circumstances:

- If there is a current process on the CPU made current, SDA changes its process context to that of that CPU's current process.
- If there is no current process on the CPU made current, the SDA process context is undefined and no process-specific information is available until you set the SDA process context to that of a specific process.

The following commands also change the CPU context for SDA to that of the CPU on which the process was most recently current:

SET PROCESS **process-name**

SET PROCESS/ADDRESS=**pcb-address**

SET PROCESS/INDEX=**nn**

SET PROCESS/NEXT

SHOW PROCESS **process-name**

SHOW PROCESS/ADDRESS=**pcb-address**

SHOW PROCESS/INDEX=**nn**

SHOW PROCESS/NEXT

VALIDATE PROCESS/POOL **process-name**

VALIDATE PROCESS/POOL/ADDRESS=**pcb-address**

VALIDATE PROCESS/POOL/INDEX=**nn**

VALIDATE PROCESS/POOL/NEXT

See Section 2.5 for further discussion of the way in which SDA maintains its context information.

See the description of the REPEAT command for an example of the use of SET CPU/NEXT command.

4.19. SET ERASE_SCREEN

Enables or disables the automatic clearing of the screen before each new page of SDA output.

Format

SET ERASE_SCREEN {ON | OFF}

Parameters

ON

Enables the screen to be erased before SDA outputs a new heading. This setting is the default.

OFF

Disables the erasing of the screen.

Description

SDA's usual behavior is to erase the screen and then show the data. By setting the OFF parameter, the clear screen action is replaced by a blank line. This action does not affect what is written to a file when the SET LOG or SET OUTPUT commands are used.

Examples

1. SDA> SET ERASE_SCREEN ON

The clear screen action is now enabled.

2. SDA> SET ERASE_SCREEN OFF

The clear screen action is disabled.

4.20. SET FETCH

Sets the default size and access method of address data used when SDA evaluates an expression that includes the @ unary operator.

Format

SET FETCH [{QUADWORD | LONGWORD | WORD | BYTE}]

[, {PHYSICAL | VIRTUAL}]

Parameters

QUADWORD

Sets the default size to 8 bytes.

LONGWORD

Sets the default size to 4 bytes.

WORD

Sets the default size to 2 bytes.

BYTE

Sets the default size to 1 byte.

PHYSICAL

Sets the default access method to physical addresses.

VIRTUAL

Sets the default access method to virtual addresses.

You can specify only one parameter out of each group. If you are changing both size and access method, separate the two parameters by spaces or a comma. Include a comma only if you are specifying a parameter from both groups. See Example 6.

Qualifiers

None.

Description

Sets the default size and/or default access method of address data used by the @ unary operator in commands such as EXAMINE and EVALUATE. SDA uses the current default size unless it is overridden by the ^Q, ^L, ^W, or ^B qualifier on the @ unary operator in an expression. SDA uses the current default access method unless it is overridden by the ^P or ^V qualifier on the @ unary operator in an expression.

Examples

1. SDA> EXAMINE MMG\$GQ_SHARED_VA_PTES
MMG\$GQ_SHARED_VA_PTES: FFFFFFFD.FF7FE000 ".`a....."

This example shows the location's contents of a 64-bit virtual address.

2. SDA> SET FETCH LONG
SDA> EXAMINE @MMG\$GQ_SHARED_VA_PTES
%SDA-E-NOTINPHYS, FFFFFFFF.FF7FE000 : virtual data not in physical
memory

This example shows a failure because the SET FETCH LONG causes SDA to assume that it should take the lower 32 bits of the location's contents as a longword value, sign-extend them, and use that value as an address.

```
3. SDA> EXAMINE @^QMMG$GQ_SHARED_VA_PTES
FFFFFDFD.FF7FE000: 000001D0.40001119 "...@..."
```

This example shows the correct results by overriding the SET FETCH LONG with the ^Q qualifier on the @ operator. SDA takes the full 64 bits of the location's contents and uses that value as an address.

```
4. SDA> SET FETCH QUAD
SDA> EXAMINE @MMG$GQ_SHARED_VA_PTES
FFFFFDFD.FF7FE000: 000001D0.40001119 "...@..."
```

This example shows the correct results by changing the default fetch size to a quadword.

```
5. SDA> SET FETCH PHYSICAL
SDA> EXAMINE /PHYSICAL @0
```

This command uses the contents of the physical location 0 as the physical address of the location to be examined.

```
6. SDA> SET FETCH QUADWORD, PHYSICAL
```

This command sets the default fetch size and default access method at the same time.

4.21. SET LOG

Initiates or discontinues the recording of an SDA session in a text file.

Format

```
SET [NO]LOG filespec
```

Parameter

filespec

Name of the file in which you want SDA to log your commands and their output. The default **filespec** is `SYSDISK:[default_dir]filename.LOG`, where `SYSDISK` and `[default_dir]` represent the disk and directory specified in your last DCL command SET DEFAULT. If you specify SET LOG without a filename or specify SET NOLOG, SDA stops recording the session and directs all output to `SYSD$OUTPUT`.

Qualifier

None.

Description

The SET LOG command echoes the commands and output of an SDA session to a log file. The SET NOLOG command terminates this behavior.

The following differences exist between the SET LOG command and the SET OUTPUT command:

- When logging is in effect, your commands and their results are still displayed on your terminal. The SET OUTPUT command causes the displays to be redirected to the output file and they no longer appear on the screen.
- If an SDA command requires that you press Return to produce successive screens of display, the log file produced by SET LOG will record only those screens that are actually displayed. SET OUTPUT, however, sends the entire output of any SDA commands to its listing file.
- The SET LOG command produces a log file with a default file type of .LOG; the SET OUTPUT command produces a listing file whose default file type is .LIS.
- The SET OUTPUT command can generate a table of contents, each item of which refers to a display written to its listing file. SET OUTPUT also produces running heads for each page of output. The SET LOG command does not produce these items in its log file.

If you use the SET OUTPUT command to redirect output to a listing file, a SET LOG command to direct the same output to a log file is ineffective until output is restored to the terminal.

4.22. SET OUTPUT

Redirects output from SDA to the specified file or device.

Format

```
SET OUTPUT [/[NO]INDEX | /[NO]HEADER | /PERMANENT | /SINGLE_COMMAND] filespec
```

Parameter

filespec

Name of the file to which SDA is to send the output generated by its commands. The default **filespec** is SYSSDISK:[*default_dir*].filename.LIS, where SYSSDISK and [*default-dir*] represent the disk and directory specified in your last DCL command SET DEFAULT. You must specify a file name except when /PERMANENT is specified.

Qualifiers

/INDEX

/NOINDEX

The /INDEX qualifier causes SDA to include an index page at the beginning of the output file. This is the default unless you specify /NOHEADER or modify the default with a SET OUTPUT/PERMANENT command. The /NOINDEX qualifier causes SDA to omit the index page from the output file.

/HEADER

/NOHEADER

The /HEADER qualifier causes SDA to include a heading at the top of each page of the output file. This is the default unless you modify it with a SET OUTPUT/PERMANENT command. The /NOHEADER qualifier causes SDA to omit the page headings. Use of /NOHEADER implies /NOINDEX.

/PERMANENT

Modifies the defaults for /[NO]HEADER and /[NO]INDEX. Specify either or both qualifiers with or without a NO prefix to set new defaults. Setting the default to /NOHEADER implies a default of /NOINDEX. The new defaults remain in effect until another SET OUTPUT/PERMANENT command is entered or the SDA session is ended.

You cannot combine /PERMANENT and /SINGLE_COMMAND in one command, and you cannot provide a filespec with /PERMANENT.

/SINGLE_COMMAND

Indicates to SDA that the output for a single command is to be written to the specified file and that subsequent output should be written to the terminal. /SINGLE_COMMAND cannot be combined with /PERMANENT.

Description

When you use the SET OUTPUT command to send the SDA output to a file or device, SDA continues displaying the SDA commands that you enter but sends the output generated by those commands to the file or device you specify. (See the description of the SET LOG command for a list of differences between the SET LOG and SET OUTPUT commands.)

When you finish directing SDA commands to an output file and want to return to interactive display, issue the following command:

```
SDA> SET OUTPUT SYS$OUTPUT
```

You do not need this command when you specify the /SINGLE_COMMAND qualifier on the original SET OUTPUT command.

If you use the SET OUTPUT command to send the SDA output to a listing file and do not specify /NOINDEX or /NOHEADER, SDA builds a table of contents that identifies the displays you selected and places the table of contents at the beginning of the output file. The SET OUTPUT command formats the output into pages and produces a running head at the top of each page, unless you specify /NOHEADER.

If the table of contents does not fit on a single index page at the beginning of the listing file, SDA will insert additional index pages as necessary. These are inserted into the listing file immediately preceding the pages that are listed in each index page. Each index page includes the page number for the adjacent index pages.

Note

See the description of the DUMP command for use of SET OUTPUT/NOHEADER.

4.23. SET PROCESS

Selects a process to become the SDA current process.

Format

SET PROCESS {/ADDRESS=*pcb-address* | *process-name* | /ID=*nn* | /INDEX=*nn* | /NEXT

Parameter

process-name

Name of the process to become the SDA current process. The process-name can contain up to 15 uppercase letters, numerals, the underscore (_), dollar sign (\$), colon (:), and some other printable characters. If it contains any other characters (including lowercase letters), you may need to enclose the process-name in quotation marks (" ").

Qualifiers

/ADDRESS = *pcb-address*

Specifies the process control block (PCB) address of a process in order to display information about the process.

/ID=*nn*

/INDEX=*nn*

Specifies the process for which information is to be displayed either by its index into the system's list of software process control blocks (PCBs), or by its process identification. /ID and /INDEX are functionally equivalent. You can supply the following values for *nn*:

- The process index itself.
- The process identification (PID) or extended PID longword, from which SDA extracts the correct index. The PID or extended PID of any thread of a process with multiple kernel threads may be specified. Any thread-specific data displayed by further commands will be for the given thread.

To obtain these values for any given process, issue the SDA command SHOW SUMMARY/THREADS. The /ID=*nn* and /INDEX=*nn* qualifiers can be used interchangeably.

/NEXT

Causes SDA to locate the next valid process in the process list and select that process. If there are no further valid processes in the process list, SDA returns an error.

/SYSTEM

Specifies the new current process by the system process control block (PCB). The system PCB and process header (PHD) parallel the data structures that describe processes. They contain the system working set list, global section table, and other systemwide data.

Description

When you issue an SDA command such as EXAMINE, SDA displays the contents of memory locations in its current process. To display any information about another process, you must change the current process with the SET PROCESS command.

When you invoke SDA to analyze a crash dump, the process context defaults to that of the process that was current at the time of the system failure. If the failure occurred on a multiprocessing system, SDA sets the CPU context to that of the processor that caused the system to fail. The process context is set to that of the process that was current on that processor.

When you invoke SDA to analyze a running system, its process context defaults to that of the current process, that is, the one executing SDA.

The SET PROCESS command changes the current SDA process context to that of the process indicated by **process-name**, *pcb-address*, or */INDEX=nn*. The process specified by this command becomes the current process for SDA until you either exit from SDA or change SDA process context by issuing one of the following commands:

SET PROCESS **process-name**

SET PROCESS/ADDRESS=*pcb-address*

SET PROCESS/INDEX=*nn*

SET PROCESS/NEXT

SET PROCESS/SYSTEM

SHOW PROCESS **process-name**

SHOW PROCESS/ADDRESS=*pcb-address*

SHOW PROCESS/INDEX=*nn*

SHOW PROCESS/NEXT

SHOW PROCESS/SYSTEM

VALIDATE PROCESS/POOL **process-name**

VALIDATE PROCESS/POOL/ADDRESS=*pcb-address*

VALIDATE PROCESS/POOL/INDEX=*nn*

VALIDATE PROCESS/POOL/NEXT

VALIDATE PROCESS/POOL/SYSTEM

When you analyze a crash dump from a multiprocessing system, changing process context causes a switch of CPU context as well. When you issue a SET PROCESS command, SDA automatically changes its CPU context to that of the CPU on which that process was most recently current.

The following commands will also switch process context when analyzing a system dump, if there was a current process on the target CPU at the time of the crash:

SET CPU **cpu-id**

SET CPU /FIRST

SET CPU /NEXT

SET CPU /PRIMARY

SHOW CPU **cpu-id**

SHOW CPU /FIRST

SHOW CPU /NEXT

SHOW CPU /PRIMARY

SHOW CRASH

SHOW MACHINE_CHECK **cpu-id**

See Section 2.5 for further discussion of the way in which SDA maintains its context information.

Examples

```
1. SDA> SET PROCESS/ADDRESS=80D772C0
   SDA> SHOW PROCESS
   Process index: 0012   Name: ERRFMT   Extended PID: 00000052
   -----
   Process status: 02040001   RES,PHDRES,INTER
                   status2: 00000001   QUANTUM_RESCHED

   PCB address          80D772C0   JIB address           80556600
   PHD address          80477200   Swapfile disk address 01000F01
   KTB vector address  80D775AC   HWPCB address        81260080
   Callback vector address 00000000   Termination mailbox   0000
   Master internal PID  00010004   Subprocess count      0
   Creator extended PID 00000000   Creator internal PID  00000000
   Previous CPU Id     00000000   Current CPU Id        00000000
   Previous ASNSEQ     00000000000000001   Previous ASN          0000000000000002E
   Initial process priority 4   Delete pending count  0
   # open files allowed left 100   Direct I/O count/limit
   150/150
   UIC                  [00001,000004]   Buffered I/O count/limit
   149/150
   Abs time of last event 0069D34E   BUFIO byte count/limit
   99424/99808
   ASTs remaining        247   # of threads          1
   Swapped copy of LEFC0 00000000   Timer entries allowed left 63
   Swapped copy of LEFC1 00000000   Active page table count  4
   Global cluster 2 pointer 00000000   Process WS page count   32
   Global cluster 3 pointer 00000000   Global WS page count    31
```

The SET PROCESS command switches SDA's current process context to the process whose PCB is at address 80D772C0. The SHOW PROCESS command shows that the process is ERRFMT, and displays information from its PCB and job information block (JIB).

See the description of the REPEAT command for an example of the use of the SET PROCESS/NEXT command.

4.24. SET RMS

Changes the options shown by the SHOW PROCESS/RMS command.

Format

```
SET RMS = (option[,...])
```

Parameter

option

Data structure or other information to be displayed by the SHOW PROCESS/RMS command. The table below lists those keywords that can be used as options.

Table 4.2. SET RMS Command Keywords for Displaying Process RMS Information

Keyword	Meaning
[NO]ALL[: ifi] 1	All control blocks (default)
[NO]ASB	Asynchronous save block
[NO]BDB	Buffer descriptor block
[NO]BDBSUM	BDB summary page
[NO]BLB	Buffer lock block
[NO]BLBSUM	Buffer lock summary page
[NO]CCB	Channel control block
[NO]DRC	Directory cache
[NO]FAB	File access block
[NO]FCB	File control block
[NO]FSB	File statistics block
[NO]FWA	File work area
[NO]GBD	Global buffer descriptor
[NO]GBDSUM	GBD summary page
[NO]GBH	Global buffer header
[NO]GBHSH	Global buffer hash table
[NO]GBSB	Global buffer synchronization block
[NO]IDX	Index descriptor
[NO]IFAB[: ifi] 1	Internal FAB. The optional parameter ifi is an internal file identifier. The default ifi (ALL) is all the files the current process has opened.
[NO]IFB[: ifi] 1	Internal FAB
[NO]IRAB	Internal RAB
[NO]IRB	Internal RAB
[NO]JFB	Journaling file block
[NO]KLTB	Key-less-than block
[NO]NAM	Name block
[NO]NWA	Network work area
[NO]PIO	Image I/O (NOPIO), the default, or process I/O (PIO)

Keyword	Meaning
[NO]RAB	Record access block
[NO]RLB	Record lock block
[NO]RU	Recovery unit structures, including the recovery unit block (RUB), recovery unit stream block (RUSB), and recovery unit file block (RUFB)
[NO]SFSB	Shared file synchronization block
[NO]WCB	Window control block
[NO]XAB	Extended attribute block
[NO]*	Current list of options displayed by the SHOW RMS command

The default **option** is (**ALL,NOPIO**), which designates that the SHOW PROCESS/RMS command display all structures for all files related to the process image I/O.

If only a single option is specified, you can omit the parentheses. You can add a given data structure to those displayed by ensuring that the list of keywords begins with the asterisk (*) symbol. You can delete a given data structure from the current display by preceding its keyword with NO.

Qualifier

None.

Description

The SET RMS command determines the data structures to be displayed by the SHOW PROCESS/RMS command. (See the examples included in the discussion of the SHOW PROCESS command for information provided by various displays.) You can examine the options that are currently selected by issuing a SHOW RMS command.

Examples

- SDA> SHOW RMS
RMS Display Options:
IFB, IRB, IDX, BDB, BDBSUM, ASB, CCB, WCB, FCB, FAB, RAB, NAM, XAB, RLB,
BLB, BLBSUM, GBD, GBH, FWA, GBDSUM, JFB, NWA, RU, DRC, SFSB, GBSB

Display RMS structures for all IFI values.

```
SDA> SET RMS=IFB
SDA> SHOW RMS
```

RMS Display Options: IFB

Display RMS structures for all IFI values.

The first SHOW RMS command shows the default selection of data structures that are displayed in response to a SHOW PROCESS/RMS command. The SET RMS command selects only the IFB to be displayed by subsequent SET/PROCESS commands.

- SDA> SET RMS=(*, BLB, BLBSUM, RLB)
SDA> SHOW RMS

RMS Display Options: IFB,RLB,BLB,BLBSUM

Display RMS structures for all IFI values.

The SET RMS command adds the BLB, BLBSUM, and RLB to the list of data structures currently displayed by the SHOW PROCESS/RMS command.

3. SDA> SET RMS=(*,NORLB,IFB:05)
SDA> SHOW RMS

RMS Display Options: IFB,BLB,BLBSUM
Display RMS structures only for IFI=5.

The SET RMS command removes the RLB from those data structures displayed by the SHOW PROCESS/RMS command and causes only information about the file with the ifi of 5 to be displayed.

4. SDA> SET RMS=(*,PIO)

The SET RMS command indicates that the data structures designated for display by SHOW PROCESS/RMS be associated with process-permanent I/O instead of image I/O.

4.25. SET SIGN_EXTEND

Enables or disables the sign extension of 32-bit addresses.

Format

```
SET SIGN_EXTEND {ON | OFF}
```

Parameters

ON

Enables automatic sign extension of 32-bit addresses with bit 31 set. This is the default.

OFF

Disables automatic sign extension of 32-bit addresses with bit 31 set.

Qualifiers

None.

Description

The 32-bit S0/S1 addresses need to be sign-extended to access 64-bit S0/S1 space. To do this, specify explicitly sign-extended addresses, or set the sign-extend command to **ON**, which is the default.

However, to access addresses in P2 space, addresses must not be sign-extended. To do this, specify a zero in front of the address, or set the sign-extend command to **OFF**.

Examples

1. SDA> SET SIGN_EXTEND ON

```
SDA> examine 80400000
FFFFFFFF.80400000: 23DEFF90.4A607621
```

This shows the SET SIGN_EXTEND command as ON.

2. SDA> SET SIGN_EXTEND OFF
SDA> EXAMINE 80400000
%SDA-E-NOTINPHYS, 00000000.80400000: virtual data not in physical memory

This shows the SET SIGN_EXTEND command as OFF.

4.26. SET SYMBOLIZE

Enables or disables symbolization of addresses in the display from an EXAMINE command.

Format

```
SET SYMBOLIZE {ON | OFF}
```

Parameters

ON

Enables symbolization of addresses.

OFF

Disables symbolization of addresses.

Qualifier

None.

Examples

1. SDA> SET SYMBOLIZE ON
SDA> examine g1234
SYS\$PUBLIC_VECTORS+01234: 47DF041C ". .BG"
2. SDA> SET SYMBOLIZE OFF
SDA> examine g1234
FFFFFFFF.80001234: 47DF041C ". .BG"

These examples show the effect of enabling (default) or disabling symbolization of addresses.

4.27. SHOW ACPI (Integrity servers only)

Displays the contents of Advanced Configuration and Power Interface (ACPI) tables and namespace structures.

Format

```
SHOW ACPI {/NAMESPACE | /TABLE} [/ADDRESS = address | /ALL | /CHILDREN] [ident]
```

Parameter

ident

The name of the table or the namespace structure to be displayed. If an ident is given, /ADDRESS cannot be specified.

Qualifiers

/ADDRESS = *address*

The physical address of the table entry or virtual address of a namespace structure to be displayed. If /ADDRESS is used, no ident may be specified.

/ALL

Specifies that detailed information on each entity is to be displayed. By default, only a brief summary of each entity is given, except when a specific table is displayed.

/CHILDREN

Specifies that all the child namespace structures for a specified namespace entry are to be displayed. /CHILDREN cannot be used with /TABLES.

/NAMESPACE

Specifies that ACPI namespace structures are to be displayed. Either /NAMESPACE or /TABLES must be specified.

/TABLES

Specifies that ACPI tables are to be displayed. Either /NAMESPACE or /TABLES must be specified.

Description

The SHOW ACPI command displays the Advanced Configuration and Power Interface (ACPI) Tables and Namespace structures, either as a one line summary for each entity or in detail. The amount of detail varies for each structure. The structures most interesting to OpenVMS are formatted; others are output as a hexadecimal dump.

Examples

1. SDA> SHOW ACPI /TABLES

```
ACPI Tables
```

```
-----
```

Signature Rev	Physical Address	Length	OEM Id	OEM Table Id	ASL Vendor Id
-----	-----	-----	-----	-----	-----

RSDP 02	00000000.3FB2E000	00000028	HP	-	-
XSDT 01	00000000.3FB2E02C	0000007C	HP	zx2000	HP

FACP 03	00000000.3FB373E0	000000F4	HP	zx2000	HP
SPCR 01	00000000.3FB37518	00000050	HP	zx2000	HP
DBGP 01	00000000.3FB37568	00000034	HP	zx2000	HP
APIC 01	00000000.3FB37628	00000084	HP	zx2000	HP
SPMI 04	00000000.3FB375A0	00000050	HP	zx2000	HP
CPEP 01	00000000.3FB375F0	00000034	HP	zx2000	HP
SSDT 01	00000000.3FB33870	00000A14	HP	zx2000	INTL
SSDT 01	00000000.3FB34290	000022E2	HP	zx2000	INTL
SSDT 01	00000000.3FB36580	00000342	HP	zx2000	INTL
SSDT 01	00000000.3FB368D0	00000A16	HP	zx2000	INTL
SSDT 01	00000000.3FB372F0	000000EB	HP	zx2000	INTL
FACS 01	00000000.3FB374D8	00000040	-	-	-
DSDT 01	00000000.3FB2E0E0	00005781	HP	zx2000	INTL
HCDP 00	00000000.3FB2C000	00000088	HP	zx1	HP

This example shows the default display for the ACPI tables.

2. SDA> SHOW ACPI /TABLES RSDP

ACPI Tables

RSDP

```

Physical Address:      00000000.3FB2E000   Length:
00000028
OEM Identification:      "HP"   XSDT PA:
00000000.3FB2E02C
Revision:                02
    
```

This example shows the contents of the Root System Description Pointer (RSDP) table.

3. SDA> SHOW ACPI /NAMESPACE

ACPI Namespace

Node Address Flags	ACPI Name	Owner Id	Object Type	Operand Object
FFFFFFFF.88253028	____	00	Device	FFFFFFFF.89523158
	End_Of_Peer_List		Subtree_Has_Ini	
FFFFFFFF.89521BD8	_GPE	00	Local_Scope	00000000.00000000
FFFFFFFF.89523F58	_L14	01	Method	FFFFFFFF.89523F98
	End_Of_Peer_List			

```

FFFFFFFF.89521C18  _PR_          00 Local_Scope  00000000.00000000
FFFFFFFF.89521C58  _SB_          00 Device       00000000.00000000
Subtree_Has_Ini
FFFFFFFF.89529098  SBA0          01 Device       00000000.00000000
Subtree_Has_Ini
FFFFFFFF.895290D8  _HID          01 Method       FFFFFFFF.89529118
FFFFFFFF.89529198  _CID          01 Integer       FFFFFFFF.8952AD18

```

This example shows the default display for the ACPI namespace structures.

4. SDA> SHOW ACPI/NAMESPACE/CHILDREN _GPE

```

ACPI Namespace
-----
      Node          ACPI      Owner   Object      Operand
      Address       Name      Id      Type        Object
      Flags
-----
-----
FFFFFFFF.89521BD8  \_GPE          00 Local_Scope  00000000.00000000
FFFFFFFF.89523F58  \_GPE._L14     01 Method       FFFFFFFF.89523F98
End_Of_Peer_List

```

This example shows the summary display for the _GPE (General Purpose Event) package in the ACPI namespace, plus its child node.

4.28. SHOW ADDRESS

Displays the page table related information about a memory address.

Format

```
SHOW ADDRESS address [/PHYSICAL]
```

Parameter

address

The requested address.

Qualifier

/PHYSICAL

Indicates that a physical address has been given. The SHOW ADDRESS command displays the virtual address that maps to the given physical address.

Description

The SHOW ADDRESS command displays the region of memory that contains the memory address. It also shows all the page table entries (PTEs) that map the page and can show the range of addresses mapped by the given address if it is the address of a PTE. If the virtual address is in physical memory, the corresponding physical address is displayed.

When the /PHYSICAL qualifier is given, the SHOW ADDRESS command displays the virtual address that maps to the given physical address. This provides you with a way to use SDA commands that do not have a /PHYSICAL qualifier when only the physical address of a memory location is known.

Examples

```
1. SDA> SHOW ADDRESS 80000000
FFFFFFFF.80000000 is an S0/S1 address
Mapped by Level-3 PTE at: FFFFFFFD.FFE00000
Mapped by Level-2 PTE at: FFFFFFFD.FF7FF800
Mapped by Level-1 PTE at: FFFFFFFD.FF7FDF8
Mapped by Selfmap PTE at: FFFFFFFD.FF7FDF0
Also mapped in SPT window at: FFFFFFFF.FFDF0000
Mapped to physical address 00000000.00400000
```

The **SHOW ADDRESS** command in this example shows where the address 80000000 is mapped at different page table entry levels.

```
2. SDA> SHOW ADDRESS 0
00000000.00000000 is a P0 address
Mapped by Level-3 PTE at: FFFFFFFC.00000000
Mapped by Level-2 PTE at: FFFFFFFD.FF000000
Mapped by Level-1 PTE at: FFFFFFFD.FF7FC000
Mapped by Selfmap PTE at: FFFFFFFD.FF7FDF0
Not mapped to a physical address
```

The **SHOW ADDRESS** command in this example shows where the address 0 is mapped at different page table entry levels.

```
3. SDA> SHOW ADDRESS FFFFFFFD.FF000000
FFFFFFFD.FF000000 is the address of a process-private Level-2 PTE
Mapped by Level-1 PTE at: FFFFFFFD.FF7FC000
Mapped by Selfmap PTE at: FFFFFFFD.FF7FDF0
Range mapped at level 2: FFFFFFFC.00000000 to FFFFFFFC.00001FFF (1 page)
Range mapped at level 3: 00000000.00000000 to 00000000.007FFFFFFF (1024
pages)
Mapped to physical address 00000000.01230000
```

The **SHOW ADDRESS** command in this example shows where the address FFFFFFFD.FF7FC000 is mapped at page table entry and the range mapped by the PTE at this address.

```
4. SDA> SHOW ADDRESS/PHYSICAL 0
Physical address 00000000.00000000 is mapped to system-space address
FFFFFFFF.828FC000
```

The **SHOW ADDRESS** command in this example shows physical address 00000000.00000000 mapped to system-space address FFFFFFFF.828FC000.

```
5. SDA> SHOW ADDRESS/PHYSICAL 029A6000
Physical address 00000000.029A6000 is mapped to process-space address
00000000.00030000
(process index 0024)
```

The **SHOW ADDRESS** command in this example shows physical address 00000000.029A6000 mapped to process-space address 00000000.00030000 (process index 0024).

4.29. SHOW BUGCHECK

Displays the value, name, and text associated with one or all bugcheck codes.

Format

```
SHOW BUGCHECK {/ALL (d) | name | number}
```

Parameters

name

The name of the requested bugcheck code.

number

The value of the requested bugcheck code. The severity bits in the value are ignored.

The parameters **name** and **number** and the qualifier **/ALL** are all mutually exclusive.

Qualifier

/ALL

Displays complete list of all the bugcheck codes, giving their value, name, and text. It is the default.

Description

The SHOW BUGCHECK command displays the value, name, and text associated with bugcheck codes.

Examples

```
1. SDA> SHOW BUGCHECK 104
0100 DIRENTRY      ACP failed to find same directory entry
```

The SHOW BUGCHECK command in this example shows the requested bugcheck by number, ignoring the severity (FATAL).

```
2. SDA> SHOW BUGCHECK DECNET
08D0 DECNET        DECnet detected a fatal error
```

The SHOW BUGCHECK command in this example shows the requested bugcheck by name.

```
3. SDA> SHOW BUGCHECK
BUGCHECK codes and texts
-----
0008  ACPMBFAIL      ACP failure to read mailbox
0010  ACPVAFAIL      ACP failure to return virtual address space
0018  ALCPHD         Allocate process header error
0020  ALCSMBCLR      ACP tried to allocate space already allocated
.
.
.
```

The SHOW BUGCHECK command in this example shows the requested bugcheck by displaying all codes.

4.30. SHOW CALL_FRAME

Displays the locations and contents of the quadwords representing a procedure call frame.

Format

```
SHOW CALL_FRAME { [starting-address]
| /EXCEPTION_FRAME = intstk-address
| /NEXT_FRAME | /SUMMARY | /ALL}
```

Parameter

starting-address

For Alpha, an expression representing the starting address of the procedure call frame to be displayed. If no starting-address is given, the default starting address is the contents of the frame pointer (FP) register of the SDA current process. For a process that uses pthreads, the following SDA command can be used to display the starting addresses for all pthreads:

```
SDA> pthread thread -o u
```

For Integrity servers, the starting address is an expression representing one of the following:

- The invocation context handle of a frame.
- The address of an exception frame. This is equivalent to the following SDA command:

```
SDA> SHOW CALL_FRAME /EXCEPTION_FRAME=intstk-address
```

- The address of a Thread Environment Block (TEB).

For a list of all TEBs for the process, use the following SDA command:

```
SDA> pthread thread -o u
```

If no starting address is given, the default starting address is the invocation context handle of the current procedure in the SDA current process.

Qualifier

/ALL

Displays details of all call frames beginning at the current frame and continuing until bottom of stack (equivalent to SHOW CALL and repeated execution of a SHOW CALL/NEXT command).

/EXCEPTION_FRAME=intstk-address

(Integrity servers only) Provides an alternate starting address for SHOW CALL_FRAME. intstk-address is the address of an exception frame from which SDA creates an initial invocation context and displays the procedure call frame.

/NEXT_FRAME

Displays the procedure call frame starting at the address stored in the frame longword of the last call frame displayed by this command. You must have issued a SHOW CALL_FRAME command previously in the current SDA session in order to use the /NEXT_FRAME qualifier to the command.

/SUMMARY

Provides a one-line summary for each call frame, including exception frames, system-service entry frames, ASTs, KPBs, and so on, until reaching the bottom of the stack.

Description

Whenever a procedure is called, information is stored on the stack of the calling routine in the form of a procedure call frame. The `SHOW CALL_FRAME` command displays the locations and contents of the call frame. The starting address of the call frame is determined from the specified starting address, the `/NEXT_FRAME` qualifier, or the address contained in the SDA current process frame register (the default action).

When using the `SHOW CALL_FRAME/NEXT_FRAME` command to follow a chain of call frames, SDA signals the end of the chain by the following message:

```
Cannot display further call frames (bottom of stack)
```

This message indicates that the saved frame in the previous call frame has a zero value (for Alpha) or that the current frame is marked Bottom of Stack (for Integrity servers).

Examples

```
1. SDA> SHOW CALL_FRAME
Call Frame Information
-----
          Stack Frame Procedure Descriptor
Flags:   Base Register = FP, No Jacket, Native
          Procedure Entry: FFFFFFFF.837E9F10          EXCEPTION_PRO
+01F10
          Return address on stack = FFFFFFFF.837E8A1C  EXE$CONTSIGNAL_C
+0019C
Registers saved on stack
-----
7FF95F98  FFFFFFFF.FFFFFFFB  Saved R2
7FF95FA0  FFFFFFFF.8042AEA0  Saved R3          EXCEPTION_NPRW+040A0
7FF95FA8  00000000.00000002  Saved R5
7FF95FB0  FFFFFFFF.804344A0  Saved R13        SCH$CLREF+00188
7FF95FB8  00000000.7FF9FC00  Saved R29
.
.
.
SDA> SHOW CALL_FRAME/NEXT_FRAME
Call Frame Information
-----
          Stack Frame Procedure Descriptor
Flags:   Base Register = FP, No Jacket, Native
          Procedure Entry: FFFFFFFF.800FA388          RMS_NPRO+04388
          Return address on stack = FFFFFFFF.80040BFC  EXCEPTION_NPRO
+00BFC
Registers saved on stack
-----
7FF99F60  FFFFFFFF.FFFFFFFD  Saved R2
7FF99F68  FFFFFFFF.80425BA0  Saved R3          EXCEPTION_NPRW+03DA0
7FF99F70  FFFFFFFF.80422020  Saved R4          EXCEPTION_NPRW+00220
7FF99F78  00000000.00000000  Saved R5
```

```

7FF99F80  FFFFFFFF.835C24A8  Saved R6      RMS_PRO+004A8
7FF99F88  00000000.7FF99FC0  Saved R7
7FF99F90  00000000.7FF9FDE8  Saved R8
7FF99F98  00000000.7FF9FDF0  Saved R9
7FF99FA0  00000000.7FF9FE78  Saved R10
7FF99FA8  00000000.7FF9FEBC  Saved R11
7FF99FB0  FFFFFFFF.837626E0  Saved R13     EXE$OPEN_MESSAGE+00088
7FF99FB8  00000000.7FF9FD70  Saved R29
.
.
.
SDA> SHOW CALL_FRAME/NEXT_FRAME
Call Frame Information
-----
          Stack Frame Procedure Descriptor
Flags:   Base Register = FP, No Jacket, Native
          Procedure Entry: FFFFFFFF.835C2438           RMS_PRO+00438
          Return address on stack = FFFFFFFF.83766020  EXE
$OPEN_MESSAGE_C+00740
Registers saved on stack
-----
7FF99FD88  00000000.7FF9FDA4  Saved R2
7FF99FD90  00000000.7FF9FF00  Saved R3
7FF99FD98  00000000.7FFA0050  Saved R29

```

The `SHOW CALL_FRAME` commands in this SDA session follow a chain of call frames from that specified in the frame of the SDA current process.

2. SDA> SHOW CALL/SUMMARY
Call Frame Summary

```

-----
          Frame Type           Handle           Current PC
-----
Exception Dispatcher 00000000.7FF43EB0  FFFFFFFF.8049E160  EXCEPTION_MON
+5E360
Register Stack Frame 00000000.7FF12180  00000000.000122C0  KP_SAMPLE
+122C0
Memory Stack Frame   00000000.7FF43ED0  FFFFFFFF.8066B440  EXE$CMKRNL_C
+00330
Memory Stack Frame   00000000.7FF43F20  FFFFFFFF.80194890  EXE$SS_DISP_C
+00400
SS Dispatcher        00000000.3FFFDFC0  FFFFFFFF.8018D240  SWIS
$ENTER_KERNEL_SERVICE_C+003E0
Register Stack Frame 000007FD.BFF58000  00000000.000124C0  KP_SAMPLE
+124C0
KP Start Frame       00000000.7AC95A20  FFFFFFFF.80161670  EXE
$KP_START_C+003C0
Memory Stack Frame   00000000.7AC95B50  00000000.00012CE0  KP_SAMPLE
+12CE0
Memory Stack Frame   00000000.7AC95BC0  00000000.000126F0  KP_SAMPLE
+126F0
Base Frame           00000000.7AC95BE0  00000000.7ADE0BB0  DCL+82BB0
Bottom of stack

```

This example of `SHOW CALL/SUMMARY` on an Integrity server system shows the call frame summary of a process that has triggered an exception. The exception occurred while running a program called `KP_SAMPLE` which has invoked the `$CMKRNL` system service.

4.31. SHOW CBB

Displays contents of a Common Bitmask Block.

Format

SHOW CBB address

Parameter

address

The address of the Common Bitmask Block. This is required.

Qualifiers

None.

Description

The contents of the specified common bitmask block are displayed: the number of valid bits, the interlock state, the unit size and count, and the current settings for the bits in the bitmask.

Example

```
1. SDA> SHOW CBB SMP$GS_CBB_ACTIVE_SET
Common Bitmask Block at FFFFFFFF.8180CA00
-----

Valid bits:                00000040   State:
00000000.00000000

Unit count:                0001   Unit size:
QUADWORD

Unit bitmask:
..... 00000000 00000001 00000000
```

This example shows the active-CPU common bitmask block for a single-CPU system.

4.32. SHOW CEB

Displays information about Common Event flag Blocks, also known as Common Event flag clusters.

Format

SHOW CEB [address | /ALL]

Parameter

address

The address of a common event flag block. Detailed information is displayed for the specified common event flag block.

Qualifier

/ALL

Specifies that detailed information is to be displayed for each common event flag block. By default, a one-line summary is output for each common event flag block.

Description

The contents of one or all common event flag blocks is displayed. In one-line summary format, the address, name, creator process, reference count, current settings for the 32 event flags in the cluster, and the UIC of the cluster are displayed. In detailed format, the address of the cluster's Object Rights Block (ORB) and the count of waiting threads are also displayed, with lists of all associated processes and waiting threads.

You cannot specify both an address and /ALL; they are mutually exclusive.

SHOW COMMON_EVENT_BLOCK is a synonym for SHOW CEB.

Examples

- SDA> SHOW CEB
Common Event Flags

Address UIC	Name Flags	Creator	RefCount	EvtFlags
81E1D340 [11,1]	clus6 Permanent	0000009B Test1	00000001	00000000
81E294C0 [11,1]	clus5 Permanent	0000009B Test2	00000001	00000000
8213A280 [1,*]	IPCACP_FLAGS	00000086 IPCACP	00000001	00000000

This example shows the one-line summary of all common event flag blocks.

- SDA> SHOW CEB 81E294C0
Common Event Flags

CEB Address:	clus5	81E294C0	Name:	
Creator process EPID:	Test2	0000009B	Name:	
Event flag vector:	00000001	00000000	Reference count:	
ORB address:	00000001	829F75B0	Wait count:	
UIC:	00000002 Permanent	[11,1]	Flags:	

Associated Processes			Waiting Threads		
PCB	EPID	Name	KTB	Indx	WaitMask
-----	-----	-----	-----	-----	-----

```

-----
81E1C740  000000A4  BISHOP_47          81E1C740  0000  FFFFFFFF84

```

This example shows the details for the CEB at the given address.

4.33. SHOW CLASS

Displays information about scheduling classes that are active in the system or dump being analyzed.

Format

```
SHOW CLASS [class-name | /ALL]
```

Parameter

class-name

Name of the class to be displayed.

Qualifier

/ALL

Indicates that details of all active classes are to be displayed.

Description

SDA displays information about active scheduling classes in the system. By default, a summary of the classes is displayed.

Examples

- SDA> SHOW CLASS
Scheduling Classes

```

-----

```

Class Name	Original Quantum	Current Quantum	Time Restrict	Process Count
BISH	000000C6	000000C6	00FE0000	00000001

This example shows the summary display of the SHOW CLASS command.

- SDA> SHOW CLASS bish
Class name: "BISH"
Original quantum: 000000C6 (99%)
Current quantum: 000000C6 (99%)
Time restrictions: 00FE0000 (until 23:59)

Processes currently in class:

PCB	EPID	Name
83617D40	00000225	Milord_RTA1:

This example shows the detailed display of the SHOW CLASS command.

4.34. SHOW CLUSTER

Displays connection manager and system communications services (SCS) information for all nodes in a cluster.

Format

```
SHOW CLUSTER { [ { /ADDRESS=n | /CIRCUIT=pb-addr | /CSID=csid | /NODE=name } ] |
```

Parameters

None

Qualifier

/ADDRESS=*n*

Displays only the OpenVMS Cluster system information for a specific OpenVMS Cluster member node, given the address of the cluster system block (CSB) for the node. This is mutually exclusive with the */CIRCUIT=*pb-addr**, */CSID=*csid**, and */NODE=*name** qualifiers.

/CIRCUIT=*pb-addr*

Displays only the OpenVMS Cluster system information for a specific path, where *pb-addr* is the address of its path block. This qualifier is mutually exclusive with the */ADDRESS=*n**, */CSID=*csid**, and */NODE=*name** qualifiers.

/CSID=*csid*

Displays only the OpenVMS Cluster system information for a specific OpenVMS Cluster member node. The value *csid* is the cluster system identification number (CSID) of the node to be displayed. You can find the CSID for a specific node in a cluster by examining the CSB list display of the SHOW CLUSTER command. Other SDA displays refer to a system's CSID. For instance, the SHOW LOCKS command indicates where a lock is mastered or held by CSID. This is mutually exclusive with the */ADDRESS=*n**, */CIRCUIT=*pb-addr**, and */NODE=*name** qualifiers.

/NODE=*name*

Displays only the OpenVMS Cluster system information for a specific OpenVMS Cluster member node, given its SCS node name. This is mutually exclusive with the */ADDRESS=*n**, */CIRCUIT=*pb-addr**, and */CSID=*csid** qualifiers.

/SCS

Displays a view of the cluster as seen by SCS.

Description

The SHOW CLUSTER command provides a view of the OpenVMS Cluster system from either the perspective of the connection manager (the default behavior), or from the perspective of the port driver or drivers (if the */SCS* qualifier is used).

OpenVMS Cluster as Seen by the Connection Manager

The SHOW CLUSTER command provides a series of displays.

The **OpenVMS Cluster summary** display supplies the following information:

- Number of votes required for a quorum
- Number of votes currently available
- Number of votes allocated to the quorum disk
- Status summary indicating whether or not a quorum is present

The **CSB list** displays information about the OpenVMS Cluster system blocks (CSBs) currently in operation; one CSB is assigned to each node of the cluster. For each CSB, the **CSB list** displays the following information:

- Address of the CSB
- Name of the OpenVMS Cluster node it describes
- CSID associated with the node
- Number of votes (if any) provided by the node
- State of the CSB
- Status of the CSB

For information about the state and status of nodes, see the description of the **ADD CLUSTER** command of the **SHOW CLUSTER** utility in the *VSI OpenVMS System Management Utilities Reference Manual*.

The **cluster block** display includes information recorded in the cluster block (CLUB), including a list of activated flags, a summary of quorum and vote information, and other data that applies to the cluster from the perspective of the node for which the SDA is being run.

The **cluster failover control block** display provides detailed information concerning the cluster failover control block (CLUFCB). The **cluster quorum disk control block** display provides detailed information from the cluster quorum disk control block (CLUDCB).

Subsequent displays provide information for each CSB listed previously in the **CSB list** display. Each display shows the state and flags of a CSB, as well as other specific node information. (See the **ADD MEMBER** command of the **SHOW CLUSTER** utility in the *VSI OpenVMS System Management Utilities Reference Manual* for information about the flags for OpenVMS Cluster nodes.)

If any of the qualifiers **/ADDRESS=*n***, **/CSID=*csid***, or **/NODE=*name*** are specified, then the **SHOW CLUSTER** command displays only the information from the CSB of the specified node.

OpenVMS Cluster as Seen by the Port Driver

The **SHOW CLUSTER/SCS** command provides a series of displays.

The **SCS listening process directory** lists those processes that are listening for incoming SCS connect requests. For each of these processes, this display records the following information:

- Address of its directory entry
- Connection ID
- Name
- Explanatory information, if available

The **SCS systems summary** display provides the system block (SB) address, node name, system type, system ID, and the number of connection paths for each SCS system. An **SCS system** can be a OpenVMS Cluster member, storage controller, or other such device.

Subsequent displays provide detailed information for each of the system blocks and the associated path blocks. The system block displays include the maximum message and datagram sizes, local hardware and software data, and SCS poller information. Path block displays include information that describes the connection, including remote functions and other path-related data.

If the qualifier */CIRCUIT=pb-addr* is specified, the SHOW CLUSTER command displays only the information from the specified path block.

Examples

1. SDA> SHOW CLUSTER

```
OpenVMS Cluster data structures
      --- OpenVMS Cluster Summary ---
      Quorum   Votes   Quorum Disk Votes   Status Summary
      -----   -----   -----
              2       2           1           qf_dynvote, qf_vote, quorum
      --- CSB list ---
      Address   Node     CSID       Votes   State   Status
      -----   -----   -----
      805FA780  FLAM5   00010006   0       local  member, qf_same, qf_noaccess
      8062C400  ROMRDR  000100ED   1       open   member, qf_same, qf_watcher, qf_active
      8062C780  VANDQ1  000100EF   0       open   member, qf_same, qf_noaccess
      --- Cluster Block (CLUB) 805FA380 ---
      Flags: 16080005 cluster, qf_dynvote, init, qf_vote, qf_newvote, quorum
      Quorum/Votes                2/2      Last transaction code          02
      Quorum Disk Votes            1       Last trans. number             596
      Nodes                        3       Last coordinator CSID         000100EF
      Quorum Disk                  $1$DIA0 Last time stamp                 31-DEC-1992
      Found Node SYSID              00000000FC03 17:26:35
      Founding Time                 3-JAN-1993  Largest trans. id              00000254
                                       21:04:21  Resource Alloc. retry          0
      Index of next CSID              0007      Figure of Merit                 00000000
      Quorum Disk Cntrl Block 805FADC0 Member State Seq. Num          0203
      Timer Entry Address            00000000  Foreign Cluster                 00000000
      CSP Queue                      empty
      --- Cluster Failover Control Block (CLUFCB) 805FA4C0 ---
      Flags: 00000000
      Failover Step Index            00000037  CSB of Synchr. System          8062C780
      Failover Instance ID           00000254
      --- Cluster Quorum Disk Control Block (CLUDCB) 805FADC0 ---
      State      : 0002 qs_rem_act
      Flags      : 0100 qf_noaccess
      CSP Flags  : 0000
      Iteration Counter                0          UCB address                    00000000
      Activity Counter                  0          TQE address                    805FAE00
      Quorum file LBN                   00000000  IRP address                    00000000
                                       Watcher CSID                   000100ED
      --- FLAM5 Cluster System Block (CSB) 805FA780 ---
      State: 0B local
      Flags: 070260AA
      member, qf_same, qf_noaccess, selected, local, status_rcvd, send_status
      Cpblty: 00000000
```

```

SWVers: 7.0
HWName: DEC 3000 Model 400
Quorum/Votes      1/0    Next seq. number    0000    Send queue
00000000
Quor. Disk Vote    1     Last seq num rcvd  0000    Resend queue
00000000
CSID               00010006    Last ack. seq num  0000    Block xfer Q.
805FA7D8
Eco/Version        0/23    Unacked messages    0     CDT address
00000000
Reconn. time      00000000    Ack limit           0     PDT address
00000000
Ref. count         2     Incarnation         1-JAN-1993    TQE address
00000000
Ref. time          31-AUG-1992          00:00:00    SB address
80421580
                  17:26:35    Lock mgr dir wgt    0     Current CDRP
00000001
    --- ROMRDR Cluster System Block (CSB) 8062C400 ---
State: 01 open
Flags: 0202039A member,qf_same,cluster,qf_active,selected,status_rcvd
Cpblty: 00000000
SWVers: 7.0
HWName: DEC 3000 Model 400

Quorum/Votes      2/1    Next seq. number    B350    Send queue
00000000
Quor. Disk Vote    1     Last seq num rcvd  E786    Resend queue
00000000
CSID               000100ED    Last ack. seq num  B350    Block xfer Q.
8062C458
Eco/Version        0/22    Unacked messages    1     CDT address
805E8870
Reconn. time      00000000    Ack limit           3     PDT address
80618400
Ref. count         2     Incarnation         19-AUG-1992    TQE address
00000000
Ref. time          19-AUG-1992          16:15:00    SB address
8062C140
                  16:17:08    Lock mgr dir wgt    0     Current CDRP
00000000
    --- VANDQ1 Cluster System Block (CSB) 8062C780 ---
State: 01 open
Flags: 020261AA member,qf_same,qf_noaccess,cluster,selected,status_rcvd
Cpblty: 00000000
SWVers: 7.0
HWName: DEC 3000 Model 400
Quorum/Votes      1/0    Next seq. number    32B6    Send queue
00000000
Quor. Disk Vote    1     Last seq num rcvd  A908    Resend queue
00000000
CSID               000100EF    Last ack. seq num  32B6    Block xfer Q.
8062C7D8
Eco/Version        0/23    Unacked messages    1     CDT address
805E8710
Reconn. time      00000000    Ack limit           3     PDT address
80618400

```

```

Ref. count          2      Incarnation  17-AUG-1992      TQE address
00000000
Ref. time  19-AUG-1992          15:37:06      SB address
8062BCC0
          16:21:22      Lock mgr dir wgt          0      Current CDRP
00000000
      --- SWPCTX Cluster System Block (CSB) 80D3B1C0 ---
State:  0B local
Flags:  030A60AA
  member, qf_same, qf_noaccess, selected, send_ext_status, local, status_rcvd
Cpblty: 00000037 rm8sec, vcc, dts, cwcreprc, threads
SWVers: V7.0
HWName: DEC 3000 Model 400
Quorum/Votes      1/1      Next seq. number      0000      Send queue
00000000
Quor. Disk Vote    1      Last seq num rcvd     0000      Resend queue
00000000
CSID              00010001      Last ack. seq num     0000      Block xfer Q.
80D3B218
Eco/Version        0/26      Unacked messages      0      CDT address
00000000
Reconn. time      00000000      Ack limit              0      PDT address
00000000
Ref. count          2      Incarnation  12-JUL-1996      TQE address
00000000
Ref. time  16-JUL-1996          15:36:17      SB address
80C50800
          16:15:48      Lock mgr dir wgt          0      Current CDRP
00000001

```

This example illustrates the default output of the SHOW CLUSTER command.

2. SDA> SHOW CLUSTER/SCS
OpenVMS Cluster data structures

```

-----
          --- SCS Listening Process Directory ---

Entry Address      Connection ID      Process Name      Information
-----
      80C71EC0          74D20000      SCS$DIRECTORY      Directory
Server
      80C72100          74D20001      MSCP$TAPE          NOT PRESENT
HERE
      80E16940          74D20002      MSCP$DISK          MSCP$DISK
      80E23B40          74D20003      VMS$SDA_AXP        Remote SDA
      80E23B40          74D20003      VMS$SDA_AXP        Remote SDA
      80E25540          74D20004      VMS$VAXcluster
      .....
      80E29E80          74D20005      SCA$TRANSPORT
      813020C0          74D20053      PATHWORKScluster
      .....TurboServer

          --- SCS Systems Summary ---

SB Address      Node      Type      System ID      Paths
-----

```

8493BC00	ARUSHA	VMS	000000004CA1	2
80E23800	HSJ201	HSJ	4200101A1B20	1
80E3FF40	ORNOT	VMS	000000004CA7	2
80E43F40	LOADQ	VMS	000000004C31	2
80E473C0	HSJ300	HSJ	420010051D20	1
80E47CC0	HSJ101	HSJ	420010081720	1
80E47D40	HSJ100	HSJ	4200100B1520	1
80E478C0	HSJ600	HSJ	420010070920	1
80E49180	HSJ401	HSJ	4200100D0320	1
80E47DC0	HSJ301	HSJ	420010091F20	1
80E47E40	HSJ601	HSJ	4200100A0B20	1
80E49500	HSJ400	HSJ	4200100C0120	1
80E5BF80	CHOBE	VMS	000000004CD6	2
80E5F080	ETOSHA	VMS	000000004CF3	2
80E5FC00	VMS	VMS	000000004C7A	2
80E4FF80	HSJ501	HSJ	4200101C0720	1
80E5FD80	HSJ200	HSJ	420010191920	1
80E5FE80	HSJ500	HSJ	4200101B0520	1
80E5FE00	IPL31	VMS	000000004F52	2
80E59F80	ZAPNOT	VMS	000000004CBB	2
80E61F80	ALTOS	VMS	000000004D0F	2
80E72000	TSAVO	VMS	000000004CFE	2
80ED5D00	SLYTHE	VMS	000000004DD1	1
80EDDD00	AZSUN	VMS	000000004D56	1
80EDDE00	CALSUN	VMS	000000004EA4	1
80EDFC00	4X4TRK	VMS	00000000FF26	1
80EE93C0	GNRS	VMS	00000000FC2B	1
80EE94C0	IXIVIV	VMS	000000004E56	1
80EF1A80	CLAIR	VMS	000000004CDF	1
80EF1C00	INT4	VMS	00000000FD70	1
80EFDF80	SCOP	VMS	00000000FC87	1
80EFFAC0	MOCKUP	VMS	00000000FCD5	1

--- ARUSHA System Block (SB) 8493BC00 ---

System ID	000000004CA1	Local software type	VMS
Max message size	216	Local software vers.	V7.2
Max datagram size	576	Local software incarn.	DF4AC300
Local hardware type	ALPH		009F7570
Local hardware vers.	000000000003	SCS poller timeout	5AD3
	040400000000	SCS poller enable mask	27
Status:	00000000		

--- Path Block (PB) 80E55F80 ---

Status: 0020 credit

Remote sta. addr.	000000000016	Remote port type	00000010
Remote state	ENAB	Number of data paths	2
Remote hardware rev.	00000008	Cables state	A-OK B-OK
Remote func. mask	ABFF0D00	Local state	OPEN
Reseting port	16	Port dev. name	PNA0
Handshake retry cnt.	2	SCS MSGBUF address	80E4C528
Msg. buf. wait queue	80E55FB8	PDT address	80E2A180

--- Path Block (PB) 80ED0900 ---


```

Status: 0020 credit

Remote sta. addr.    0000000000DF    Remote port type      NI
Remote state        ENAB          Number of data paths  2
Remote hardware rev. 00000104    Cables state          A-OK B-OK
Remote func. mask   83FF0180    Local state           OPEN
Reseting port       00          Port dev. name        PEA0
Handshake retry cnt. 3          SCS MSGBUF address    80ED19A0
Msg. buf. wait queue 80ED0938    PDT address           80EC3C70

.
.
.

```

This example illustrates the output of the SHOW CLUSTER /SCS command.

4.35. SHOW CONNECTIONS

Displays information about all active connections between System Communications Services (SCS) processes or a single connection.

Format

```
SHOW CONNECTIONS [ { /ADDRESS=cdt-address | /NODE=name | /SYSAP=name } ]
```

Parameters

None.

Qualifiers

/ADDRESS=cdt-address

Displays information contained in the connection descriptor table (CDT) for a specific connection. You can find the *cdt-address* for any active connection on the system in the *CDT summary page* display of the SHOW CONNECTIONS command. In addition, CDT addresses are stored in many individual data structures related to SCS connections. These data structures include class driver request packets (CDRPs) and unit control blocks (UCBs) for class drivers that use SCS, and cluster system blocks (CSBs) for the connection manager.

/NODE=name

Displays all CDTs associated with the specified remote SCS node name.

/SYSAP=name

Displays all CDTs associated with the specified local SYSAP.

Description

The SHOW CONNECTIONS command provides a series of displays.

The **CDT summary page** lists information regarding each connection on the local system, including the following:

- CDT address
- Name of the local process with which the CDT is associated
- Connection ID
- Current state
- Name of the remote node (if any) to which it is currently connected

The **CDT summary page** concludes with a count of CDTs that are free and available to the system.

SHOW CONNECTIONS next displays a page of detailed information for each active CDT listed previously.

Example

1. SDA> SHOW CONNECTIONS

```

--- CDT Summary Page ---
CDT Address      Local Process      Connection ID      State      Remote
Node
-----
805E7ED0        SCS$DIRECTORY      FF120000          listen
805E8030        MSCP$TAPE          FF120001          listen
805E8190        VMS$VMScluster    FF120002          listen
805E82F0        MSCP$DISK          FF120003          listen
805E8450        SCA$TRANSPORT     FF120004          listen
805E85B0        MSCP$DISK          FF150005          open       VANDQ1
805E8710        VMS$VMScluster    FF120006          open       VANDQ1
805E8870        VMS$VMScluster    FF120007          open       ROMRDR
805E89D0        MSCP$DISK          FF120008          open       ROMRDR
805E8C90        VMS$DISK_CL_DRVR  FF12000A          open       ROMRDR
805E8DF0        VMS$DISK_CL_DRVR  FF12000B          open       VANDQ1
805E8F50        VMS$TAPE_CL_DRVR  FF12000C          open       VANDQ1
Number of free CDT's: 188
--- Connection Descriptor Table (CDT) 80C44850 ---
State: 0001 listen          Local Process:      MSCP$TAPE
Blocked State: 0000
Local Con. ID 899F0003      Datagrams sent      0      Message queue
80C4488C
Remote Con. ID 00000000      Datagrams rcvd      0      Send Credit Q.
80C44894
Receive Credit          0      Datagram discard    0      PB address
00000000
Send Credit              0      Message Sends       0      PDT address
00000000
Min. Rec. Credit        0      Message Recvs       0      Error Notify
822FFCC0
Pend Rec. Credit        0      Mess Sends NoFP     0      Receive Buffer
00000000
Initial Rec. Credit     0      Mess Recvs NoFP     0      Connect Data
00000000
Rem. Sta. 000000000000      Send Data Init.     0      Aux. Structure
00000000
Rej/Disconn Reason      0      Req Data Init.      0      Fast Recvmsg Rq
00000000

```

```

Queued for BDLT      0      Bytes Sent      0      Fast Recvmsg PM
00000000
Queued Send Credit  0      Bytes rcvd    0      Change Affinity
00000000
                                Total bytes map    0
--- Connection Descriptor Table (CDT) 805E8030 ---
State: 0001 listen      Local Process:  MSCP$TAPE
Blocked State: 0000
Local Con. ID  FF120001  Datagrams sent  0      Message queue
805E8060
Remote Con. ID  00000000  Datagrams rcvd  0      Send Credit Q.
805E8068
Receive Credit    0      Datagram discard  0      PB address
00000000
Send Credit      0      Messages Sent    0      PDT address
00000000
Min. Rec. Credit  0      Messages Rcvd.  0      Error Notify
804540D0
Pend Rec. Credit  0      Send Data Init.  0      Receive Buffer
00000000
Initial Rec. Credit  0      Req Data Init.  0      Connect Data
00000000
Rem. Sta. 000000000000  Bytes Sent      0      Aux. Structure
00000000
Rej/Disconn Reason  0      Bytes rcvd      0
Queued for BDLT    0      Total bytes map  0
Queued Send Credit  0
.
.
.

```

This example shows the default output of the SHOW CONNECTIONS command.

4.36. SHOW CPU

When analyzing a dump, displays information about the state of a CPU at the time of the system failure. SHOW CPU is only valid when you are analyzing a crash dump. It is not a valid command when you are analyzing the running system, because all the CPU-specific information may not be available. If invoked when you are analyzing a running system, SHOW CPU will only list the CPU database address(es) for the specified CPU or all CPUs.

Format

```
SHOW CPU [cpu-id | /FIRST | /NEXT | /PRIMARY]
```

Parameter

cpu-id

Numeric value indicating the identity of the CPU for which context information is to be displayed. If you specify the **cpu-id** parameter, the SHOW CPU command performs an implicit SET CPU command, making the CPU indicated by **cpu-id** the current CPU for subsequent SDA commands.

If you do not specify a **cpu-id**, the state of the SDA current CPU is displayed.

If you specify the **cpu-id** of a CPU that was not active at the time of the system failure, SDA displays the following message:

```
%SDA-E-CPUNOTVLD, CPU not booted or CPU number out of range
```

See the description of the SET CPU command and Section 2.5 for information on how this can affect the CPU context---and process context---in which SDA commands execute.

Qualifiers

/FIRST

The state of the lowest numbered CPU (not necessarily the primary CPU) is displayed.

/NEXT

The state of the next higher numbered CPU is displayed. SDA skips CPUs not in the configuration at the time of system failure. If there are no further CPUs, SDA returns an error.

/PRIMARY

The state of the primary CPU is displayed.

Description

The SHOW CPU command displays system failure information about the CPU specified by **cpu-id** or, by default, the SDA current CPU, as defined in Section 2.5.

The SHOW CPU command produces several displays. The first display is a brief description of the system failure and its environment that includes the following:

- Reason for the bugcheck.
- Name of the currently executing process. If no process has been scheduled on this CPU, SDA displays the following message:

```
Process currently executing: no processes currently scheduled on the processor
```
- File specification of the image executing within the current process (if there is a current process).
- Interrupt priority level (IPL) of the CPU at the time of the system failure.
- The CPU database address.
- The CPU's capability set.
- On Integrity server systems, the Exception Frame Summary.

On Alpha, the **register display** follows. First the *general registers* are output, showing the contents of the CPU's integer registers (R0 to R30), and the AI, RA, PV, FP, PC, and PS at the time of the system failure.

The Alpha *processor registers* display consists of the following parts:

- Common processor registers

- Processor-specific registers
- Stack pointers

The first part of the processor registers display includes registers common to all Alpha processors, which are used by the operating system to maintain the current process virtual address space, system space, or other system functions. This part of the display includes the following registers:

- Hardware privileged context block base register (PCBB)
- System control block base register (SCBB)
- Software interrupt summary register (SISR)
- Address space number register (ASN)
- AST summary register (ASTSR)
- AST enable register (ASTEN)
- Interrupt priority level register (IPL)
- Processor priority level register (PRBR)
- Page table base register (PTBR)
- Virtual page table base register (VPTB)
- Floating-point control register (FPCR)
- Machine check error summary register (MCES)

On Integrity server systems, the *register display* is in the form of the contents of the exception frame generated by the bugcheck. See `SHOW CRASH` for more details.

The last part of the display includes the four stack pointers: the pointers of the kernel, executive, supervisor, and user stacks (KSP, ESP, SSP, and USP, respectively). In addition, on Integrity servers, the four register stack pointers are displayed: KBSP, EBSP, SBSP, UBSP.

The `SHOW CPU` command concludes with a listing of the spinlocks, if any, owned by the CPU at the time of the system failure, reproducing some of the information given by the `SHOW SPINLOCKS` command. The spinlock display includes the following information:

- Name of the spinlock.
- Address of the spinlock data structure (SPL).
- The owning CPU's CPU ID.
- IPL of the spinlock.
- Indication of the depth of this CPU's ownership of the spinlock. A number greater than 1 indicates that this CPU has nested acquisitions of the spinlock.
- Rank of the spinlock.

- Timeout interval for spinlock acquisition (in terms of 10 milliseconds).
- Shared array (shared spinlock context block pointers)

Examples

1. SDA> SHOW CPU 0

CPU 00 Processor crash information

CPU 00 reason for Bugcheck: CPUEXIT, Shutdown requested by another CPU

Process currently executing on this CPU: None

Current IPL: 31 (decimal)

CPU database address: 81414000

CPUs Capabilities: PRIMARY, QUORUM, RUN

General registers:

```

R0  = FFFFFFFF.81414000  R1  = FFFFFFFF.81414000  R2  =
    00000000.00000000
R3  = FFFFFFFF.810AD960  R4  = 00000000.01668E90  R5  =
    00000000.00000001
R6  = 66666666.66666666  R7  = 77777777.77777777  R8  =
    FFFFFFFF.814FB040
R9  = 99999999.99999999  R10 = FFFFFFFF.814FB0C0  R11 =
    BBBBBBBB.BBBBBBBB
R12 = CCCCCCCC.CCCCCCCC  R13 = FFFFFFFF.810AD960  R14 =
    FFFFFFFF.81414018
R15 = 00000000.00000004  R16 = 00000000.000006AC  R17 =
    00000000.00000047
R18 = 00000000.00000000  R19 = 00000000.00000000  R20 =
    FFFFFFFF.8051A494
R21 = 00000000.00000000  R22 = 00000000.00000001  R23 =
    00000000.00000010
R24 = FFFFFFFF.81414000  AI  = FFFFFFFF.81414000  RA  =
    FFFFFFFF.81006000
PV  = 00000001.FFFFFFFF  R28 = 00000000.00000000  FP  =
    FFFFFFFF.88ABDFD0
PC  = FFFFFFFF.8009C95C  PS  = 18000000.00001F04

```

Processor Internal Registers:

```

ASN  = 00000000.00000000          ASTSR/ASTEN =
    00000000
IPL  =          0000001F  PCBB = 00000000.01014080  PRBR =
    FFFFFFFF.81414000
PTBR = 00000000.0000FFBF  SCBB = 00000000.000001E8  SISR =
    00000000.00000100
VPTB = FFFFFFFEFC.00000000  FPCR = 00000000.00000000  MCES =
    00000000.00000000

    KSP  = FFFFFFFF.88ABDCD8
    ESP  = FFFFFFFF.88ABF000
    SSP  = FFFFFFFF.88AB9000
    USP  = FFFFFFFF.88AB9000

```

Spinlocks currently owned by CPU 00

SCS		Address	810AF300
Owner CPU ID	00000000	IPL	00000008
Ownership Depth	00000000	Rank	0000001A
Timeout Interval	002DC6C0	Share Array	00000000

This example shows the default output of the SHOW CPU command on an Alpha system.

4.37. SHOW CRASH

Provides system information identifying a running system, or displays information about the state of the system at the time of a system failure.

Format

```
SHOW CRASH [/ALL | /CPU=n]
```

Parameters

None.

Qualifiers

/ALL

Displays exception data for all CPUs. By default, the registers (on Alpha) or exception frame contents (on Integrity servers) are omitted from the display for any CPUs with CPUEXIT or DBGCPUEXIT bugchecks.

/CPU=*n*

Allows exception data to be displayed from CPUs other than the one considered as the crash CPU when more than one CPU crashes simultaneously.

Description

The SHOW CRASH command has two different functions, depending on whether you use it to analyze a running system or a system failure.

When used during the analysis of a running system, the SHOW CRASH command produces a display that describes the system and the version of OpenVMS that it is running. The **system crash information** display contains the following information:

- Name and version number of the operating system
- Major and minor IDs of the operating system
- Identity of the OpenVMS system, including an indication of its cluster membership
- CPU ID of the primary CPU
- Address of all CPU databases

When used during the analysis of a system failure, the SHOW CRASH command produces several displays that identify the system and describe its state at the time of the failure.

If the current CPU context for SDA is not that of the processor that signaled the bugcheck, or the CPU specified with the /CPU=*n* qualifier, the SHOW CRASH command first performs an implicit SET CPU command to make that processor the current CPU for SDA. (See the description of the SET CPU command and Section 2.5 for a discussion of how this can affect the CPU context--and process context--in which SDA commands execute.)

The **system crash information** display in this context provides the following information:

- Date and time of the system failure.
- Name and version number of the operating system.
- Major and minor IDs of the operating system.
- Identity of the system.
- CPU IDs of both the primary CPU and the CPU that initiated the bugcheck. In a uniprocessor system, these IDs are identical.
- Bitmask of the active and available CPUs in the system.
- For each active processor in the system, the address of its CPU database and the name of the bugcheck that caused the system failure. Generally, there will be only one significant bugcheck in the system. All other processors typically display the following as their reason for taking a bugcheck:

```
CPUEXIT, Shutdown requested by another CPU
```

Subsequent screens of the SHOW CRASH command display information about the state of each active processor on the system at the time of the system failure. The information in these screens is identical to that produced by the SHOW CPU command, including the registers (on Alpha), exception frame (on Integrity servers), stack pointers, and records of spinlock ownership. The first such screen presents information about the processor that caused the failure; others follow according to the numeric order of their CPU IDs. For the processor that caused the failure, if an exception bugcheck (INVEXCEPTN, SSRVEXCEPT, FATALEXCEPT, UNXSIGNAL) or, for Integrity servers only, also a KRNLSTAKNV or DEBUGCRASH bugcheck has occurred, SHOW CRASH first displays the exception frame from the original exception. If /ALL is not specified, the registers (on Alpha) or exception frame contents (on Integrity servers) are omitted from the display for any CPUs with CPUEXIT or DBGCPUEXIT bugchecks.

SHOW CRASH displays the original exception in process dumps.

Examples

1. SDA> SHOW CRASH
Version of system: OpenVMS (TM) Alpha Operating System, Version X901-SSB

System Version Major ID/Minor ID: 3/0

VMScLuster node: VMSTS6, a

Crash CPU ID/Primary CPU ID: 00/00

Bitmask of CPUs active/available: 00000001/00000001

CPU bugcheck codes:
CPU 00 -- INVEXCEPTN, Exception while above ASTDEL

System State at Time of Exception

Exception Frame:

```

R2 = FFFFFFFF.810416C0  SCS$GA_LOCALSB+005C0
R3 = FFFFFFFF.81007E60  EXE$GPL_HWRPB_L
R4 = FFFFFFFF.850AEB80
R5 = FFFFFFFF.81041330  SCS$GA_LOCALSB+00230
R6 = FFFFFFFF.81038868  CON$INITLINE
R7 = FFFFFFFF.81041330  SCS$GA_LOCALSB+00230
PC = FFFFFFFF.803EF81C  SYS$TTDRIVER+0F81C
PS = 30000000.00001F04

```

```

          FFFFFFFF.803EF80C:  STL          R24,#X0060 (R5)
          FFFFFFFF.803EF810:  LDL          R28,#X0138 (R5)
          FFFFFFFF.803EF814:  BIC          R28,R27,R28
          FFFFFFFF.803EF818:  00000138
PC => FFFFFFFF.803EF81C:  HALT
          FFFFFFFF.803EF820:  HALT
          FFFFFFFF.803EF824:  BR          R31,#XFF0000
          FFFFFFFF.803EF828:  LDL          R24,#X0138 (R5)
          FFFFFFFF.803EF82C:  BIC          R24,#X40,R24

```

PS =>

```

          MBZ SPAL          MBZ      IPL VMM MBZ CURMOD INT PRVMOD de
          0   30   000000000000 1F  0   0   KERN  1   KERN

```

Signal Array

```

          Length = 00000003
          Type   = 0000043C
          Arg    = FFFFFFFF.803EF81C  SYS$TTDRIVER+0F81C
          Arg    = 30000000.00001F04

```

```

%SYSTEM-F-OPCDEC, opcode reserved to Digital fault at
PC=FFFFFFFF803EF81C, PS=00001F04

```

Saved Scratch Registers in Mechanism Array

```

R0  = 00000000.00000000  R1  = FFFFFFFF.811998B8  R16 =
00000000.00001000
R17 = FFFFFFFF.8119B1F0  R18 = 00000000.00000010  R19 =
FFFFFFF.810194F0
R20 = 00000000.00000000  R21 = 0000000F.00000000  R22 =
00000000.00000000
R23 = 00000000.00004000  R24 = 00000000.00001000  R25 =
00000000.00000000
R26 = FFFFFFFF.81041474  R27 = 00000000.00004000  R28 =
00000000.00001000

```

```

.
.
.
.
.
.
.

```

(CPU-specific display omitted)

This long display reflects the output of the SHOW CRASH command within the analysis of a system failure on an OpenVMS Alpha system.

```

2. SDA> SHOW CRASH
System crash information
-----
Time of system crash: 12-OCT-2000 11:27:58.02

Version of system: OpenVMS (TM) Alpha Operating System, Version X74B-FT2

System Version Major ID/Minor ID: 3/0

System type: DEC 3000 Model 400

Crash CPU ID/Primary CPU ID: 00/00

Bitmask of CPUs active/available: 00000001/00000001

CPU bugcheck codes:
    CPU 00 -- PGFIPLHI, Pagefault with IPL too high

System State at Time of Page Fault:
-----

Page fault for address 00000000.00046000 occurred at IPL: 8
Memory management flags: 00000000.00000001 (instruction fetch)

Exception Frame:
-----
    R2 = 00000000.00000003
    R3 = FFFFFFFF.810B9280  EXCEPTION_MON+39C80
    R4 = FFFFFFFF.81564540  PCB
    R5 = 00000000.00000088
    R6 = 00000000.000458B0
    R7 = 00000000.7FFA1FC0
    PC = 00000000.00046000
    PS = 20000000.00000803

    00000000.00045FF0:    LDQ            R2, #X0050 (FP)
    00000000.00045FF4:    LDQ            R12, #X0058 (FP)
    00000000.00045FF8:    LDQ            R13, #X0060 (FP)
    00000000.00045FFC:    LDQ            R14, #X0068 (FP)
PC => 00000000.00046000:    BIS            R1, R17, R1
    00000000.00046004:    BIS            R31, #X01, R25
    00000000.00046008:    STQ_U         R1, #X0002 (R10)
    00000000.0004600C:    BSR            R26, #X00738C
    00000000.00046010:    LDQ_U         R16, #X0002 (R10)

PS =>
    MBZ SPAL      MBZ      IPL VMM MBZ CURMOD INT PRVMOD de
      0   20    000000000000 08  0  0   KERN   0  USER
.
.
.
.
(CPU-specific display omitted)
.

```

.

.

This display reflects the output of a SHOW CRASH command within the analysis of a PGFIPLHI bugcheck on an OpenVMS Alpha system.

```

3. SDA> SHOW CRASH /ALL
System crash information
-----

Time of system crash:  1-DEC-2003 13:31:10.50

Version of system: OpenVMS I64 Operating System, Version XA2T-J2S

System Version Major ID/Minor ID: 3/0

System type: HP rx2600  (900MHz/1.5MB)

Crash CPU ID/Primary CPU ID:  01/00

Bitmask of CPUs active/available:  00000003/00000003

CPU bugcheck codes:
    CPU 01 -- database address 8396DD80 -- SSRVEXCEPT, Unexpected
    system se
        1 other -- CPUEXIT, Shutdown requested by another CPU
            CPU 00 -- database address 83864000

System State at Time of Original Exception
-----

Exception Frame at 00000000.7FF43BD0
-----

IPL                =                00
TRAP_TYPE          =                00000008 Access control violation fault
IVT_OFFSET         =                00000800 Data TLB Fault
IIP                = 00000000.00020120 SYS$K_VERSION_08+00100
IIPA               = 00000000.00020110 SYS$K_VERSION_08+000F0
IFA                = 00000000.00000000

IPSR               = 00001010.0A0A6010

IC  MFH MFL AC  BE  RT  TB  LP  DB  SI  DI  PP  SP  DFH DFL DT  PK  I
   UP
1  0  1  0  0  1  0  1  0  0  0  0  0  1  0  1  0  1
   IA  BN  ED  RI  SS  DD  DA  ID  IT  MC  IS  CPL
   0  1  0  0  0  0  0  0  1  0  0  0

PREVSTACK          =                00
BSP                = 00000000.7FF12240

```

```

BSPSTORE      = 00000000.7FF120C0
BSPBASE       = 00000000.7FF120C0
RNAT          = 00000000.00000000

RSC           = 00000000.00000003 LOADRS  BE  PL  MODE
                    0000      0   0   Eager

PFS           = 00000000.00000B9F

SOL           SOF      PPL      PEC      RRB.PR  RRB.FR  RRB.GR  SOR
23. (32-54)  31. (32-62)  0       0.      0.      0.      0.      0.

FLAGS         =                00
STKALIGN      =                000002D0
PREDS         = 00000000.FF562AA3
IHA           = FFFFFFFF.7FF3E120
INTERRUPT_DEPTH =                00

ISR           = 00000804.00000000

                    ED  EI  SO  NI  IR  RS  SP  NA  R  W  X  CODE
                    1  0  0  0  0  0  0  0  1  0  0  0000

ITIR          = 00000000.FFFF0934 KEY      PS
                    FFFF09      0D

IFS           = 80000000.00000593

SOL           SOF      Valid      RRB.PR  RRB.FR  RRB.GR  SOR
11. (32-42)  19. (32-50)  1                0.      0.      0.      0.

B0            = FFFFFFFF.80241AE0 AMAC$EMUL_CALL_NATIVE_C+00340
B1            = 80000000.FFD643B0
B2            = 00000000.00000000
B3            = 00000000.00000000
B4            = 00000000.00000000
B5            = 00000000.7FF43E38
B6            = 00000000.00020110 SYS$K_VERSION_08+000F0
B7            = FFFFFFFF.80A28170 NSA$CHECK_PRIVILEGE_C

GP            = 00000000.00240000
R2            = FFFFFFFF.839B8098 PSB+00058
R3            = E0000000.00000068
R4            = FFFFFFFF.839731C0 PCB
R5            = 00000000.00000008
R6            = 00000000.7FF43F40
R7            = 00000000.00000002
R8            = 00000000.00010000 SYS$K_VERSION_07
R9            = 00000000.00000020
R10           = 00000000.0000003E

```

```

R11          = 00000000.00000001

KSP          = 00000000.7FF43EA0

R13          = 00000000.00000000
R14          = 00000000.00040008 UCB$M_SUPMMSG+00008
R15          = 00000000.00020110 SYS$K_VERSION_08+000F0
R16          = FFFFFFFF.802417A0 AMAC$EMUL_CALL_NATIVE_C
R17          = 00000000.00010004 UCB$M_DELETEUCB+00004
R18          = 00000000.00040000 UCB$M_CHAN_TEAR_DOWN
R19          = 00000000.00040000 UCB$M_CHAN_TEAR_DOWN
R20          = 00000000.7FF43F38
R21          = 00000000.7FF43F80
R22          = 00000000.00040000 UCB$M_CHAN_TEAR_DOWN
R23          = 00000000.00000000
R24          = 00000000.00000000
R25          = 00000000.00000000
R26          = 00000000.00000000
R27          = 00000000.FF565663
R28          = 00000000.00000003
R29          = 00000000.7FF43EA0
R30          = 000007FD.C0000300
R31          = FFFFFFFF.806549D0 PROCESS_MANAGEMENT_MON+677D0

R32          = 00000000.7AC9DBC0
R33          = 00000000.00000001
R34          = 00000000.7FFCF88C MMG$IMGHDRBUF+0008C
R35          = FFFFFFFF.83973528 ARB+00230
R36          = 00000000.00000000
R37          = 00000000.00000000
R38          = FFFFFFFF.80A28410 NSA$CHECK_PRIVILEGE_C+002A0
R39          = 00000000.00000915
R40          = FFFFFFFF.82D01640 SYSTEM_PRIMITIVES+00221440
R41          = 00000000.00000B9F
R42          = 00000000.7FF43EA0

R43/OUT0    = 00000000.7FFCF87C MMG$IMGHDRBUF+0007C
R44/OUT1    = E0000000.00000068
R45/OUT2    = 00000000.00000000
R46/OUT3    = 00000000.FF561663
R47/OUT4    = 00000000.7FFCDA68 CTL$AG_CLIDATA
R48/OUT5    = 00000000.7FFCDBE8 CTL$AG_CLIDATA+00180
R49/OUT6    = 00000000.00000003
R50/OUT7    = FFFFFFFF.839731C0 PCB

NATMASK     =                003A
NATS        = 00000000.00000000
CSD         = CFFFFFFF.00000000
SSD         = CCCC0BAD.BAD0CCCC
LC          = 00000000.00000000
EC          = 00000000.00000000

FPSR        = 0009804C.0270033F SF3    SF2    SF1    SF0    TRAPS
                004C    004C    004E    000C    3F

F6          = 0FFC9.C0000000.00000000
F7          = 1003E.00000000.00000018
F8          = 1000B.FF000000.00000000

```

```

F9          = 10007.A8000000.00000000
F10         = 10003.C2492492.49249249
F11         = 0FFF6.C30C30C3.0C30C30C

```

```
PPREVMODE   = 03
```

Instruction Stream:

```

-----
                { .mfb
SYS$K_VERSION_08+000E0:      nop.m      000000
                           nop.f      000000
                           br.ret.sptk.many b0 ;;
                }
                { .mii
ar.pfs, 0B, 08, 00      SYS$K_VERSION_08+000F0:      alloc      r41 =
                           mov          r29 = r12
                           mov          r42 = r12
                }
                { .mmi
PC => SYS$K_VERSION_08+00100:      ld4          r24 =
[r0] ;;
                           nop.m      000000
                           sxt4        r24 = r24 ;;
                }
                { .mii
SYS$K_VERSION_08+00110:      nop.m      000000
                           sxt4        r14 = r24 ;;
                           cmp.eq      p6, p7 =
r14, r0
                }
                { .mfb
SYS$K_VERSION_08+00120:      nop.m      000000
                           nop.f      000000
                           (p6) br.cond.dpnt.few 0000060
                }

```

Signal Array

```

-----
Length = 00000005
Type   = 0000000C
Arg    = 00000000.00000000
Arg    = 00000000.00000000
Arg    = 00000000.00020120
Arg    = 00000000.00000003
%SYSTEM-F-ACCVIO, access violation, reason mask=00, virtual
address=0000000000000000,
                                           PC=0000000000020120,
PS=00000003

```

CPU 01 Processor state at time of SSRVEXCEPT bugcheck

```

-----
CPU 01 reason for Bugcheck: SSRVEXCEPT, Unexpected system service
exception

```

Process currently executing on this CPU: SYSTEM

Current image file: IPFEX3\$DKB200:[SYS0.][SYSMGR]X.EXE;2

Current IPL: 0 (decimal)

CPU database address: 8396DD80

CPUs Capabilities: QUORUM,RUN

Exception Frame at 00000000.7FF435B0

```

-----
IPL                =                00
TRAP_TYPE          =                00000041      Bugcheck Breakpoint Trap
IVT_OFFSET         =                00002C00      Break Instruction
IIP                = FFFFFFFF.80491E90      EXCEPTION_MON+5E690
IIPA               = FFFFFFFF.80491E80      EXCEPTION_MON+5E680
IFA                = 00000000.00030000      SYS$K_VERSION_01

.
.
.

IIM                = 00000000.00100002      BREAK$C_SYS_BUGCHECK

PPREVMODE         =                00

KR0                = 00000000.00000000
KR1                = 00000000.00000000
KR2                = 00000000.00000000
KR3                = 00000000.00000003
KR4                = 00000000.00000000
KR5 (Next Timer)  = 000000BC.DEA95C24
KR6 (CPUdb VA)   = FFFFFFFF.8396DD80
KR7 (Slot VA)    = FFFFFFFF.86910000

KSP                = 00000000.7FF43880
ESP                = 00000000.7FF68000
SSP                = 00000000.7FFAC000
USP                = 00000000.7AC9DB60

```

No spinlocks currently owned by CPU 01

CPU 00 Processor state at time of CPUEXIT bugcheck

CPU 00 reason for Bugcheck: CPUEXIT, Shutdown requested by another CPU

Process currently executing on this CPU: None

Current IPL: 31 (decimal)

CPU database address: 83864000

CPUs Capabilities: PRIMARY, QUORUM, RUN

Exception Frame at FFFFFFFF.8696F9F0

```
-----
IPL                =                1F
TRAP_TYPE          =                00000041    Bugcheck Breakpoint Trap
IVT_OFFSET         =                00002C00    Break Instruction
IIP                = FFFFFFFF.802F62F0        SYSTEM_SYNCHRONIZATION
+43BF0
IIPA               = FFFFFFFF.802F62F0        SYSTEM_SYNCHRONIZATION
+43BF0
IFA                = FFFFFFFF.86A280C0
.
.
.
IIM                = 00000000.00100002        BREAK$C_SYS_BUGCHECK
PPREVMODE          =                00
KR0                = 00000000.203D0000
KR1                = 00000000.60000000
KR2                = 00000000.00000000
KR3                = 00000000.0001001F
KR4                = 00000000.00000000
KR5 (Next Timer)  = 000000C4.FDFE03C8
KR6 (CPUdb VA)    = FFFFFFFF.83864000
KR7 (Slot VA)     = FFFFFFFF.8690F000
KSP                = FFFFFFFF.8696FCC0
ESP                = FFFFFFFF.86971000
SSP                = FFFFFFFF.86957000
USP                = FFFFFFFF.86957000
```

No spinlocks currently owned by CPU 00

This example from an OpenVMS Integrity server system shows summary information on the crash: the time it occurred, its OpenVMS version, hardware type, and bugcheck codes. This is followed by the exception frame from the exception that triggered the crash, the instruction stream active at the time of the exception, and the signal array that describes the exception. The exception frame from the bugcheck triggered by the original exception is then displayed (that is, the bugcheck on the crash CPU) followed by the bugcheck exception frame for the other CPU in the system.

4.38. SHOW DEVICE

Displays a list of all devices in the system and their associated data structures, or displays the data structures associated with a given device or devices.

Format

```
SHOW DEVICE [ device-name[:] | /ADDRESS=ucb-address | /BITMAP | /CDT=cdt_addr
```

Parameters

device-name

Device or devices for which data structures are to be displayed. The following table lists several uses of the **device-name** parameter:

To display the structures for:	Take the following action:
All devices in the system	Do not specify a device-name (for example, SHOW DEVICE).
A single device	Specify an entire device-name (for example, SHOW DEVICE VTA20).
All devices of a certain type on a single controller	Specify only the device type and controller designation (for example, SHOW DEVICE RTA or SHOW DEVICE RTB).
All devices of a certain type on any controller	Specify only the devicetype (for example, SHOW DEVICE RT).
All devices whose names begin with a certain character or character string	Specify the character or character string (for example, SHOW DEVICE D).
All devices on a single node or HSC	Specify only the node name or HSC name (for example, SHOW DEVICE GREEN\$).
All devices with a certain allocation class	Specify the allocation class including leading and trailing \$, for example, SHOW DEVICE \$63\$.

A colon (:) at the end of a device name is optional.

Note

All qualifiers specific to Memory Channel (CHANNELS, HOMEPAGE, and PDT) are disabled for OpenVMS Integrity server systems.

Qualifiers

/ADDRESS=ucb-address

Indicates the device for which data structure information is to be displayed by the address of its unit control block (UCB). The /ADDRESS qualifier is an alternate method of supplying a device name to the SHOW DEVICE command. If both the device-name parameter and the /ADDRESS qualifier

appear in a single SHOW DEVICE command, SDA responds only to the parameter or qualifier that appears first. /ADDRESS is functionally equivalent to /UCB.

/BITMAP

Displays information about data structures related to Write Bitmap (WBM). Bitmaps are used by Host-Base Volume Shadowing (HBVS) for the implementation of Mini Copy and Host-Based Minimerge (HBMM). If the /BITMAP qualifier is specified with a device that is not an HBVS virtual unit, the error NOSUCHDEV is returned

A device name must be specified. If SHOW DEVICE/BITMAP DSis entered, bitmaps for all HBVS virtual units are displayed.

/CDT=cdt_address

Identifies the device by the address of its Connector Descriptor Table (CDT). This applies to cluster port devices only.

/CHANNELS

Displays information on active Memory Channel channel blocks. This qualifier is ignored for devices other than Memory Channel.

/HOMEPAGE

Displays fields from the Memory Channel Home Page. This qualifier is ignored for devices other than Memory Channel.

/PDT

Displays the Memory Channel Port Descriptor Table. This qualifier is ignored for devices other than Memory Channel.

/UCB=ucb-address

See the description of /ADDRESS, which is functionally equivalent to /UCB.

Description

The SHOW DEVICE command produces several displays taken from system data structures that describe the devices in the system configuration.

If you use the SHOW DEVICE command to display information for more than one device or one or more controllers, it initially produces the **device data block (DDB) list** to provide a brief summary of the devices for which it renders information in subsequent screens.

Information in the **DDB list** appears in five columns, the contents of which are as follows:

- Address of the device data block (DDB)
- Controller name
- Name of the ancillary control process (ACP) associated with the device

- Name of the device driver
- Address of the driver prologue table (DPT)

The SHOW DEVICE command then produces a display of information pertinent to the device controller. This display includes information gathered from the following structures:

- Device data block (DDB)
- Primary channel request block (CRB)
- Interrupt dispatch block (IDB)
- Driver dispatch table (DDT)

If the controller is an HSC controller, SHOW DEVICE also displays information from its system block (SB) and each path block (PB).

Many of these structures contain pointers to other structures and driver routines. Most notably, the DDT display points to various routines located within driver code, such as the start I/O routine, unit initialization routine, and cancel I/O routine.

For each device unit subject to the SHOW DEVICE command, SDA displays information taken from its unit control block, including a list of all I/O request packets (IRPs) in its I/O request queue. For certain mass storage devices, SHOW DEVICE also displays information from the primary class driver data block (CDDB), the volume control block (VCB), and the ACP queue block (AQB). For units that are part of a shadow set, SDA displays a summary of shadow set membership.

As it displays information for a given device unit, SHOW DEVICE defines the symbols of the table below as appropriate:

Symbol	Meaning
UCB	Address of unit control block
SB	Address of system block
ORB	Address of object rights block
DDB	Address of device data block
DDT	Address of driver dispatch table
CRB	Address of channel request block
SUD	Address of supplementary VCB data
SHAD	Address of host-based shadowing data structure
AMB	Associated mailbox UCB pointer
IRP	Address of I/O request packet
2P_UCB	Address of alternate UCB for dual-pathed device
LNMB	Address of logical name block for mailbox
PDT	Address of port descriptor table
CDDB	Address of class driver descriptor block for MSCP served device
2P_CDDB	Address of alternate CDDB for MSCP served device

Symbol	Meaning
RWAITCNT	Resource wait count for MSCP served device
VCB	Address of volume control block for mounted device
2P_DDB	Address of secondary DDB
VP_IRP	Address of volume processing IRP
MMB	Address of merge management block
CPYLOCK	ID of copier lock
VU_TO	Virtual Unit Timeout (seconds)
VU_UCB	UCB address of Virtual Unit
MPDEV	Address of multipath data structure
PRIMARY_UCB	UCB address for primary path
CURRENT_UCB	UCB address for current path

If you are examining a driver-related system failure, you may find it helpful to issue a `SHOW STACK` command after the appropriate `SHOW DEVICE` command, to examine the stack for any of these symbols. Note, however, that although the `SHOW DEVICE` command defines those symbols relevant to the last device unit it has displayed, and redefines symbols relevant to any subsequently displayed device unit, it does not undefine symbols. (For instance, `SHOW DEVICE DUA0` defines the symbol `PDT`, but `SHOW DEVICE MBA0` does not undefine it, even though the `PDT` structure is not associated with a mailbox device.) To maintain the accuracy of such symbols that appear in the stack listing, use the `DEFINE` command to modify the symbol name. For example:

```
SDA> DEFINE DUA0_PDT PDT
SDA> DEFINE MBA0_UCB UCB
```

See the descriptions of the `READ` and `FORMAT` commands for additional information on defining and examining the contents of device data structures.

Examples

```
1. SDA> SHOW DEVICE/ADDRESS=8041E540
OPA0                               VT300_Series          UCB address
 8041E540

Device status: 00000010 online
Characteristics: 0C040007 rec,ccl,trm,avl,idv,odv
                 00000200 nnm
Owner UIC [000001 ,000004] Operation count          160   ORB address
 8041E4E8
  PID          00010008 Error count                  0     DDB address
 8041E3F8
Class/Type          42/70 Reference count            2     DDT address
 8041E438
Def. buf. size      80   BOFF                        00000001   CRB address
 8041E740
DEVDEPEND           180093A0 Byte count              0000012C   I/O wait queue
 8041E5AC
DEVDEPN2           FB101000 SVAPTE                  80537B80
DEVDEPN3           00000000 DEVSTS                    00000001
FLCK index          3A
```

```
DLCK address      8041E880
*** I/O request queue is empty ***
```

This example reproduces the SHOW DEVICE display for a single device unit, OPA0. Whereas this display lists information from the UCB for OPA0, including some addresses of key data structures and a list of pending I/O requests for the unit, it does not display information about the controller or its device driver. To display the latter information, specify the device-name as OPA (for example, SHOW DEVICE OPA).

2. SDA> SHOW DEVICE DU
I/O data structures

```
-----
                                DDB list
                                -----
                                Address      Controller      ACP      Driver      DPT
                                -----      -
                                80D0B3C0    BLUES$DUA      F11XQP    SYS$DKDRIVER 807735B0
                                8000B2B8    RED$DUA        F11XQP    SYS$DKDRIVER 807735B0
                                80D08BA0    BIGTOP$DUA     F11XQP    SYS$DKDRIVER 807735B0
                                80D08AE0    TIMEIN$DUA     F11XQP    SYS$DKDRIVER 807735B0
                                .
                                .
                                .
                                Press RETURN for more.
                                .
                                .
                                .
```

This excerpt from the output of the SHOW DEVICE DU command illustrates the format of the DDB list. In this case, the DDB list concerns itself with those devices whose device type begins with DU. It displays devices of these types attached to various HSCs (RED\$ and BLUES\$) and systems in a cluster (BIGTOP\$ and TIMEIN\$).

4.39. SHOW DUMP

Displays formatted information from the header, error log buffers, logical memory blocks (LMBs), memory map, compression data, and a summary of the dump. Also displays hexadecimal information of individual blocks.

Format

```
SHOW DUMP [/ALL
| /BLOCK[=m [{:|;}n] ]
| /COLLECTION [= {ALL|n} ]
| /COMPRESSION_MAP [=m [:n[:p[{:|;}q]]]]
| /ERROR_LOGS
| /FILE = {COLLECTION | DUMP [=n]}
```

| /HEADER
 | /LMB [= {ALL|n}]
 | /MEMORY_MAP
 | /SUMMARY]

Parameters

None.

Qualifiers

/ALL

Displays the equivalent to specifying all the /SUMMARY, /HEADER, /ERROR_LOGS, /COMPRESSION_MAP, /LMB=ALL, /MEMORY_MAP, and /COLLECTION qualifiers.

/BLOCK [=m [[:;]n]]

Displays a hexadecimal dump of one or more blocks. You can specify ranges by using the following syntax:

<i>no value</i>	Displays next block
<i>m</i>	Displays single block
<i>m:n</i>	Displays a range of blocks from <i>m</i> to <i>n</i> , inclusive
<i>m;n</i>	Displays a range of blocks starting at <i>m</i> and continuing for <i>n</i> blocks

/COLLECTION [= {ALL|n}]

Displays the contents of the file identification or unwind data collection (on Integrity servers only) appended to a copy of the dump using COPY/COLLECT or written to a separate collection file using COLLECT/SAVE. By default, a summary of the collection is displayed. You can specify that the details of a single entry or all entries are to be displayed. *n* is the start block number of the collection entry, as displayed in the collection summary.

/COMPRESSION_MAP [=m [:n[:p[[:;]q]]]]

In a compressed dump, displays details of the compression data. You can specify levels of detail by using the following syntax, where m,n,p,q may each be wildcarded (*):

<i>no value</i>	Displays a summary of all compression map blocks.
<i>m</i>	Displays contents of a single compression map block.
<i>m:n</i>	Displays details of single compression map entry.
<i>m:n:p</i>	Displays compressed and raw data for the specified compression section (item <i>p</i> in section

	<i>m:n</i>). Note that <i>m:n:p</i> may contain wildcards (*).
<i>m:n:p:q</i>	Displays compressed and raw data for the specified range of compression sections (items <i>p</i> to <i>q</i> inclusive in section <i>m:n</i>).
<i>m:n:p;q</i>	Displays compressed and raw data for the specified range of compression sections (<i>q</i> items starting from item <i>p</i> in section <i>m:n</i>).

/ERROR_LOGS

Displays a summary of the error log buffers.

/FILE = {COLLECTION | DUMP [=n]}

If analyzing multiple dump files from a partial dump copy, or if a separate collection file is in use, the /FILE qualifier indicates whether the SHOW DUMP command applies to one of the dump files or to the collection file.

If /FILE is not specified, by default, the SHOW DUMP/SUMMARY, SHOW DUMP/HEADER, SHOW DUMP/COLLECTION, and SHOW DUMP/ALL commands apply to all open files, and the SHOW DUMP/LMB=ALL and SHOW DUMP/COMPRESSION commands apply to all open dump files. If /FILE=DUMP is specified without a file number, then these commands apply to the primary dump file.

By default, SHOW DUMP/BLOCK applies to the primary dump file. By default, SHOW DUMP/LMB=n and SHOW DUMP/COMPRESSION=n apply to the primary dump file or to the dump file for which the command was last used.

All other qualifiers are applicable only to the primary dump file.

/HEADER

Displays the formatted contents of the dump header.

/LMB[= {ALL|n}]

In a selective dump, displays the formatted contents of logical memory block (LMB) headers and the virtual address (VA) ranges within the LMB. You can specify the LMBs to be displayed by using the following syntax:

<i>no value</i>	Displays next LMB
<i>n</i>	Displays LMB at block <i>n</i> of the dump
ALL	Displays all LMBs

/MEMORY_MAP

In a full dump, displays the contents of the memory map.

/SUMMARY

Displays a summary of the dump. This is the default.

Description

The SHOW DUMP command displays information about the structure of the dump file. It displays the header, the error log buffers, and, if appropriate, the compression map, the logical memory block (LMB) headers, the memory map, the file identification collection, and the unwind data collection (on Integrity server systems only). Use this command when troubleshooting dump analysis problems.

Examples

1. SDA> SHOW DUMP/SUMMARY

```
Summary of dump file DKA300:[SYS0.SYSEXEXE]SYSDUMP.DMP;8
```

```
-----
Dump type:                Compressed selective
Size of dump file:        000203A0/000203A0 (132000./132000.)
Highest VBN written:      0000D407          (54279.)
Uncompressed equivalent:  0001AF1C          (110364.)
Compression ratio:        2.03:1          (49.2%)
```

Uncomp VBN	Uncomp blocks	Dump file section	VBN	Blocks
-----	-----			
		Dump header	00000001	00000002
		Error log buffers	00000003	00000020
		Compression map	00000023	00000010
		LMB 0000 (PT space)	00000033	00000038
		00000033 000000D2		
		LMB 0001 (S0/S1 space)	0000006B	0000621B
		00000105 000095A5		
		LMB 0002 (S2 space)	00006286	000001A3
		000096AA 00000352		
		LMB 0003 (Page tables of key process "SYSTEM")	00006429	00000005
		000099FC 00000062		
		LMB 0004 (Memory of key process "SYSTEM")	0000642E	00000071
		00009A5E 00000342		
		.		
		.		
		LMB 0003 (Page tables of key process "NETACP")	0000697B	00000009
		0000AE14 00000052		
		LMB 0004 (Memory of key process "NETACP")	00006984	000013F7
		0000AE66 00001F42		
		LMB 0005 (Key global pages)	00007D7B	000002BA
		0000CDA8 00000312		
		LMB 0006 (Page tables of process "DTWM")	00008035	00000013
		0000D0BA 00000082		
		LMB 0007 (Memory of process "DTWM")	00008048	000013A3
		0000D13C 000022E4		
		.		
		.		
		LMB 0006 (Page tables of process "Milord_FTA1:")	0000C5E3	00000005
		00019A44 00000062		


```

LMB 0007 (Memory of process "Milord_FTA1:")      0000C5E8 00000074
00019AA6 00000222
LMB 0008 (Remaining global pages)              0000C65C 00000DAC
00019CC8 00001255

```

This example of the SHOW DUMP/SUMMARY command gives a summary of a selective dump.

2. SDA> SHOW DUMP/HEADER

Dump header

```

-----
Header field          Meaning
Value
-----
DMP$W_FLAGS          Flags
0FC1
DMP$V_OLDDUMP:      Dump has been analyzed
DMP$V_WRITECOMP:    Dump write was completed
DMP$V_ERRLOGCOMP:   Error log buffers written
DMP$V_DUMP_STYLE:   Selective dump
                    Verbose messages
                    Dump off system disk
                    Compressed
DMP$B_FLAGS2         Additional flags
09
DMP$V_COMPRESSED:   Dump is compressed
DMP$V_ALPHADUMP:    This is an OpenVMS Alpha dump
DMP$Q_SYSIDENT      System version
"X69G-FT1"
DMP$Q_LINKTIME      Base image link date/time      " 8-JUN-1996
02:07:27.31"
DMP$L_SYSVVER       Base image version
03000000
DMP$W_DUMPVER       Dump version
0704
DMP$L_DUMPBLOCKCNT  Count of blocks dumped for memory
0000D3D5
DMP$L_NOCOMPBLOCKCNT Uncompressed blocks dumped for memory
0001AEEA
DMP$L_SAVEPRCNT     Number of processes saved
00000014
.
.
.
EMB$Q_CR_TIME       Crash date/time      " 3-JUL-1996
09:30:13.36"
EMB$L_CR_CODE       Bugcheck code
"SSRVEXCEPT"
EMB$B_CR_SCS_NAME   Node name
"SWPCTX "
EMB$T_CR_HW_NAME    Model name      "DEC 3000
Model 400"
EMB$T_CR_LNAME      Process name
"SYSTEM"
DMP$L_CHECKSUM      Dump header checksum
439E5E91

```

This example of the SHOW DUMP/HEADER command shows the information in the header.

3. SDA> SHOW DUMP/COLLECTION

File and unwind data collection

```
Collection start VBN:      0002155B
Collection end VBN:       00022071
Collection block count:   00000B17
```

VBN	Blocks	Contents
0002155B	000000C1	Unwind data segment 00000001 of _\$30\$DKB200:[VMS \$COMMON.SYSEXE]DCL.EXE;1
0002161C	00000001	Unwind data segment 00000001 of _\$30\$DKB200:[VMS \$COMMON.SYSEXE]USB\$UC...
0002161D	0000000C	Unwind data segment 00000008 of _\$30\$DKB200:[VMS \$COMMON.SYSEXE]USB\$UC...
.	.	.
0002200F	0000001F	Unwind data segment 00000007 of _\$30\$DKB200:[VMS \$COMMON.SYSEXE]LATACP...
0002202E	00000006	Unwind data segment 0000000B of _\$30\$DKB200:[VMS \$COMMON.SYSEXE]LATACP...
00022034	00000001	Unwind data segment 00000002 of _\$30\$DKB200:[BISHOP]CMEXEC_LOOP.EXE;1
00022035	00000001	File data for _\$30\$DKA0:
00022036	0000003B	File data for _\$30\$DKB200:
00022071	00000001	Disk data

This example of the SHOW DUMP/COLLECTION command shows the contents of the file identification and unwind data collection appended to a system dump when it was copied using the SDA command COPY/COLLECT. Note that unwind data segments are found only in system dumps taken on OpenVMS Integrity server systems.

4.40. SHOW EFI (Integrity servers Only)

Displays information from the Extensible Firmware Interface (EFI) data structures. Currently, the only display provided by SDA is the EFI memory map.

Format

```
SHOW EFI /MEMMAP [=ALL] [range]
```

Parameters

range

The entry or range of entries to be displayed, expressed using the following syntax:

<i>m</i>	Displays entry <i>m</i>
<i>m:n</i>	Displays the entries from <i>m</i> to <i>n</i>
<i>m;n</i>	Displays <i>n</i> entries starting at <i>m</i>

You cannot specify a range with /MEMMAP=ALL.

Qualifiers

/MEMMAP [=ALL]

Displays the EFI memory map. This qualifier is required. By default, only entries in the EFI memory map with the RUNTIME attribute are displayed. If /MEMMAP=ALL is specified, all entries are displayed.

You cannot specify /MEMMAP=ALL and also supply a range of entries to be displayed.

Description

SDA locates the EFI memory map in the system or dump and displays the contents. If no range is given, SDA also displays information about the location and size of the memory map.

Examples

1. SDA> SHOW EFI/MEMMAP

```
EFI Memory Map
```

```
-----
```

```
Memory map address:      FFFFF802.06402000
Entry count:             00000025
Size of entry:           00000030
```

Entry Pages (4KB)	Memory Type Attributes	Physical Address	Virtual Address
0003	Runtime_Services_Code	00000000.000C0000	FFFFFF802.00000000
00000000.00000040	80000000.00000001 UC	Runtime	
0016	Runtime_Services_Data	00000000.3F048000	FFFFFF802.00040000
00000000.00000304	80000000.00000008 UCE	Runtime	
0017	Runtime_Services_Code	00000000.3F34C000	FFFFFF802.00344000
00000000.0000003C	80000000.00000008 UCE	Runtime	
0019	Runtime_Services_Data	00000000.3F3E2000	FFFFFF802.00380000
00000000.00000012	80000000.00000008 UCE	Runtime	
001A	Runtime_Services_Code	00000000.3F3F4000	FFFFFF802.00392000
00000000.0000006E	80000000.00000008 UCE	Runtime	
001B	Runtime_Services_Data	00000000.3F462000	FFFFFF802.00400000
00000000.00000182	80000000.00000008 UCE	Runtime	
001C	Runtime_Services_Code	00000000.3F5E4000	FFFFFF802.00582000
00000000.000004DC	80000000.00000008 UCE	Runtime	
001D	PAL_Code	00000000.3FAC0000	FFFFFF802.00A80000
00000000.00000040	80000000.00000008 UCE	Runtime	
0020	Runtime_Services_Data	00000000.3FB38000	FFFFFF802.00AC0000
00000000.000004C8	80000000.00000008 UCE	Runtime	
0022	Memory_Mapped_IO	00000000.FED00000	FFFFFF802.01000000
00000000.00001300	80000000.00000001 UC	Runtime	
0024	Mem_Map_IO_Port_Space	0003FFFF.FC000000	FFFFFF802.02400000
00000000.00004000	80000000.00000001 UC	Runtime	

This example shows a typical display from the SHOW EFI/MEMMAP command.

4.41. SHOW EXCEPTION_FRAME

Displays the contents of the exception frame at the given address or searches to display a one-line summary of all exception frames found on all applicable stacks.

Format

```
SHOW EXCEPTION_FRAME {address | [/SUMMARY] [range]}
```

Parameter

address

Address of the exception frame.

range

Range of addresses specifiable as *start:end* or *start:length*.

Qualifier

/SUMMARY (D)

- The /SUMMARY qualifier is the default.
- SHOW EXCEPTION and SHOW EXCEPTION *range* imply /SUMMARY.
- If a range, either *start:end* or *start:length*, is given, then that range is searched instead of the stacks.

Description

Displays the contents of the exception frame at the given address (which is rounded down to an octaword-aligned address), or searches to display a one-line summary of all exception frames found on all applicable stacks.

Under some circumstances, the exception frame of the actual bugcheck is copied (by BUGCHECK) to the system stack for the CPU. Since this stack is also searched, multiple hits may occur for this exception frame.

On Alpha, the search for exception frames relies on valid processor status (PS) values in the PS offset from each possible 64-byte-aligned start address for an exception frame. Since only some of the bits in the PS can be validated, there may be frames displayed that are not exception frames (false positives). Do not assume that each frame displayed is actually an exception frame without further investigation.

On Integrity servers, the search for exception frames is focused on the type/subtype offsets from each possible octaword-aligned start address for an exception frame. Thus, it is likely that frames displayed are exception frames.

Examples

1. SDA> SHOW EXCEPTION
Exception Frame Summary

Exception Frame Service_Number	Type	Stack	IIP / Ret_Addr	Trap_Type /
00000000.7FF43540	ORIGINAL_INTSTK	Kernel	FFFFFFFF.8048DB70	00000041
	Bugcheck Breakpoint Trap			
00000000.7FF43BA0	INTSTK	Kernel	00000000.00020200	00000008
	Access control violation fault			
00000000.7FF43F40	SSENTRY	Kernel	00000000.00020090	01000019 SYS
	\$CMKRNL			

The SHOW EXCEPTION_FRAME command example displays the summary.

Examples of the display of the contents of an exception frame are available in the SHOW CRASH description.

4.42. SHOW EXECUTIVE

Displays the location and size of each loadable image that makes up the executive.

Format

```
SHOW EXECUTIVE [execlet-name | /ALL | /SUMMARY (D)]
```

Parameter

execlet-name

Displays detailed data for the specified loadable image only. If you use wildcards in **execlet-name**, SDA displays detailed data for all matching loadable images.

If the command is specified with no parameter or qualifier, the default is to display one line of data for each loadable image.

Qualifiers

/ALL

Displays detailed data for all loadable images.

/SUMMARY

Displays a single line of data for all loadable images. This is the default.

Description

The executive consists of two base images and a number of other executive images.

The base image called SYS\$BASE_IMAGE.EXE contains:

- Symbol vectors for universal executive routines and data cells
- Procedure descriptors for universal executive routines
- Globally referenced data cells

The base image called `SY$PUBLIC_VECTORS.EXE` contains:

- Symbol vectors for system service procedures
- Procedure descriptors for system services
- Transfer routines for system services

The base images are the pathways to routines and system service procedures in the other executive images.

The `SHOW EXECUTIVE` command lists the location and size of each executive image with other information such as link date and time. It can enable you to determine whether a given memory address falls within the range occupied by a particular image. (Table 4.1 describes the contents of each executive image.)

`SHOW EXECUTIVE` also displays the base address and length for each nonzero length image section.

On OpenVMS Alpha the execlets can be sliced; on OpenVMS Integrity servers all execlets are sliced. This means each different image section can be relocated in system memory so that the sections are no longer contiguous. The `SHOW EXECUTIVE` display contains information on where each image section resides.

The difference between a sliced image and a non-sliced image in the display is that the base, the end, and the length of a sliced image are blank. Only the image section base, end, and length are valid.

On Alpha, there are six different image section types: nonpaged read only, nonpaged read-write, paged read only, paged read-write, init, and fixup. Each section type can occur only once. Only the image sections loaded into system memory are displayed.

On Integrity servers, there are six different image section types: code, short data, read-only data, read-write data, init, and fixup. Some section types can occur more than once. Only the image sections loaded into system memory are displayed.

The `MAP` command makes it easier to find out in which execlet an address resides. See the description of the `MAP` command for details.

By default, SDA displays each location within an executive image as an offset from the beginning of the image, for instance, `EXCEPTION+00282`. Similarly, those symbols that represent system services point to the transfer routine in `SY$PUBLIC_VECTORS.EXE` and not to the actual system service procedure. When tracing the course of a system failure through the listings of modules contained within a given executive image, you may find it useful to load into the SDA symbol table all global symbols and global entry points defined within one or all executive images. See the description of the `READ` command for additional information.

The `SHOW EXECUTIVE` command usually shows all components of the executive, as illustrated in the following example. In rare circumstances, you may obtain a partial listing. For instance, after it has loaded the `EXCEPTION` module (in the `INIT` phase of system initialization), the system can successfully post a bugcheck exception and save a crash dump before loading all the executive images that are normally loaded.

Examples

1.

```
SDA> SHOW EXECUTIVE
VMS Executive layout summary
-----
```

Image Length	LDRIMG SymVec	SeqNum	Base	End
SYS\$MADDRIVER 00000000.0001C000	8161BCC0	00000094	FFFFFFFF.837C2000	FFFFFFFF.837DDFFF
SYS\$DADDRIVER 00000000.00010000	8161AB80	00000092	FFFFFFFF.82238000	FFFFFFFF.82247FFF
SYS\$LASTDRIVER 00000000.0001C000	81617540	00000090	FFFFFFFF.813DA000	FFFFFFFF.813F5FFF
SYS\$LTDRIVER 00000000.00038000	81611B40	0000008E	FFFFFFFF.813A2000	FFFFFFFF.813D9FFF
LAT\$RATING 00000000.00008000	81611440	0000008C	FFFFFFFF.8139A000	FFFFFFFF.813A1FFF
PWIPDRIVER 00000000.00014000	8160B440	0000008A	FFFFFFFF.81386000	FFFFFFFF.81399FFF
.				
.				
ERRORLOG		814195C0	00000014	--< sliced >--
SYSTEM_SYNCHRONIZATION		81418840	00000012	--< sliced >--
SYSTEM_PRIMITIVES		81417AC0	00000010	--< sliced >--
SYSTEM_DEBUG FFFFFFFF.833E5FFF 00000000.00064000		81416D40	0000000E	FFFFFFFF.83382000
SYS\$OPDRIVER		81415FC0	0000000C	--< sliced >--
SYS\$ESBTDRIVER		81415240	0000000A	--< sliced >--

The SHOW EXECUTIVE command displays a summary list of the executive images. The display has been moved left to fit within the page boundaries of the manual.

2. SDA> SHOW EXECUTIVE EX*
VMS Executive layout

Image ImageOff SymVec	Base	End	Length
EXCEPTION_MON			
Data (read/write) 00000000.00000014 00010000	FFFFFFFF.841BAC00	FFFFFFFF.841BAC13	
Data (read/write) 00000000.00000004 00014000	FFFFFFFF.841BAE00	FFFFFFFF.841BAE03	
Code 00000000.000EA760 00018000	FFFFFFFF.8041E600	FFFFFFFF.80508D5F	
Data (read only) 00000000.00007790 00104000	FFFFFFFF.841BB000	FFFFFFFF.841C278F	
Data (read/write) 00000000.0000DCA0 0010C000	FFFFFFFF.841C2800	FFFFFFFF.841D049F	
Data (read/write) 00000000.00000014 0011C000	FFFFFFFF.841D0600	FFFFFFFF.841D0613	
Data (read only) 00000000.00007594 00120000	FFFFFFFF.841D0800	FFFFFFFF.841D7D93	
Short data 00000000.00007448 00130000	FFFFFFFF.841D7E00	FFFFFFFF.841DF247	

```

Linked 2-APR-2004 13:08 LDRIMG 84891900 SeqNum 00000022 GP
FFFFFFFF.843D7E00

EXEC_INIT
Code          FFFFFFFF.80327700 FFFFFFFF.803B304F
00000000.0008B950 00010000
Data (read only) FFFFFFFF.84196C00 FFFFFFFF.8419D62F
00000000.00006A30 0009C000
Data (read/write) FFFFFFFF.8419D800 FFFFFFFF.841A7987
00000000.0000A188 000A4000
Short data      FFFFFFFF.841A7A00 FFFFFFFF.841AA2DF
00000000.000028E0 000B0000
Linked 23-MAR-2004 15:02 LDRIMG 84889040 SeqNum 0000001E GP
FFFFFFFF.843A7A00

```

This example from Integrity servers displays the use of the wildcard with the `SHOW EXECUTIVE` command. The display has been moved left to fit within the page boundaries of the manual.

4.43. SHOW GALAXY

Displays a brief one-page summary of the state of the Galaxy and all the instances in the Galaxy.

Format

`SHOW GALAXY`

Parameters

None.

Qualifiers

None.

Examples

```

SDA> SHOW GALAXY
Galaxy summary
-----
  GMDB address          Creator node ID  Revision          Creation time
-----
  FFFFFFFF.7F234000    00000001        1.0              31-MAR-1999 13:15:08.08
  O

Node ID      NODEB address      Name      Version          Join time
-----
00000000    FFFFFFFF.7F236000  ANDA1A    1.0              31-MAR-1999 14:11:09.08
00000001    FFFFFFFF.7F236200  ANDA2A    1.0              31-MAR-1999 14:10:49.06
00000002    FFFFFFFF.7F236400  ANDA3A    1.0              31-MAR-1999 14:13:26.16
00000003    FFFFFFFF.7F236600  - Node block is empty -

```

This `SHOW GALAXY` example shows the summary of the state of the Galaxy.

4.44. SHOW GCT

Displays the contents of the Galaxy configuration tree either in summary (hierarchical format) or in detail, node by node.

Format

```
SHOW GCT [/ADDRESS=n | /ALL | /HANDLE | /OWNER=n
| /SUMMARY (D) | /TYPE=type ]
[/CHILDREN] | [/FULL]
```

Parameters

None.

Qualifiers

/ADDRESS=*n*

Displays the Galaxy configuration tree (GCT) node at the given address.

/ALL

Provides a detailed display of all nodes in the tree.

/CHILDREN

When used with /ADDRESS=*n* or /HANDLE=*n*, the /CHILDREN qualifier causes SDA to display all nodes in the configuration tree that are children of the specified node.

/FULL

When used with /CHILDREN, /OWNER=*n*, or /TYPE=*type*, the /FULL qualifier causes SDA to provide a detailed display of each node.

/HANDLE=*n*

Provides a detailed display of the Galaxy configuration tree (GCT) node with the given handle.

/OWNER=*n*

Displays all nodes in the tree currently owned by the node with the given handle.

/SUMMARY

Provides a summary display of the Galaxy configuration tree (GCT) in hierarchical form. This qualifier is the default.

/TYPE=*type*

Displays all nodes in the tree of the given type, which can be one of the following:

BUS	CAB	COMMUNITY
-----	-----	-----------

CORE	CPU	CPU_MODULE
EXP_CHASSIS	FRU_DESC	FRU_ROOT
HARD_PARTITION	HOSE	HW_ROOT
IO_CTRL	IOP	MEMORY_CTRL
MEMORY_DESC	MEMORY_SUB	PARTITION
POWER_ENVIR	PSEUDO	RISER
ROOT	SBB	SLOT
SMB	SOC	SOCKET
SW_ROOT	SYS_CHASSIS	SYS_INTER_SWITCH
TEMPLATE_ROOT	THREAD	

The type given may be an exact match, in which case just that type is displayed (for example, a CPU); or a partial match, in which case all matching types are displayed (for example, /TYPE=CP displays both CPU and CPU_MODULE nodes).

Description

Examples

1. SDA> SHOW GCT

Galaxy Configuration Tree summary

Base address of Config Tree: FFFFFFFF.83694040 (2 pages)

Initial Current Name/Min PA/ OS type/Max PA/

Handle Hierarchy Id Owner Owner Base PA Size (bytes) Flags

```
-----
00000000 Root 00000000.00000000 414C4147-5958-0030-0000-.....
|
00000240 | _HW_Root 00000000.00000000
00000280 | | _IOP 00000000.00000006 00001800 000000A0.00000000
000000AF.FFFFFFFF
00000300 | | _IOP 00000000.00000007 00001700 000000B0.00000000
000000BF.FFFFFFFF
00000380 | | _IOP 00000000.00000008 00001600 000000C0.00000000
000000CF.FFFFFFFF
00000400 | | _CPU_Module 00000000.00000000 00001580
00000440 | | | _CPU 00000000.09000000 00001600 Primary
00000480 | | | _CPU 00000000.1B000001 00001600 00001800
000004C0 | | _CPU_Module 00000000.00000001 00001580
00000500 | | | _CPU 00000000.1B000002 00001600 00001800
00000540 | | | _CPU 00000000.10000003 00001600 00001700
00000580 | | _CPU_Module 00000000.00000002 00001580
000005C0 | | | _CPU 00000000.07000004 00001700 Primary
00000600 | | | _CPU 00000000.0A000005 00001700 00001800
00000640 | | _CPU_Module 00000000.00000003 00001580
00000680 | | | _CPU 00000000.07000006 00001800 Primary
000006C0 | | | _CPU 00000000.0C000007 00001800 00001600
00000700 | | _Memory_Sub 00000000.00000000 00001580 00000000.00000000
00000000.FFFFFFFF
00000780 | | _Memory_Ctrl 00000000.00000005 00001600
```

```

000007C0 | |__Memory_Desc 00000000.00000000 00001600 00000000.00000000
00000000.40000000
| | |__Fragment 00001600 00000000.00000000 00000000.00200000 Console
Private Base
| | |__Fragment 00001600 00000000.00200000 00000000.3FD7E000 Private Base
| | |__Fragment 00001600 00000000.3FF7E000 00000000.00082000 Console
Private Base
00000A40 | |__Memory_Desc 00000000.40000000 00001700 00000000.40000000
00000000.40000000
| | |__Fragment 00001700 00000000.40000000 00000000.00200000 Console
Private Base
| | |__Fragment 00001700 00000000.40200000 00000000.3FD7E000 Private Base
| | |__Fragment 00001700 00000000.7FF7E000 00000000.00082000 Console
Private Base
00000CC0 | |__Memory_Desc 00000000.80000000 00001800 00000000.80000000
00000000.40000000
| | |__Fragment 00001800 00000000.80000000 00000000.00200000 Console
Private Base
| | |__Fragment 00001800 00000000.80200000 00000000.3FD7E000 Private Base
| | |__Fragment 00001800 00000000.BFF7E000 00000000.00082000 Console
Private Base
00000F40 | |__Memory_Desc 00000000.C0000000 00001580 00000000.C0000000
00000000.40000000
| |__Fragment 00001580 00000000.C0000000 00000000.40000000 Shared
|
000011C0 |__SW_Root 00000000.00000000
00001580 | |__Community 00000000.00000000 000011C0
00001600 | |__Partition 00000000.00000000 00001580 ANDA1A OpenVMS Alpha
00001700 | |__Partition 00000000.00000001 00001580 ANDA2A OpenVMS Alpha
00001800 | |__Partition 00000000.00000002 00001580 ANDA3A OpenVMS Alpha
|
00001200 |__Template_Root 00000000.00000000
00001240 |__IOP 00000000.00000000
000012C0 |__CPU 00000000.00000000
00001300 |__Memory_Desc 00000000.00000000 00000000.02000000

```

This command shows the summary (hierarchical) display of the configuration tree.

- SDA> SHOW GCT/HANDLE=00000700

```
Galaxy Configuration Tree
-----
```

```

Handle:                                00000700   Address:
  FFFFFFFF.83694740
Node type:                               Memory_Sub   Size:
  0080
Id:                                       00000000.00000000   Flags:
  00000000.00000001 Hardware

```

Related nodes:

Node relationship	Handle	Type	Id
Initial owner	00001580	Community	00000000.00000000

```

Current owner      -<Same>-
Parent            00000240    HW_Root
00000000.00000000
Previous sibling   00000640    CPU_Module
00000000.00000003
Next sibling       -<None>-
Child             00000780    Memory_Ctrl
00000000.00000005
Configuration binding 00000240    HW_Root
00000000.00000000
Affinity binding  00000240    HW_Root
00000000.00000000

```

```
Min. physical address: 00000000.00000000
```

```
Max. physical address: 00000000.FFFFFFFF
```

This command shows the detailed display of the specified node.

4.45. SHOW GLOBAL_SECTION_TABLE

Displays information contained in the global section table, including pageable sections of loadable images. Functionally equivalent to SHOW GST.

Format

```
SHOW GLOBAL_SECTION_TABLE [ /SECTION_INDEX=n ]
```

```
SHOW GST [ /SECTION_INDEX=n ]
```

Parameters

None.

Qualifiers

```
/SECTION_INDEX=n
```

Displays only the global section table entry for the specified section.

Description

Displays the entire contents of the global section table, unless you specify the qualifier /SECTION_INDEX. This command is equivalent to SHOW PROCESS/PROCESS_SECTION_TABLE/SYSTEM. SDA displays the information in the table below for each GST entry.

Part	Definition
INDEX	Index number of the entry. Entries in the global section table begin at the highest location in the table, and the table expands toward lower addresses.
ADDRESS	Address of the global section table entry.
SECT/GPTE	Virtual address that marks the beginning of the first page of the section described by this entry,

Part	Definition
	if a loadable image; or the virtual address of the global page table entry for the first page, if a global section.
GSD	Address of the corresponding Global Section Descriptor. This field is zero for loadable images.
PAGELETS	Length of the global section. This is in units of pagelets, except for a PFN-mapped section in which the units are pages.
VCN	Virtual block number. The number of the file's virtual block that is mapped into the section's first page.
WINDOW	Address of the window control block on which the section file is open.
REFCNT	Number of pages of this section that are currently mapped.
FLINK	Forward link. The pointer to the next entry in the GST list.
BLINK	Backward link. The pointer to the previous entry in the GST list.
FLAGS	Flags that describe the access that the system and processes have to the global section.

Examples

1. SDA> SHOW GST

Global Section Table

Global section table information

Last entry allocated 00000238

First free entry 00000000

Global section table

Index	Address	Sect/GPTE	Addr	CCB/GSD	Pagelets	VCN	Window	Refcnt	Flink	Blink	Flags
-------	---------	-----------	------	---------	----------	-----	--------	--------	-------	-------	-------

00000001	81409FD8	FFFFFFFF	.83384000	00000000	00000025	00000003	81419E40				
----------	----------	----------	-----------	----------	----------	----------	----------	--	--	--	--

00000003 0000 0000 AMOD=KRNL

00000002	81409FB0	FFFFFFFF	.833AE000	00000000	00000064	00000220	8141A040				
----------	----------	----------	-----------	----------	----------	----------	----------	--	--	--	--

00000007 0000 0000 AMOD=KRNL

00000003	81409F88	FFFFFFFF	.83312000	00000000	00000001	0000063A	81450BC0				
----------	----------	----------	-----------	----------	----------	----------	----------	--	--	--	--

00000001 0000 0000 CRF WRT AMOD=KRNL

00000004	81409F60	FFFFFFFF	.833C0000	00000000	00000003	00000003	814233C0				
----------	----------	----------	-----------	----------	----------	----------	----------	--	--	--	--

00000001 0000 0000 AMOD=KRNL

00000005	81409F38	FFFFFFE0	.00058890	82065C70	00000002	0000000D	814F9AC0				
----------	----------	----------	-----------	----------	----------	----------	----------	--	--	--	--

00000003 0005 0005 WRTMOD=EXEC AMOD=USER PERM

Name = INS\$82065BC0_003 SYSGBL

File = DISK\$X97D_R2Y:[VMS\$COMMON.SYSLIB]DECW\$TRANSPORT_COMMON.EXE;1

00000006	81409F10	FFFFFFFF	.833E6000	00000000	00000011	00000023	8142E480				
----------	----------	----------	-----------	----------	----------	----------	----------	--	--	--	--

00000002 0000 0000 AMOD=KRNL

```

00000007 81409EE8 FFFFFFFE.00052010 82025CA0 0000000C 00000004 814C0600
  00000000 0007 0007 WRTMOD=EXEC AMOD=USER PERM
File = DISK$X97D_R2Y:[VMS$COMMON.SYSLIB]SYS$SSISHR.EXE;1 SYSGBL
00000008 81409EC0 FFFFFFFF.83400000 00000000 000000B4 00000003 81446340
  0000000C 0000 0000 AMOD=KRNL
00000009 81409E98 FFFFFFFF.83418000 00000000 00000038 000000B7 81446340
  00000001 0000 0000 CRF WRT AMOD=KRNL
0000000A 81409E70 FFFFFFFE.00052028 820261B0 00000027 00000019 814C0AC0
  00000003 000A 000A WRTMOD=EXEC AMOD=USER PERM
Name = INS$82026130_006 SYSGBL
File = DISK$X97D_R2Y:[VMS$COMMON.SYSLIB]DISMNTSHR.EXE;1
0000000B 81409E48 FFFFFFFE.00052050 82026630 0000007A 00000004 814C0D00
  00000008 000B 000B WRTMOD=EXEC AMOD=USER PERM
Name = INS$82026540_002 SYSGBL
File = DISK$X97D_R2Y:[VMS$COMMON.SYSLIB]DTI$SHARE.EXE;1
.
.
.

```

4.46. SHOW GLOCK

Displays the Galaxy locks for the Galaxy Management Database (GMDB), process tables, and/or system tables.

Format

```
SHOW GLOCK [/ADDRESS=n [/PHYSICAL]
```

```
| /ALL
```

```
| /GMDB_TABLE
```

```
| /HANDLE=n [/LINKED]
```

```
| /PROCESS_TABLE [=n ]
```

```
| /SYSTEM_TABLE [=n ]]
```

```
[/BRIEF]
```

Parameters

None.

Qualifiers

/ALL

Displays information provided by the /GMDB_TABLE, /PROCESS_TABLE, and /SYSTEM_TABLE qualifiers. The /ALL qualifier also displays information from the base GMDB Galaxy lock.

/BRIEF

Displays a single line for each Galaxy lock, regardless of any other qualifiers.

/GMDB_TABLE

Displays the Galaxy lock table for the Galaxy Management Database (GMDB) including the embedded and attached Galaxy locks.

/PROCESS_TABLE [=n]

Displays all the process Galaxy lock tables with the embedded and attached Galaxy locks, as well as a summary table. The `/PROCESS_TABLE=n` qualifier displays the single Galaxy lock table without a summary page.

/SYSTEM_TABLE [=n]

Displays all the system Galaxy lock tables with the embedded and attached Galaxy locks, as well as a summary table. The `/SYSTEM_TABLE=n` qualifier displays the single Galaxy lock table without a summary page.

/ADDRESS=n [/PHYSICAL]

Displays the single Galaxy lock at address *n*. Because process Galaxy locks are located by their physical address, you must use the `/PHYSICAL` qualifier to enter such an address.

/HANDLE=n [/LINKED]

Displays the single Galaxy lock whose handle is *n*. The optional qualifier `/LINKED` causes SDA to display all Galaxy locks linked to the one specified.

Examples

- SDA> SHOW GLOCK
Galaxy Lock Database

```

-----
Base address of GLock segment of GMDB:      FFFFFFFF.7F238000
Length:                                     00000000.00082000

  Nodes:                                     00000000.00000007  Flags:
00000000.00000000

Process tables:                             00000000.00000400  System tables:
00000000.00000400
  First free:                               00000002
00000001
  First used:                               00000001
00000000

Embedded GLocks:

GLock address:                             FFFFFFFF.7F238020  Handle:
80000000.00000805

  GLock name:                               GMDB_GLOCK_LOCK   Flags:
  00
  Owner count:                               00  Owner node:
  00
  Node sequence:                             0000  Owner:
000000

```

```

IPL:                                08  Previous IPL:
  00
Wait bitmask:                        00000000.00000000  Timeout:
00000000
Thread ID:                            00000000.00000000

GLock address:                       FFFFFFFF.7F238190  Handle:
80000000.00000833

GLock name:                          PRC_LCKTBL_LOCK  Flags:
  00
Owner count:                          00  Owner node:
  00
Node sequence:                        0000  Owner:
000000
IPL:                                08  Previous IPL:
  00
Wait bitmask:                        00000000.00000000  Timeout:
00000000
Thread ID:                            00000000.00000000

GLock address:                       FFFFFFFF.7F2381D0  Handle:
80000000.0000083B

GLock name:                          SYS_LCKTBL_LOCK  Flags:
  00
Owner count:                          00  Owner node:
  00
Node sequence:                        0000  Owner:
000000
IPL:                                08  Previous IPL:
  00
Wait bitmask:                        00000000.00000000  Timeout:
00000000
Thread ID:                            00000000.00000000

```

This example shows the summary of the Galaxy lock database.

2. SDA> SHOW GLOCK/PROCESS_TABLE

Galaxy Lock Database: Process Lock Table #0001

```

-----
Base address of Process Lock Table #0001:  FFFFFFFF.7F23A000

Lock size:                               0040  Flags:
  01  VALID
Region Index/Sequence:                   0008/00000001  Access mode:
  03
Region physical size:  00000000.00002000  Virtual size:
00000000.00002000
Number of locks:                          00000000.00000080  Nodes:
00000000.00000007

```

Per-node reference counts:

```

Node   Count
----   -
0000   0001

```



```

0001    0001
0002    0001

```

Embedded GLock:

```

GLock address:      FFFFFFFF.7F23A040  Handle:
80000000.00000C09

  GLock name:      PLCKTBL_LOCK001  Flags:
    00
  Owner count:      00  Owner node:
    00
  Node sequence:    0000  Owner:
000000
  IPL:              00  Previous IPL:
    00
  Wait bitmask:     00000000.00000000  Timeout:
00000000
  Thread ID:        00000000.00000000

```

Attached GLocks:

```

GLock address:      P00000000.C05EC7C0  Handle:
00000001.000000F9

  GLock name:      CPU_BAL_LOCK      Flags:
    00
  Owner count:      00  Owner node:
    00
  Node sequence:    0000  Owner:
000000
  IPL:              00  Previous IPL:
    00
  Wait bitmask:     00000000.00000000  Timeout:
00000000
  Thread ID:        00000000.00000000

```

```

.
.
.

```

```

GLock address:      P00000000.C05EC000  Handle:
00000001.00000001

  GLock name:      CPU_BAL_LOCK      Flags:
    00
  Owner count:      00  Owner node:
    00
  Node sequence:    0000  Owner:
000000
  IPL:              00  Previous IPL:
    00
  Wait bitmask:     00000000.00000000  Timeout:
00000000
  Thread ID:        00000000.00000000

```

```
Used GLock count = 0020
```

```
Free GLock count = 0060
```

```
Galaxy Lock Database: Process Lock Table Summary
```

```
Total used Process Lock Tables:          00000001
Total free Process Lock Tables:          000003FF
```

This example shows the Galaxy locks for all processes.

4.47. SHOW GMDB

Displays the contents of the Galaxy Management Database (GMDB) and/or the node blocks of the instances in the Galaxy system.

Format

```
SHOW GMDB [/ALL]
```

```
[/NODE [=name | =n | /ADDRESS=n ] [/SUMMARY]
```

Parameters

None.

Qualifiers

/ADDRESS

Specifies the address of a single node block to be displayed when used with the /NODE qualifier. See the description of the /NODE qualifier.

/ALL

Displays the contents of the Galaxy Management Database and all node blocks that have ever been used (contents nonzero).

/NODE [=name | =n | /ADDRESS=n]

Displays the contents of the specified node block, given by either the name of the instance, the partition number, or the address of the node block. If you specify only the /NODE qualifier, the node block for the current instance is displayed.

/SUMMARY

Displays a one-page summary of the GMDB and all node blocks.

Note

The default action displays the contents of the Galaxy Management Database.

Examples

1. SDA> SHOW GMDB

```
Galaxy Management Database
```

```

-----
Base address of GMDB:                FFFFFFFF.7F234000
Base address of NODEB for this instance: FFFFFFFF.7F236000

Revision:                            1.0 Maximum node ID:
00000003
Creation time: 31-MAR-1999 13:15:08.08 Incarnation:
00000000.00000003
State:                                OPERATIONAL Creator node:
00000001
Base size:                            00000000.00004000 Total size:
00000000.000A6000
Last joiner ID:                       00000002 Remover node ID:
FFFFFFFF
Last leaver ID:                       00000002 Node timeout (msec)
5000.
Lock owner                             00000002 Lock flags:
0000
Break owner:                           FFFFFFFF Breaker ID:
FFFFFFFF

Version Information:

Min Version Operational                1.0 Min Version Allowed
1.0
Max Version Operational                1.0

Membership bitmask:                    FFFFFFFF.7F236800

Valid bits:                            00000004 State:
00000000.0000001E AUTO_LOCK TIMEOUT_CRASH....
Unit count:                             0001 Unit size:
QUADWORD
Lock IPL:                               16 Saved IPL:
00000008
Count of bits set:                      00000003
Timeout count:                          000186A0
Summary bitmask:                        00000000.00000001

Unit bitmask:
.....7 00000000

Remove node bitmask:                   FFFFFFFF.7F236880

Valid bits:                            00000004 State:
00000000.00000018 SUMMARY_BITS SET_COUNT
Unit count:                             0001 Unit size:
QUADWORD
Count of bits set:                      00000000
Summary bitmask:                        00000000.00000000

Unit bitmask:
.....0 00000000

Subfacility validation flags:           00000000

```

```

Galaxy locks segment: FFFFFFFF.7F238000 Length:
00000000.00082000
Shared memory segment: FFFFFFFF.7F2BA000 Length:
00000000.0000A000
CPU comms segment: FFFFFFFF.7F2C4000 Length:
00000000.00014000
CPU info segment: FFFFFFFF.7F2D8000 Length:
00000000.00002000
Membership segment: FFFFFFFF.7F2DA000 Length: (empty)

MMAP address: FFFFFFFF.7F234200

Level count: 0000 Flags:
0001 VALID
Top page count: 00000053 Virtual size:
00000000.000A6000
PFN list page count: 00000000 First PFN:
00060000
Data page count: 00000053

```

This example shows the overall summary of the Galaxy Management Database.

2. SDA> SHOW GMDB/NODE=0

```

GMDB: Node ID 00000000 (current instance)
-----

Base address of node block: FFFFFFFF.7F236000

Version: 1.0 Node name:
ANDA1A
Join time: 31-MAR-1999 14:11:09.08 Incarnation:
00000000.00000005
State: MEMBER Crash_all acknowledge:
00000000
Validation done: 00000000 Reform done:
00000000

IP interrupt mask: 00000000.00000000

Little brother: 00000002 Heartbeat:
00000000.0019EAD1
Big brother: 00000001 Last watched_node:
00000000

Watched_node #0: FFFFFFFF.7F236078 Node watched:
00000002
Last heartbeat: 00000000.0017C1AD Miss count:
00000000

```

This example shows Galaxy Management Database information for the specified instance.

4.48. SHOW GSD

Displays information contained in the global section descriptors.

Format

```
SHOW GSD [/ADDRESS=n | /ALL | /DELETED | /GLXGRP
| /GLXSYS | /GROUP | /SYSTEM]
```

Parameters

None.

Qualifiers

/ADDRESS=*n*

Displays a specific global section descriptor entry, given its address.

/ALL

Displays information in all the global section descriptors, that is, the system, group, and deleted global section descriptors, plus the Galaxy group and Galaxy system global section descriptors, if the system or dump being analyzed is a member of an OpenVMS Galaxy system. This qualifier is the default.

/DELETED

Displays information in the deleted (that is, delete pending) global section descriptors.

/GLXGRP

Displays information in the group global section descriptors of a Galaxy system.

/GLXSYS

Displays information in the system global section descriptors of a Galaxy system.

/GROUP

Displays information in the group global section descriptors.

/SYSTEM

Displays information in the system global section descriptors.

Description

The SHOW GSD command displays information that resides in the global section descriptors. The table below shows the fields and their meaning.

Field	Meaning
ADDRESS	Gives the address of the global section descriptor.
NAME	Gives the name of the global section.

Field	Meaning
GSTX	Gives the global section table index.
FLAGS	Gives the settings of flags for specified global section, as a hexadecimal number; also displays key flag bits by name.
BASEPFN 1	Gives physical page frame number at which the section starts. This field applies only to PFN mapped global sections.
PAGES 1	Gives number of pages (not pagelets) in section. This field applies only to PFN mapped global sections.
REFCNT 1	Gives number of times this global section is mapped. This field applies only to PFN mapped global sections.

Examples

```
SDA > SHOW GSD
```

```
System Global Section Descriptor List
```

```
-----PFNMAP-----
ADDRESS      NAME          GSTX  FLAGS          BASEPFN  PAGES  REFCNT
817DAF30     SECIDX_422    02DD  0082C3C9      WRT AMOD=USER PERM
817DAE60     SECIDX_421    02DC  008A83CD      DZRO WRT AMOD=USER PAGFIL
817DAD90     SECIDX_420    02DB  0088C3CD      DZRO WRT AMOD=USER PERM PAGFIL
817DACC0     SECIDX_419    02DA  008883DC      DZRO WRT AMOD=USER PAGFIL
817DABE0     SECIDX_418    0000  0001C3C1      AMOD=USER PERM          00000B0B  00000002  00000000
817DAB00     SECIDX_417    0000  0001C3C1      AMOD=USER PERM          00000B0B  00000002  00000000
817DA890     SECIDX_412    02D6  0080C3CD      DZRO WRT AMOD=USER PERM
817DA850     SECIDX_411    02D5  008083CD      DZRO WRT AMOD=USER
      .
      .
      .
```

4.49. SHOW GST

See SHOW GLOBAL_SECTION_TABLE.

4.50. SHOW HEADER

Displays the header of the dump file.

Format

```
SHOW HEADER
```

Parameters

None.

Qualifiers

None.

Description

The SHOW HEADER command produces a 10-column display, each line of which displays both the hexadecimal and ASCII representation of the contents of the dump file header in 32-byte intervals. Thus, the first eight columns, when read right to left, represent the hexadecimal contents of 32 bytes of the header; the ninth column, when read left to right, records the ASCII equivalent of the contents. (The period [.] in this column indicates an ASCII character that cannot be displayed.)

After it displays the contents of the header blocks, the SHOW HEADER command displays the hexadecimal contents of the saved error log buffers.

See the *OpenVMS AXP Internals and Data Structures* manual for a discussion of the information contained in the dump file header. See also the SHOW DUMP and CLUE ERRLOG commands, which you can use to obtain formatted displays of the dump header and error log buffers.

See also the SHOW DUMP command, which will output a formatted display of the contents of the dump header.

Examples

```
SDA> SHOW HEADER

Dump file header
-----
00000000 7FFA6000 00000000 7FFA1C98 00000000 0000187C 08090FC1 00000004  ....Ã...|.....ú.....'ú..... 00000000
00001FFF 0000000D 00002000 80D0A000 00000000 7AFFBADO 00000000 7FFAC100  .Ãú.....Ðº.z.....Ð..... 00000020
0000B162 00000000 00000001 00000000 00040704 FCFEFFFF 03000000 80C13670  p6Ã.....ù.....b±.. 00000040
00000000 00000400 00000008 00000000 3154462D 31393658 00000011 00000000  .....X691-FT1..... 00000060
00000000 00000000 00000000 00000000 00000000 00000000 00000000 00000000  ..... 00000080
00000000 00000000 00000000 00000000 00000000 00000000 00000000 00000000  ..... 000000A0
FF7FC000 FFFFFFFD FF000000 80C220F0 00000000 00000000 00000000 00000000  .....ð Ã.....ý.....Ã..... 000000C0
.
.
.

Saved error log messages
-----
0004FFF9 0000040B 00000001 00000000 00000070 80D0B000 80D0A00C 00000000  ....Ð..ºÐ.p.....ù..... 80D0A000
B4510020 60030000 00000000 00000020 20585443 50575308 00000000 00020000  .....SWPCTX .....Q..... 80D0A020
30303320 43454412 00000002 00000000 3154462D 31393658 0000009A 2C31075A  Z.l,....X691-FT1.....DEC 300 80D0A040
000000AA 59EC7C0A 00000000 00000000 00000000 00303034 206C6564 6F4D2030  0 Model 400.....|iya... 80D0A060
20585443 50575308 00000000 00020000 0004FFF9 0000040B 00000001 00000000  .....ù.....SWPCTX 80D0A080
3154462D 31393658 0001009A 2C3107FD 1DDB0040 60030000 00000000 00000020  .....@.Û.ý.l,....X691-FT1 80D0A0A0
00000000 00303034 206C6564 6F4D2030 30303320 43454412 00000003 00000000  .....DEC 3000 Model 400.... 80D0A0C0
4B442458 54435057 530A0064 000001AB 00000000 00010001 00000000 00000000  .....«...d..SWPCTX$DK 80D0A0E0
.
.
.
```

4.51. SHOW IMAGE

Displays information about an image, regardless of the type of image (executive, activated, or installed).

Format

```
SHOW IMAGE image-name
```

Parameters

image-name

Name of the image to be displayed. This is a required parameter that may include wildcards.

Qualifiers

None.

Description

Searches the executive image list for the image name, and, if a match is found, displays the loaded image information. Next, searches the activated image list for the process (if SDA has a current process context). If a match is found, displays the activated image information. Finally, searches the installed image lists, directory by directory. If a match is found, displays the installed image (known file entry) information.

SHOW IMAGE x is equivalent to SHOW EXECUTIVE x followed by SHOW PROCESS/IMAGE=x followed by SHOW KFE x .

Examples

1. SDA> show image sys\$public_vectors

```
Image SYS$PUBLIC_VECTORS
-----

                                VMS Executive image layout
                                -----

Image                               Base                               End
  Length      ImageOff  SymVec
-----
SYS$PUBLIC_VECTORS
                                81804B18
  Nonpaged read only             FFFFFFFF.80000000 FFFFFFFF.800025FF
00000000.00002600 00000000
  Nonpaged read/write            FFFFFFFF.81800000 FFFFFFFF.81807FFF
00000000.00008000 00004000
    Linked 30-AUG-2004 09:36 LDRIMG 81C17480  SeqNum 00000000 --<
sliced >--

                                Process activated images
                                -----

  Image Name/Link Time/Section Type      Start      End      Type/File Id
-----
SYS$PUBLIC_VECTORS                      81804B18 818071B7 GLBL

                                IMCB  Sym Vect Maj,Minor ID  Base      End
ImageOff
-----
                                7FF6A250 81804B18 113,16596271

                                Known File Entries
                                -----

KFD Device/Directory/Type: $31$DKB100:<SYS0.SYSCOMMON.SYSLIB>.EXE
-----
```


KFE File ID/ Address End	Flags/ ImageOff	Image Name/ Section Type	KFERES Address/ Base
82984C50 (3923,194,0)		SYSS\$PUBLIC_VECTORS;1	

This example shows the output from `SHOW IMAGE` for `SYSS$PUBLIC_VECTORS`. Part of the example has been moved left to stay within page boundaries of the manual.

4.52. SHOW KFE

Displays information about known file entries (installed images).

Format

```
SHOW KFE [image_name | /ADDRESS=kfe_address | /ALL]
```

```
SHOW KNOWN_FILE_ENTRY [image_name | /ADDRESS=kfe_address | /ALL]
```

Parameters

image-name

Name of the image to be displayed. This may include wildcards, but cannot include device or directory information.

Qualifiers

/ADDRESS=kfe_address

Specifies the address of a single KFE of interest. The details are displayed for this KFE with device/directory information from the corresponding KFD (Known File Directory).

/ALL

Displays details for all KFEs, including device/directory information from the corresponding KFDs, with the contents of the Known File Pointer Block (KFPB).

Description

The `SHOW KFE` command displays information about known files (installed images). By default, a summary line without image-section information is given for each image. Use the `/ALL` qualifier to obtain detailed information for all images. For a single image, specify the image name or KFE address.

The `image_name` parameter, the `/ADDRESS`, and `/ALL` qualifiers cannot be used together. `SHOW KNOWN_FILE_ENTRY` is a synonym for `SHOW KFE`.

Examples

1. `SDA> SHOW KFE`

Known File Entries

```
-----
KFPB address:          8292D860
Hash table address:   82975360
Hash table size:      0080
Entry count:          016F
```

```
KFD Device/Directory/Type: $31$DKB100:<SYS0.SYSCOMMON.CDE
$DEFAULTS.SYSTEM.BIN>.EXE
-----
```

```
KFD address:          829E8D60
Reference count:      0002
```

KFE	Image Name	KFERES Address	File ID	Flags
829E8290	DECW\$LOGINOUT;1	(7204,49,0)	LIM Open HdrRes	Shared
829E8DB0	DTGREET;1	(5651,19,0)	Open HdrRes	Shared

```
KFD Device/Directory/Type: $31$DKB100:<SYS0.SYSCOMMON.SYSEXE>.EXE
-----
```

```
KFD address:          8299C140
Reference count:      0066
```

KFE	Image Name	KFERES Address	File ID	Flags
8299C210	AUTHORIZE;1		(72,176,0)	
	ProcPriv AuthPriv			
829ACE10	BACKUP;1		(73,176,0)	
8299C2A0	CDU;1		(75,176,0)	
	ProcPriv Open HdrRes AuthPriv			
8299C660	CIA;1		(510,176,0)	
	ProcPriv AuthPriv			
829ACE90	CONVERT;1		(77,176,0)	
829A3AD0	COPY;1	829A3E70	(78,176,0)	
	Open HdrRes Shared			
829ACF10	CREATE;1		(79,176,0)	
.				
.				
.				

This example shows the first page of summary output for all known images.

2. SDA> show kfe decc*

Known File Entries

```
-----
KFD Device/Directory/Type: $31$DKB100:<SYS0.SYSCOMMON.SYSLIB>.EXE
-----
```

KFE	Image Name/	KFERES Address/	File
ID/	Flags/		

Address ImageOff	Section Type	Base	End
829900B0	DECC\$SHR;1 LIM Open HdrRes	82990960	(2431,189,0)
	Shared ResCode		
	Paged read only	FFFFFFFF.80A70000	
FFFFFFFF.80C815FF	00000000 Initialization	00000000.7BEC0000	
00000000.7BF00DFF	00220000 Fixup	00000000.7BF10000	
00000000.7BF1B1FF	00270000 Nonpaged read/write	00000000.7BF20000	
00000000.7BF2FBFF	00280000 Nonpaged read/write	00000000.7BF30000	
00000000.7BF309FF	00290000 Fixup	00000000.7BF40000	
00000000.7BF401FF	002A0000 Paged read/write	00000000.7BF50000	
00000000.7BF56FFF	002B0000		
KFD Device/Directory/Type: \$31\$DKB100:<SYS0.SYSCOMMON.SYSMSG>.EXE			
KFE Flags/ Address ImageOff	Image Name/ Section Type	KFERES Address/ Base	File ID/ End
829AE4F0	DECC\$MSG;1 LIM Open HdrRes Shared		(257,176,0)

This example shows the details for all images that match the wildcard DECC*.

4.53. SHOW KNOWN_FILE_ENTRY

See SHOW KFE.

4.54. SHOW LAN

Displays information contained in various local area network (LAN) data structures.

Format

```
SHOW LAN [/qualifier[,...]]
```

Parameters

None.

Qualifiers

/ATM

Specifies that asynchronous transfer mode (ATM) information for the LAN be displayed.

/CLIENT=*name*

Specifies that information be displayed for the specified client. Valid client designators are SCA, DECNET, LAT, MOPRC, TCPIP, DIAG, ELN, BIOS, LAST, USER, ARP, MOPDL, LOOP, BRIDGE, DNAME, ENCRY, DTIME, and LTM. The /CLIENT, /DEVICE, and /UNIT qualifiers are synonymous and mutually exclusive.

/COUNTERS

Specifies that the LAN station block (LSB) and unit control block (UCB) counters be displayed.

/CSMACD

Specifies that Carrier Sense Multiple Access with Collision Detect (CSMA/CD) information for the LAN be displayed. By default, both CSMA/CD and Fiber Distributed Data Interface (FDDI) information is displayed.

/DEVICE=*name*

Specifies that information be displayed for the specified device, unit, or client. For each LAN adapter on the system, there is one **device** and multiple users of that device called, **units** or **clients**. Device designators are specified in the format **XXdn**, where **XX** is the type of device, **d** is the device letter, and **n** is the unit number. The device letter and unit number are optional. The first unit, which is always present, is the template unit. These are specified as indicated in this example for a DEMNA called EX:

```
/DEVICE=EX---display all EX devices on the system
```

```
/DEVICE=EXA---display the first EX device only
```

```
/DEVICE=EXA0---display the first EXA unit
```

```
/DEVICE=SCA---display SCA unit
```

```
/DEVICE=LAT---display LAT units
```

Valid client names are listed in the /CLIENT=*name* qualifier. The /CLIENT, /DEVICE, and /UNIT qualifiers are synonymous and mutually exclusive.

/ELAN

Specifies information from an Emulated LAN (ELAN) that runs over an asynchronous transfer mode (ATM) network. The /ELAN qualifier displays the LAN Station Block (LSB) address, device state, and the LSB fields pertinent to an ELAN for both the parent ATM device and the ELAN pseudo-device drivers. It also specifies the name, description, parent device, state, and LAN emulation client (LEC) attributes of the ELAN.

The qualifier /ELAN used with the device qualifier (/ELAN/DEVICE=ELA) will only display information for the specified device or pseudo-device.

/ERRORS

Specifies that the LSB and UCB error counters be displayed.

/FDDI

Specifies that Fiber Distributed Data Interface (FDDI) information for the LAN be displayed. By default, both CSMA/CD and FDDI information is displayed.

/FULL

Specifies that all information from the LAN, LSB, and UCB data structures be displayed.

/INTERNAL

Specifies internal counters of the drivers by displaying the internal counters. If the **/INTERNAL** qualifier is used with the **/DEVICE** qualifier, the **/INTERNAL** specifies the internal counters of a specific driver.

/QUEUES

Specifies a listing of all queues, whether their status is valid or invalid, and all elements of the queues. If the **/QUEUES** qualifier is used with the **/DEVICE** qualifier, the **/QUEUES** specifies a specific queue.

/SOURCEROUTING

Specifies that the information in the source routing table maintained by the Token Ring driver be displayed.

/SUMMARY

Specifies that only a summary of LAN information (a list of flags, LSBs, UCBs, and base addresses) be printed. This is the default.

/TIMESTAMPS

Specifies that time information (such as start and stop times and error times) from the device and unit data structures be printed. SDA displays the data in chronological order.

/TR

Specifies that Token Ring information for the LAN be displayed.

/UNIT=*name*

Specifies that information be displayed for the specified unit. See the descriptions for **/CLIENT=*name*** and **/DEVICE=*name*** qualifiers.

/VCI

Specifies that information be displayed for the VMS Communication Interface Block (VCIB) for each LAN device with an active VCI user. If you use the **/VCI** qualifier with the **/DEVICE** qualifier, the VCIB is only displayed for the specified device.

Description

The **SHOW LAN** command displays information contained in various local area network (LAN) data structures. By default, or when the **/SUMMARY** qualifier is specified, **SHOW LAN** displays a list of

flags, LSBs, UCBs, and base addresses. When the /FULL qualifier is specified, SHOW LAN displays all information found in the LAN, LSB, and UCB data structures.

Examples

```
1. SDA> SHOW LAN/FULL
LAN Data Structures
-----
                -- LAN Information Summary 23-MAY-1996 13:07:52 --
LAN flags: 00000004 LAN_INIT
LAN block address      80DB7140      Timer DELTA time
10000000
Number of stations      2      DAT sequence number
1
LAN module version      1      First SVAPTE
FFDF60F0
LANIDEF version        51      Number of PTEs
3
LANUDEF version        26      SVA of first page
8183C000
First LSB address      80DCA980

                -- LAN CSMACD Network Management 23-MAY-1996 13:07:52 --
Creation time          None      Times created
0
Deletion time          None      Times deleted
0
Module EAB             00000000      Latest EIB
00000000
Port EAB               00000000
Station EAB            00000000
NM flags: 00000000

                -- LAN FDDI Network Management 23-MAY-1996 13:07:52 --
Creation time          None      Times created
0
Deletion time          None      Times deleted
0
Module EAB             00000000      Link EAB
00000000
Port EAB               00000000      PHY port EAB
00000000
Station EAB            00000000      Module EIB
00000000
NM flags: 00000000
LAN Data Structures
-----
                -- ESA Device Information 23-MAY-1996 13:07:52 --
LSB address           80DCA980      Driver code address
80CAE838
Driver version        00000001.07010037      Device1 code address
00000000
Device1 version       00000000.00000000      Device2 code address
00000000
Device2 version       00000000.00000000      LAN code address
80CAFA00
LAN version           00000001.07010112      DLL type
CSMACD
```

```

Device name          EY_NITC2      MOP name
MXE
MOP ID              94           HW serial          Not
supplied
HW version          00000000     Promiscuous mode
OFF
Controller mode     NORMAL       Promiscuous UCB
00000000
Internal loopback   OFF         All multicast state
OFF
Hardware address    08-00-03-DE-00-12  CRC generation mode
ON
Physical address    AA-00-04-00-88-FE  Full Duplex Enable
OFF
Active unit count   1           Full Duplex State
OFF
Line speed          10
Flags: 00000000
Char: 00000000
Status: 00000003 RUN,INITED

```

LAN Data Structures

```

-----
-- ESA Device Information (cont) 23-MAY-1996 13:07:52 --
Put rcv ptr/index   00000000     Get rcv ptr/index
00000015
Put xmt ptr/index   80DCB620     Get xmt ptr/index
80DCB620
Put cmd ptr/index   00000000     Get cmd ptr/index
00000000
Put uns ptr/index   00000000     Get uns ptr/index
00000000
Put smt ptr/index   00000000     Get smt ptr/index
00000000
RBufs owned by dev 0           Rcv packet limit
32
XEnts owned by dev 0           XEnts owned by host
4
CEnts owned by dev 0           Transmit timer
0
UEnts owned by dev 0           Control timer
0
SEnts owned by dev 0           Periodic SYSID timer
599
Current rcv buffers 17          Ring unavail timer
0
Rqst MAX rcv buffers 32         USB timer
26
Rqst MIN rcv buffers 16         Receive alignment
0
Curr MAX rcv buffers 32         Receive buffer size
1518
Curr MIN rcv buffers 16         Min 1st chain segment
0

```

```
FILL rcv buffers          16    Min transmit length
0
ADD rcv buffers           32    Dev xmt header size
0
```

LAN Data Structures

```
-----
                -- ESA Device Information (cont) 23-MAY-1996 13:07:52 --
Last receive          23-MAY 13:07:51    Last transmit        23-MAY
13:07:50
ADP address           80D4B280    IDB address
80DCA880
DAT stage             00000000    DAT xmt status
0000003C.003C0001
DAT number started    1      DAT xmt complete     23-MAY
13:07:19
DAT number failed     0      DAT rcv found
None
DAT VCRP              80DCBB80    DAT UCB
00000000
Mailbox enable flag   0      CRAM read comman
00000000
CSR base phys addr 00000000.00000000    CRAM write comma
00000000
Mailboxes in use     0      Media
UNDF
2nd LW status flags  00000000
LAN Data Structures
-----
```

```
                -- ESA Network Management Information 23-MAY-1996 13:07:52 --
Creation time         None    Create count
0
Deletion time         None    Enable count
0
Enabled time          None    Number of ports
0
Disabled time         None    Events logged
0
EIB address           00000000    NMgmt assigned addr
None
LLB address           00000000    Station name itmlst
00000000
LHB address           00000000    Station itmlst len
0
First LPB address     00000000
LAN Data Structures
-----
```

```
                -- ESA Fork Information 23-MAY-1996 13:07:52 --
ISR   FKB sched       23-MAY 13:07:51    ISR   FKB in use flag
FREE
ISR   FKB time        23-MAY 13:07:51    ISR   FKB count
200
IPL8  FKB sched       23-MAY 13:07:20    IPL8  FKB in use flag
FREE
IPL8  FKB time        23-MAY 13:07:20    IPL8  FKB count
1
RESET FKB sched       None      RESET FKB in use flag
FREE
```



```

RESET FKB time          None      RESET FKB count
0
NM   FKB sched          None      NM   FKB in use flag
FREE
NM   FKB time           None      NM   FKB count
0
Fork status code        0

```

LAN Data Structures

```

-----
-- ESA Queue Information 23-MAY-1996 13:07:52 --
Control hold queue      80DCACF0  Status: Valid, empty
Control request queue   80DCACF8  Status: Valid, empty
Control pending queue   80DCAD00  Status: Valid, empty
Transmit request queue  80DCACE8  Status: Valid, empty
Transmit pending queue  80DCAD18  Status: Valid, empty
Receive buffer list     80DCAD38  Status: Valid, 17 elements
Receive pending queue   80DCAD20  Status: Valid, empty
Post process queue      80DCAD08  Status: Valid, empty
Delay queue             80DCAD10  Status: Valid, empty
Auto restart queue      80DCAD28  Status: Valid, empty
Netwrk mgmt hold queue  80DCAD30  Status: Valid, empty
-- ESA Multicast Address Information 23-MAY-1996 13:07:52 --
AB-00-00-04-00-00
-- ESA Unit Summary 23-MAY-1996 13:07:52 --
UCB      UCB Addr  Fmt  Value          Client      State
----      -
ESA0      80D4F6C0
ESA1      80E35400  Eth  60-03          DECNET      0017
STRTN, LEN, UNIQ, STRTD
LAN Data Structures
-----
-- ESA Counters Information 23-MAY-1996 13:07:52 --
Octets received          596      Octets sent
230
PDUs received            8        PDUs sent
5
Mcast octets received    596      Mcast octets sent
138
Mcast PDUs received      8        Mcast PDUs sent
3
Unrec indiv dest PDUs    0        PDUs sent, deferred
0
Unrec mcast dest PDUs    1        PDUs sent, one coll
0
Data overruns            0        PDUs sent, mul coll
0
Unavail station buffs    0        Excessive collisions
0
Unavail user buffers     0        Late collisions
0
CRC errors                0        Carrier check failure
0
Alignment errors         0        Last carrier failure
None

```

Rcv data length err	0	Coll detect chk fail
5		
Frame size errors	0	Short circuit failure
0		
Frames too long	0	Open circuit failure
0		
Seconds since zeroed	34	Transmits too long
0		
Station failures	0	Send data length err
0		

LAN Data Structures

```

-----
-- ESA Counters Information (cont) 23-MAY-1996 13:07:52 --
No work transmits          0   Ring avail transitions
  0
Buffer_Addr transmits     0   Ring unavail transitions
  0
SVAPTE/BOFF transmits    0   Loopback sent
  0
Global page transmits     0   System ID sent
  0
Bad PTE transmits        0   ReqCounters sent
  0
Restart pending counter   0   Internal counters size
  40
+00 MCA not enabled      187  +2C Generic (or unused)
  00000000
+04 Xmt underflows       0   +30 Generic (or unused)
  00000000
+08 Rcv overflows        0   +34 Generic (or unused)
  00000000
+0C Memory errors        0   +38 Generic (or unused)
  80DCAD18
+10 Babbling errors      0   +3C Generic (or unused)
  80DCAD18
+14 Local buffer errors   0   +40 Generic (or unused)
  004E0840
+18 LANCE interrupts     202  +44 Generic (or unused)
  61616161
+1C Xmt ring <31:0>      00000000  +48 Generic (or unused)
  61616161
+20 Xmt ring <63:32>    00000000  +4C Generic (or unused)
  61616161
+24 Soft errors handled   0   +50 Generic (or unused)
  61616161
+28 Generic (or unused)  00000000  +54 Generic (or unused)
  61616161

```

LAN Data Structures

```

-----
-- ESA Error Information 23-MAY-1996 13:07:52 --
Fatal error count        0   Last error CSR
  00000000
Fatal error code         None  Last fatal error
  None

```

```

Prev error code          None      Prev fatal error
None
Transmit timeouts       0      Last USB time
None
Control timeouts       0      Last UUB time
None
Restart failures       0      Last CRC time
None
Power failures         0      Last CRC srcadr
None
Bad PTE transmits     0      Last length erro
None
Loopback failures     0      Last exc collisi
None
System ID failures    0      Last carrier fai
None
ReqCounters failures  0      Last late collis
None
LAN Data Structures
-----

```

```

-- ESA0 Template Unit Information 23-MAY-1996 13:07:52 --

```

```

LSB address            80DCA980   Error count
0
VCIB address          00000000   Parameter mask
00000000
Stop IRP address      00000000   Promiscuous mode
OFF
Restart IRP address   00000000   All multicast mode
OFF
LAN medium            CSMACD     Source Routing mode
TRANSPARENT
Packet format         Ethernet  Access mode
EXCLUSIVE
Eth protocol type     00-00     Shared user DES
None
802E protocol ID     00-00-00-00-00  Padding mode
ON
802.2 SAP             00       Automatic restart
DISABLED
802.2 Group SAPs     00,00,00,00  Allow prom client
ON
Controller mode      NORMAL    Can change address
OFF
Internal loopback    OFF      802.2 service
User
CRC generation mode   ON      Rcv buffers to save
1
Functional Addr mod   ON      Minimum rcv buffers
4
Hardware address     08-00-03-DE-00-12  User transmit FC/AC
ON
Physical address     FF-FF-FF-FF-FF-FF  User receive FC/AC
OFF

```

```

LAN Data Structures

```

```

-----
-- ESA1 60-03 (DECNET) Unit Information 23-MAY-1996 13:07:52
--
LSB address          80DCA980   Error count
0
VCIB address         00000000   Parameter mask
00DA8695
Stop IRP address     80E047C0   Promiscuous mode
OFF
Restart IRP address  00000000   All multicast mode
OFF
LAN medium           CSMACD     Source Routing mode
TRANSPARENT
Packet format        Ethernet   Access mode
EXCLUSIVE
Eth protocol type    60-03     Shared user DES
None
802E protocol ID    00-00-00-00-00   Padding mode
ON
802.2 SAP            00        Automatic restart
DISABLED
802.2 Group SAPs    00,00,00,00   Allow prom client
ON
Controller mode      NORMAL     Can change address
OFF
Internal loopback    OFF       802.2 service
User
CRC generation mode  ON        Rcv buffers to save
10
Functional Addr mod  ON        Minimum rcv buffers
4
Hardware address     08-00-03-DE-00-12   User transmit FC/AC
ON
Physical address     AA-00-04-00-88-FE   User receive FC/AC
OFF
LAN Data Structures
-----
-- ESA1 60-03 (DECNET) Unit Information (cont) 23-MAY-1996
13:07:52 --
Last receive         23-MAY 13:07:47   Starter's PID
0001000F
Last transmit        23-MAY 13:07:50   Maximum header size
16
Last start attempt   23-MAY 13:07:20   Maximum buffer size
1498
Last start done      23-MAY 13:07:20   Rcv quota charged
15040
Last start failed    None       Default FC value
00
MCA match enabled    01        Default AC value
00
Last MCA filtered    AB-00-00-04-00-00   Maintenance state
ON
UCB status: 00000017 STRTN,LEN,UNIQ,STRTD
Receive IRP queue    80E356E8   Status: Valid, 1 element
Receive pending queue 80E356E0   Status: Valid, empty
Multicast address table, embedded:
AB-00-00-04-00-00

```

LAN Data Structures

```

-----
-- ESA1 60-03 (DECNET) Counters Information 23-MAY-1996 13:07:52
--
Octets received          483    Octets sent
 180
PDUs received            7      PDUs sent
 3
Mcast octets received   483    Mcast octets sent
 180
Mcast PDUs received     7      Mcast PDUs sent
 3
Unavail user buffer      0      Multicast not enabled
 0
Last UUB time            None    User buffer too small
 0

```

The SHOW LAN/FULL command displays information for all LAN, LSB, and UCB data structures.

```

2. SDA> SHOW LAN/TIME
-- LAN History Information 12-FEB-1995 11:08:48 --
12-FEB 11:08:47.92  ESA                Last receive
12-FEB 11:08:47.92  ESA                Last fork scheduled
12-FEB 11:08:47.92  ESA                Last fork time
12-FEB 11:08:47.77  ESA5         LAST        Last receive
12-FEB 11:08:47.72  ESA3         LAT         Last receive
12-FEB 11:08:41.25  ESA                Last transmit
12-FEB 11:08:41.25  ESA5         LAST        Last transmit
12-FEB 11:08:40.02  ESA2         DECnet     Last receive
12-FEB 11:08:39.14  ESA2         DECnet     Last transmit
12-FEB 11:08:37.39  ESA3         LAT         Last transmit
12-FEB 10:19:25.31  ESA                Last unavail user buffer
12-FEB 10:19:25.31  ESA2         DECnet     Last unavail user buffer
11-FEB 14:10:20.09  ESA5         LAST        Last start completed
11-FEB 14:10:02.16  ESA3         LAT         Last start completed
11-FEB 14:09:58.44  ESA2         DECnet     Last start completed
11-FEB 14:09:57.44  ESA                Last DAT transmit

```

The SHOW LAN/TIME command displays print time information from device and unit data structures.

```

3. SDA> SHOW LAN/VCI/DEVICE=ICB
-- ICB VCI Information 17-APR-1996 14:22:07 --
LSB address = 80A1D580
Device state = 00000003 RUN, INITED
-- ICB2 80-41 (LAST) VCI Information 17-APR-1996 14:22:07 --
VCIB address = 8096F238
CLIENT flags: 00000001 RCV_DCB
LAN flags:    00000004 LAN_INIT
DLL flags:    00000005 XMT_CHAIN, PORT_STATUS
UCB status:   00000015 STRTN, UNIQ, STRTD
VCI ID                LAST        VCI version
00010001
UCB address            80A4C5C0    DP VCRP address
00000000
Hardware address 00-00-93-08-52-CF    LDC address
80A1D720

```

```

Physical address 00-00-93-08-52-CF   LAN medium
TR
Transmit available      80A1D670   Outstanding operations
0
Maximum receives      0   Outstanding receives
0
Max xmt size          4444   Header size
52
Build header rtn      808BF230   Report event rtn
86327130
XMT initiate rtn     808BF200   Transmit complete rtn
86326D80
XMT frame rtn       808BF210   Receive complete rtn
86326A80
-- ICB2 80-41 (LAST) VCI Information (cont) 17-APR-1996 14:22:07
--
Portmgmt initiate rtn 808BF0C0   Portmgmt complete rtn
86327100
Monitor request rtn  00000000   Monitor transmit rtn
00000000
Monitor flags        00000000   Monitor receive rtn
00000000
Port usable          00000000   Port unusable
00000000

```

The SHOW LAN/VCI/DEVICE=ICB command displays the VCIB for a Token Ring device (ICB) that has an active VCI user (LAST).

```

4. SDA> SHOW LAN/ELAN
-- HCA Emulated LAN LSB Information 17-APR-1996 14:08:02 --
LSB address = 8098D200
Device state = 00000101 RUN,RING_AVAIL
Driver CM VC setup adr 808986A0   Driver CM VC teardown adr
80898668
NIPG CM handle adr    8096C30C   NIPG CM SVC handle
00000000
NIPG CM agent handle adr 809B364C   NIPG CM mgr lineup handle
809B394C
NIPG CM ILMI IO handle 809B378C   MIB II handle adr
809B94CC
MIB handle adr       809B3ACC   Queue header for EL LSBs
00000000
DEC MIB handle adr   809BBD8C   NIPG current TQEs used
00000000
Count of allocated TQEs 0000000D   NIPG current pool used
0000D2C0
NIPG pool allocations 00075730
-- ELA Emulated LAN LSB Information 17-APR-1996 14:08:02 --
LSB address = 80AB08C0
Device state = 00000001 RUN
ELAN name = ELAN 1
ELAN description = ATM ELAN
ELAN parent = HCA0
ELAN state = 00000001 ACTIVE
MAX transmit size    MTU_1516   ELAN media type      LAN_802_3
LEC attr buff adr    80AB1FC0   LEC attr buff size   00000328
Event mask           00000000   PVC identifier        00000000
Extended sense       00000000

```

```

-- ELA Emulated LAN LEC Attributes 17-APR-1996 14:08:02 --
LAN type          00000000          LAN MTU          00000001
Proxy flag        00000000          Control timeout  0000000A
Max UF count      00000001          Max UF time     00000001
VCC timeout       000004B0          Max retry count 00000002
LEC id            00000002          Forw delay time 0000000F
Flush timeout     00000004          Path switch delay 00000006
SM state          00000070          Illegal CTRL frames 00000000
CTRL xmt failures 00000000          CTRL frames sent 0000000C
CTRL frames_rcvd 00000012          LEARPs sent     00000000
LEARPS rcvd       00000000          UCASTs sent direct 00000000
UCASTs flooded   00000006          UCASTs discarded 00000001
NUCASTs sent     00000000
Local ESI         00000000.00000000
BUS ATM addr      39999900000000008002BA57E80.AA000302FF12.00
LES ATM addr      39999900000000008002BA57E80.AA000302FF14.00
My ATM addr       39999900000000008002BA57E80.08002B2240A0.00

```

The SHOW LAN/ELAN command displays information for the parent ATM device (HCA) driver and the ELAN pseudo-device (ELA) driver.

```

5. SDA> SHOW LAN/ELAN/DEV=ELA
-- ELA Emulated LAN LSB Information 17-APR-1996 14:08:22 --
LSB address = 80AB08C0
Device state = 00000001 RUN
ELAN name = ELAN 1
ELAN description = ATM ELAN
ELAN parent = HCA0
ELAN state = 00000001 ACTIVE
MAX transmit size  MTU_1516          ELAN media type  LAN_802_3
LEC attr buff adr  80AB1FC0          LEC attr buff size  00000328
Event mask         00000000          PVC identifier    00000000
Extended sense     00000000

-- ELA Emulated LAN LEC Attributes 17-APR-1996 14:08:22 --
LAN type          00000000          LAN MTU          00000001
Proxy flag        00000000          Control timeout  0000000A
Max UF count      00000001          Max UF time     00000001
VCC timeout       000004B0          Max retry count 00000002
LEC id            00000002          Forw delay time 0000000F
Flush timeout     00000004          Path switch delay 00000006
SM state          00000070          Illegal CTRL frames 00000000
CTRL xmt failures 00000000          CTRL frames sent 0000000C
CTRL frames_rcvd 00000012          LEARPs sent     00000000
LEARPS rcvd       00000000          UCASTs sent direct 00000000
UCASTs flooded   00000006          UCASTs discarded 00000001
NUCASTs sent     00000000
Local ESI         00000000.00000000
BUS ATM addr      39999900000000008002BA57E80.AA000302FF12.00
LES ATM addr      39999900000000008002BA57E80.AA000302FF14.00
My ATM addr       39999900000000008002BA57E80.08002B2240A0.00

```

The SHOW LAN/ELAN/DEVICE=ELA command displays information for the ELAN pseudo-device (ELA) driver only.

```

6. SDA> SHOW LAN/ELAN/DEVICE=HCA
-- HCA Emulated LAN LSB Information 17-APR-1996 14:08:25 --
LSB address = 8098D200
Device state = 00000101 RUN,RING_AVAIL

```

Driver CM VC setup adr 80898668	808986A0	Driver CM VC teardown adr
NIPG CM handle adr 00000000	8096C30C	NIPG CM SVC handle
NIPG CM agent handle adr 809B394C	809B364C	NIPG CM mgr lineup handle
NIPG CM ILMI IO handle 809B94CC	809B378C	MIB II handle adr
MIB handle adr 00000000	809B3ACC	Queue header for EL LSBs
DEC MIB handle adr 00000000	809BBD8C	NIPG current TQEs used
Count of allocated TQEs 0000D2C0	0000000D	NIPG current pool used
NIPG pool allocations	000757B2	

The SHOW LAN/ELAN/DEVICE=HCA command displays information for the ATM device (HCA) driver only.

4.55. SHOW LOCKS

Displays information about all lock management locks in the system, or about a specified lock.

Format

```
SHOW LOCKS [ lock-id
| /ADDRESS=n
| /ALL (d)
| /BRIEF
| /BLOCKING
| /CACHED
| /CONVERT
| /GRANTED
| /NAME=name
| /STATUS=(keyword[,...])
| /WAITING ] or SHOW LOCKS {/POOL | /SUMMARY}
```

Parameters

lock-id

Name of a specific lock.

Qualifiers

/ADDRESS=n

Displays a specific lock, given the address of the lock block.

/ALL

Lists all locks that exist in the system. This is the default behavior of the SHOW LOCKS command.

/BLOCKING

Displays only the locks that have a blocking AST specified or attached.

/BRIEF

Displays a single line of information for each lock.

/CACHED

Displays locks that are no longer valid. The memory for these locks is saved so that later requests for locks can use them. Cached locks are not displayed in the other SHOW LOCKS commands.

/CONVERT

Displays only the locks that are on the conversion queue.

/GRANTED

Displays only the locks that are on the granted queue.

/NAME=*name*

Displays all locks on the specified resource. Name can be the actual name of the resource, if it only contains uppercase letters, numerals, the underscore (_), dollar sign, colon (:), and some other printable characters, as for example, /NAME=MY_LOCK. If it contains other printable characters (including lowercase letters), you may need to enclose the name in quotation marks (""), as for example, /NAME="My_Lock/47". If it contains nonprintable characters, you can specify the name as a comma-separated list comprised of strings and hexadecimal numbers. For example, /NAME=("My_Lock",0C00,"/47") would specify the name "My_Lock<NUL><FF>/47". The hexadecimal number can be no more than 8 digits (4 bytes) in length. Nonprintable sequences of more than 4 bytes must be split into multiple hexadecimal numbers. The maximum length of a resource name is 32 characters.

/POOL

Displays the lock manager's poolzone information, which contains the lock blocks (LKB) and resource blocks (RSB).

/STATUS=(*keyword*[,...])

Displays only the locks that have the specified status bits set in the LKB\$_STATUS field. If you specify only one keyword, you can omit the parentheses. Status keywords are as follows:

Keyword	Meaning
2PC_IP	Indicates a two-phase operation in progress
2PC_PEND	Indicates a two-phase operation pending
ASYNC	Completes request asynchronously
BLKASTFLG	Specifies a blocking AST
BLKASTQED	Indicates a blocking AST is queued
BRL	Indicates a byte range lock
CACHED	Indicates a lock block in cache

Keyword	Meaning
CVTSUBRNG	Indicates a sub-range convert request
CVTTOSYS	Converts back to system-owned lock
DBLKAST	Delivers a blocking AST
DCPLAST	Delivers a completion AST
DPC	Indicates a delete pending cache lock
FLOCK	Indicates a fork lock
GRSUBRNG	Grants sub-range lock
IP	Indicates operation in process
MSTCPY	Indicates a lock block is a master copy
NEWSUBRNG	Indicates a new sub-range request
NOQUOTA	Does not charge quota
PCACHED	Indicates lock block needs to be cached
PROTECT	Indicates a protected lock
RESEND	Resends during failover
RM_RBRQD	Requires remaster rebuild
RNGBLK	Specifies a range block
RNGCHG	Indicates a changing range
TIMOUTQ	Indicates lock block is on timeout queue
VALBLKRD	Indicates read access to lock value block
VALBLKWRT	Indicates write access to lock value block
WASSYSOWN	Indicates was system-owned lock

/SUMMARY

Displays summary data and performance counters.

/WAITING

Displays only the waiting locks.

Description

The SHOW LOCKS command displays the information described in the table below for each lock management lock in the system, or for the lock indicated by **lock-id**, an address or name. (Use the SHOW SPINLOCKS command to display information about spinlocks.) You can obtain a similar display for the locks owned by a specific process by issuing the appropriate SHOW PROCESS/LOCKS command. See the *VSI OpenVMS Programming Concepts Manual* for additional information.

You can display information about the resource to which a lock is queued by issuing the SHOW RESOURCES command specifying the resource's **lock-id**.

Table 4.3. Contents of the SHOW LOCKS and SHOW PROCESS/LOCKS Displays

Display Element	Description
Process Index	Index in the PCB array to a pointer to the process control block (PCB) of the process that owns the

Display Element	Description
	lock. This display element is produced only by the SHOW PROCESS/LOCKS command.
Name	Name of the process that owns the lock. This display element is produced only by the SHOW PROCESS/LOCKS command.
Extended PID	Clusterwide identification of the process that owns the lock. This display element is produced only by the SHOW PROCESS/LOCKS command.
Lock ID	Identification of the lock.
PID	Systemwide identification of the lock.
Flags	Information specified in the request for the lock.
Par. ID	Identification of the lock's parent lock.
Sublocks	Count of the locks that the lock owns.
LKB	Address of the lock block (LKB). If a blocking AST has been enabled for this lock, the notation "BLKAST" appears next to the LKB address.
Priority	The lock priority.
Granted at	Lock mode at which the lock was granted.
RSB	Address of the resource block.
Resource	Dump of the resource name. The two leftmost columns of the dump show its contents as hexadecimal values, the least significant byte being represented by the rightmost two digits. The rightmost column represents its contents as ASCII text, the least significant byte being represented by the leftmost character.
Status	Status of the lock, information used internally by the lock manager.
Length	Length of the resource name.
Mode	Processor access mode of the namespace in which the resource block (RSB) associated with the lock resides.
Owner	Owner of the resource. Certain resources owned by the operating system list "System" as the owner. Resources owned by a group have the number (in octal) of the owning group in this field.
Copy	Indication of whether the lock is mastered on the local system or is a process copy.

Examples

- SDA> SHOW LOCKS
Lock Database

```

Lock id: 3E000002          PID: 00000000   Flags: CONVERT NOQUEUE
      SYNCSTS
Par. id: 00000000          SUBLCKs: 0           NOQUOTA CVTSYS
LKB: FFFFFFFF.7DF48150    BLKAST: 81107278
Priority: 0000

```

```

Granted at CR 00000000-FFFFFFFF

```

```

RSB: FFFFFFFF.7DF68D50
Resource: 494D6224 42313146 F11B$bMI Status: NOQUOTA VALBLKR
      VALBLKW
Length 18 4D55445F 5944414C LADY_DUM
Kernel mode 00000000 00005350 PS.....
System 00000000 00000000 .....

```

Local copy

Lock Database

```

Lock id: 3F000003          PID: 00000000   Flags: VALBLK CONVERT
      SYNCSTS
Par. id: 0100007A          SUBLCKs: 0           CVTSYS
LKB: FFFFFFFF.7DF48250    BLKAST: 00000000
Priority: 0000

```

```

Granted at NL 00000000-FFFFFFFF

```

```

RSB: FFFFFFFF.7DF51D50
Resource: 01F77324 42313146 F11B$s÷. Status: NOQUOTA VALBLKR
      VALBLKW
Length 10 00000000 00000000 .....
Kernel mode 00000000 00000000 .....
System 00000000 00000000 .....

```

Local copy

Lock Database

```

Lock id: 0A000004          PID: 0001000F   Flags: VALBLK CONVERT
      SYNCSTS
Par. id: 00000000          SUBLCKs: 0           SYSTEM NODLCKW
      NODLCKB
LKB: FFFFFFFF.7DF48350    BLKAST: 81190420   QUECVT
Priority: 0000

```

```

Granted at EX 00000000-FFFFFFFF

```

```

RSB: FFFFFFFF.7DF50850
Resource: 004F0FDF 24534D52 RMS$$b.O. Status: VALBLKR VALBLKW
      Length 26 5F313039 58020000 ...X901_
      Exec. mode 00202020 204C354B K5L .
      System 00000000 00000000 .....

```

Local copy

.

2. SDA> SHOW RESOURCES/LOCKID=0A000004

Resource Database

```

RSB:          FFFFFFFF.7DF50850  GGMODE:      EX  Status: DIRENTR VALID
Parent RSB:   00000000.00000000  CGMODE:      EX
Sub-RSB count: 0                FGMODE:      EX
Lock Count:   1                 RQSEQNM:    0000
BLKAST count: 1                 CSID: 00000000  (MILADY)

```

```

Resource:     004F0FDF 24534D52  RMS$$$.O.  Valblk: 00000000
00000000
Length 26     5F313039 58020000  ...X901_    00000000
00000000
Exec. mode    00202020 204C354B  K5L      .
System        00000000 00000000  ....     Seqnum: 00000000

```

```

Granted queue (Lock ID / Gr mode / Range):
0A000004 EX 00000000-FFFFFFFF

```

```

Conversion queue (Lock ID / Gr mode / Range -> Rq mode / Range):
*** EMPTY QUEUE ***

```

```

Waiting queue (Lock ID / Rq mode / Range):
*** EMPTY QUEUE ***

```

This SDA session shows the output of the SHOW LOCKS command for several locks. The SHOW RESOURCES command, executed for the last displayed lock, verifies that the lock is in the resource's granted queue. (See Table 4-26 for a full explanation of the contents of the display of the SHOW RESOURCES command.)

3. SDA> SHOW LOCK/BRIEF/BLOCKING

Lock Database

LKB Address	Lockid	ParentId	PID	BLKAST	SubLocks	RQ	GR	Queue	RSB Address	Resource Name	Mode
FFFFFFFF.7FF42450	51000003	00000000	00000000	80CC7648	0	CR	Granted	FFFFFFFF.7FF45050	F11B\$B\$WPCTX_DUMPS	Kern	
FFFFFFFF.7FF42850	01000005	00000000	00000000	80CB5020	111	CR	Granted	FFFFFFFF.7FF42950	F11B\$vX6JU_R3N	Kern	
FFFFFFFF.7FF42A50	01000006	00000000	00000000	80CB3D98	0	PR	Granted	FFFFFFFF.7FF42B50	VCC\$VX6JU_R3N	Kern	
FFFFFFFF.7FF42E50	40000008	00000000	00000000	80CC7648	0	CR	Granted	FFFFFFFF.7FF43150	F11B\$X6JU_R3N	Kern	
FFFFFFFF.7FF43E50	13000010	00000000	00000000	80CB3D98	0	PR	Granted	FFFFFFFF.7FF53D50	VCC\$VSWPCTX_DUMPS	Kern	
FFFFFFFF.7FF48750	12000033	03000094	00010008	80CE7220	0	PW	Granted	FFFFFFFF.7FF48E50	APPENDER	Exec	
FFFFFFFF.7FF49550	1500003A	00000000	00010008	00010B20	0	CR	Granted	FFFFFFFF.7FF54E50	AUDRSV\$DJ.....X6JU_R3N	User	
FFFFFFFF.7FF49B50	1300003D	00000000	00010007	00035EF8	0	CR	Granted	FFFFFFFF.7FF56250	OPCSopcom-restart	User	
FFFFFFFF.7FF4BE50	2100004F	00000000	0001000B	80CE66F0	4	NL	Granted	FFFFFFFF.7FF4DC50	RMS\$y.....X6JU_R3N	Exec	
FFFFFFFF.7FF4C950	13000054	00000000	0001000B	80CE66F0	0	EX	Granted	FFFFFFFF.7FF4CE50	RMS\$B.O.....X6JU_R3N	Exec	
FFFFFFFF.7FF4E050	0800005F	00000000	00010009	80CE66F0	4	NL	Granted	FFFFFFFF.7FF4AD50	RMS\$E.....X6JU_R3N	Exec	
FFFFFFFF.7FF4EA50	0C000064	00000000	00010007	00035F30	0	CR	Granted	FFFFFFFF.7FF56150	OPCSopcom-abort	User	
FFFFFFFF.7FF51350	18000078	00000000	00010011	0000B930	0	PR	Granted	FFFFFFFF.7FF44E50	NET\$NETPROXY_MODIFIED	Kern	
FFFFFFFF.7FF52850	0C000082	00000000	00000000	80CB5020	0	CR	Granted	FFFFFFFF.7FF43550	F11B\$VSWPCTX_DUMPS	Kern	
FFFFFFFF.7FF53250	09000087	00000000	00010008	80CE66F0	4	EX	Granted	FFFFFFFF.7FF49850	RMS\$J.....X6JU_R3N	Exec	
FFFFFFFF.7FF54C50	2700008E	00000000	0001000A	80CE66F0	2	EX	Granted	FFFFFFFF.7FF53750	RMS\$.O.....X6JU_R3N	Exec	
FFFFFFFF.7FF54750	03000094	00000000	00010008	80CE66F0	2	EX	Granted	FFFFFFFF.7FF4A950	RMS\$K.....X6JU_R3N	Exec	
FFFFFFFF.7FF54B50	04000098	10000042	00010008	00011358	0	CR	Granted	FFFFFFFF.7FF55050	WRITER	User	
FFFFFFFF.7FF54D50	05000099	11000047	00010009	00010F48	0	PR	Granted	FFFFFFFF.7FF56F50	JBC\$_CHECK_DB	User	
FFFFFFFF.7FF55150	0100009A	10000042	00010008	000112E0	0	CR	Granted	FFFFFFFF.7FF55250	DOORBELL	User	
FFFFFFFF.7FF55350	0200009B	00000000	00010008	00010B20	0	CR	Granted	FFFFFFFF.7FF55450	AUDRSV\$DK.....X6JU_R3N	User	
FFFFFFFF.7FF55550	0200009C	00000000	00010008	80CE66F0	2	EX	Granted	FFFFFFFF.7FF55850	RMS\$L.....X6JU_R3N	Exec	
FFFFFFFF.7FF55D50	020000A0	00000000	00010008	000123B0	0	CR	Granted	FFFFFFFF.7FF55C50	AUDRSV\$OL.....X6JU_R3N	User	
FFFFFFFF.7FF57250	040000A9	00000000	0001000A	80CE66F0	2	EX	Granted	FFFFFFFF.7FF4AD50	RMS\$E.....X6JU_R3N	Exec	
FFFFFFFF.7FF57A50	030000AF	110000AA	0001000A	00012628	0	PR	Granted	FFFFFFFF.7FF57D50	QMAN\$REF.....	User	
FFFFFFFF.7FF58150	010000B2	110000AA	0001000A	000109C0	0	PR	Granted	FFFFFFFF.7FF58050	QMAN\$NEW_JOBCTL	User	
FFFFFFFF.7FF58E50	050000B9	110000AA	0001000A	000147F8	0	PR	Granted	FFFFFFFF.7FF58F50	QMAN\$MASTER_QUEUES	User	

This example shows the brief display for all locks with a blocking AST.

4.56. SHOW MACHINE_CHECK

Displays the contents of the stored machine check frame. This command is valid for the DEC 4000 Alpha, DEC 7000 Alpha, and DEC 10000 Alpha computers only.

Format

```
SHOW MACHINE_CHECK [/FULL] [cpu-id]
```

Parameters

cpu-id

Numeric value indicating the identity of the CPU for which context information is to be displayed. This parameter changes the SDA current CPU (the default) to the CPU specified with **cpu-id**. If you specify the **cpu-id** of a processor that was not active at the time of the system failure, SDA displays the following message:

```
%SDA-E-CPUNOTVLD, CPU not booted or CPU number out of range
```

If you use the **cpu-id** parameter, the **SHOW MACHINE_CHECK** command performs an implicit **SET CPU** command, making the CPU indicated by **cpu-id** the current CPU for subsequent SDA commands. (See the description of the **SET CPU** command and Section 2.5 for information on how this can affect the CPU context---and process context---in which SDA commands execute.)

Qualifiers

/FULL

Specifies that a detailed version of the machine check information be displayed. This is currently identical to the default summary display.

Description

The **SHOW MACHINE_CHECK** command displays the contents of the stored machine check frame. A separate frame is allocated at boot time for every CPU in a multiple-CPU system. This command is valid for the DEC 4000 Alpha, DEC 7000 Alpha, and DEC 10000 Alpha computers only.

If you do not specify a qualifier, a summary version of the machine check frame is displayed.

The default **cpu-id** is the SDA current CPU.

Examples

```
1. SDA> SHOW MACHINE_CHECK
CPU 00 Stored Machine Check Crash Data
-----
Processor specific information:
-----
Exception address:      FFFFFFFF.800B0250      Exception Summary:
00000000.00000000
Pal base address:      00000000.00008000      Exception Mask:
00000000.00000000
HW Interrupt Request:  00000000.00000342      HW Interrupt Ena:
00000001.FFC01CE0
MM_CSR                 00000000.00003640      ICCSR:
00000002.381F0000
D-cache address:      00000007.FFFFFFFF      D-cache status:
00000000.000002E0
```

```

BIU status:          00000000.00000050    BIU address [7..0]:
  00000000.000060E0
BIU control:        00000008.50006447    Fill Address:
  00000000.00006120
Single-bit syndrome: 00000000.00000000    Processor mchck VA:
  00000000.00006190
A-box control:      00000000.0000040E    B-cache TAG:
  00106100.83008828
System specific information:
-----
Garbage bus info:   00200009 00000038    Device type:
  000B8001
LCNR:              00000001    Memory error:
  00000000
LBER:              00000009    Bus error synd 0,1: 00000000
  00000000
Bus error cmd:     00048858 00AB1C88    Bus error synd 2,3: 00000000
  0000002C
LEP mode:          00010010    LEP lock address:
  00041108

```

The `SHOW MACHINE_CHECK` command in this SDA display shows the contents of the stored machine check frame.

2. SDA> SHOW MACHINE_CHECK 1

CPU 01 Stored Machine Check Crash Data

Processor specific information:

```

Exception address:  FFFFFFFF.800868A0    Exception Summary:
  00000000.00000000
Pal base address:   00000000.00008000    Exception Mask:
  00000000.00000000
HW Interrupt Request: 00000000.00000342    HW Interrupt Ena:
  00000000.1FFE1CE0
MM_CSR              00000000.00005BF1    ICCSR:
  00000000.081F0000
D-cache address:    00000007.FFFFFFFF    D-cache status:
  00000000.000002E0
BIU status:         00000000.00000050    BIU address [7..0]:
  00000000.000063E0
BIU control:        00000008.50006447    Fill Address:
  00000000.00006420
Single-bit syndrome: 00000000.00000000    Processor mchck VA:
  00000000.00006490
A-box control:      00000000.0000040E    B-cache TAG:
  35028EA0.50833828
System specific information:
-----
Garbage bus info:   00210001 00000038    Device type:
  000B8001
LCNR:              00000001    Memory error:
  00000080
LBER:              00040209    Bus error synd 0,1: 00000000
  00000000
Bus error cmd:     00048858 00AB1C88    Bus error synd 2,3: 00000000
  0000002C

```

```
LEP mode:                00010010    LEP lock address:
00041108
```

The SHOW MACHINE_CHECK command in this SDA display shows the contents of the stored machine check frame for **cpu-id** 01.

4.57. SHOW MEMORY

Displays the availability and usage of memory resources.

Format

```
SHOW MEMORY [ /ALL ][ /BUFFER_OBJECTS ][ /CACHE ][ /FILES ]
[ /FULL ][ /GH_REGIONS ][ /PHYSICAL_PAGES ][ /POOL ]
[ /RESERVED ][ /SLOTS ]
```

Parameters

None.

Qualifiers

/ALL

Displays all available information, that is, information displayed by the following qualifiers:

- /BUFFER_OBJECTS
- /CACHE
- /FILES
- /GH_REGIONS
- /PHYSICAL_PAGES
- /POOL
- /RESERVED
- /SLOTS

This is the default display.

/BUFFER_OBJECTS

Displays information about system resources used by buffer objects.

/CACHE

Displays information about either the Virtual I/O Cache facility or the Extended File Cache facility. The system parameter VCC_FLAGS determines which is used. The cache facility information is displayed as part of the SHOW MEMORY and SHOW MEMORY/CACHE/FULL commands.

/FILES

Displays information about the use of each paging and swapping file currently installed.

/FULL

When used with the **/POOL** and **/CACHE** qualifiers, displays additional information. This qualifier is ignored otherwise. For **/CACHE**, the additional information is only displayed when the Virtual I/O Cache facility is in use (Alpha only); **/FULL** is ignored if the Extended File Cache facility is in use. Additional information on how memory is being used by the Extended File Cache facility can be obtained using the XFC extension described in Chapter 9.

/GH_REGIONS

Displays information about the granularity hint regions (GHR) that have been established. For each of these regions, information is displayed about the size of the region, the amount of free memory, the amount of memory in use, and the amount of memory released to OpenVMS from the region. The granularity hint regions information is also displayed as part of **SHOW MEMORY** and **SHOW MEMORY/ALL** commands.

/PHYSICAL_PAGES

Displays information about the amount of physical memory and the number of free and modified pages.

/POOL

Displays information about the usage of each dynamic memory (pool) area, including the amount of free space and the size of the largest contiguous block in each area.

/RESERVED

Displays information about memory reservations.

/SLOTS

Displays information about the availability of process control block (PCB) vector slots and balance slots.

Description

For more information about the **SHOW MEMORY** command, see the description in the *VSI OpenVMS DCL Dictionary* or online help.

4.58. SHOW PAGE_TABLE

Displays a range of system page table entries, the entire system page table, or the entire global page table.

Format

```
SHOW PAGE_TABLE [range | /FREE [/HEADER=address ]  
| /GLOBAL | /GPT | /PT
```

```
| /INVALID_PFN [=option]
| /NONMEMORY_PFN [=option]
| /PTE_ADDRESS | /SECTION_INDEX=n
| /S0S1 (d) | /S2 | /SPTW | /ALL]
[/L1 | /L2 | /L3 (d)]
```

Parameters

range

Range of virtual addresses or PTE addresses for which SDA displays page table entries. If the qualifier `/PTE_ADDRESS` is given, then the range is of PTE addresses; otherwise, the range is of virtual addresses. The range given can be of process-space addresses.

If `/PTE_ADDRESS` is given, the range is expressed using the following syntax:

<i>m</i>	Displays the single page table entry at address <i>m</i>
<i>m:n</i>	Displays the page table entries from address <i>m</i> to address <i>n</i>
<i>m;n</i>	Displays <i>n</i> bytes of page table entries starting at address <i>m</i>

If `/PTE_ADDRESS` is not given, then range is expressed using the following syntax:

<i>m</i>	Displays the single page table entry that corresponds to virtual address <i>m</i>
<i>m:n</i>	Displays the page table entries that correspond to the range of virtual addresses from <i>m</i> to <i>n</i>
<i>m;n</i>	Displays the page table entries that correspond to a range of <i>n</i> bytes starting at virtual address <i>m</i>

Note that OpenVMS Alpha and Integrity servers page protections are slightly different. For additional information, see Section 2.8.

Qualifiers

/FREE

Causes the starting addresses and sizes of blocks of pages in the free PTE list to be displayed. The qualifiers `/S0S1` (default), `/S2`, `/GLOBAL`, and `/HEADER` determine which free PTE list is to be displayed. A range cannot be specified, and no other qualifiers can be combined with `/FREE`.

/GLOBAL

Lists the global page table. When used with the `/FREE` qualifier, `/GLOBAL` indicates the free PTE list to be displayed.

/HEADER=*address*

When used with the /FREE qualifier, the /HEADER=*address* qualifier displays the free PTE list for the specified private page table.

/GPT

Specifies the portion of page table space that maps the global page table as the address range.

/INVALID_PFN [=option]

The /INVALID_PFN qualifier, which is valid only on platforms that supply an I/O memory map, causes SDA to display only page table entries that map to PFNs that are not in the system's private memory or in Galaxy-shared memory, and which are not I/O access pages.

/INVALID_PFN has two optional keywords, READONLY and WRITABLE. If neither keyword is specified, all relevant pages are displayed.

If READONLY is specified, only pages marked for no write access are displayed. If WRITABLE is specified, only pages that allow write access are displayed. For example, SHOW PAGE_TABLE/ALL/INVALID_PFN=WRITABLE would display all system pages whose protection allows write, but which map to PFNs that do not belong to this system.

/L1**/L2****/L3 (D)**

Specifies the level for which page table entries are to be displayed for the specified portion of memory. You can specify only one level. /L3 is the default.

/NONMEMORY_PFN [=option]

The /NONMEMORY_PFN qualifier causes SDA to display only page table entries that are not in the system's private memory or in Galaxy-shared memory.

/NONMEMORY_PFN has two optional keywords, READONLY and WRITABLE. If neither keyword is specified, all relevant pages are displayed.

If READONLY is specified, only pages marked for no write access are displayed. If WRITABLE is specified, only pages that allow write access are displayed. For example, SHOW PAGE_TABLE/ALL/NONMEMORY_PFN=WRITABLE would display all system pages whose protection allows write, but which map to PFNs that do not belong to this system.

/PT

Specifies that the page table entries for the page table region of system space are to be displayed.

/PTE_ADDRESS

Specifies that the range given is of PTE addresses instead of the virtual addresses mapped by the PTEs.

/SECTION_INDEX=*n*

Displays the page table for the range of pages in the global section or pageable part of a loaded image. For pageable portions of loaded images, one of the qualifiers /L1, /L2, or /L3 can also be specified.

/S0S1 (D)**/S2**

Specifies the region whose page table entries are to be displayed. When used with the /FREE qualifier, indicates the free PTE list to be displayed. By default, the page table entries or the free list for S0 & S1 space is displayed.

/SPTW

Displays the contents of the system page table window.

/ALL

Displays the page table entries for all shared (system) addresses. It is equivalent to specifying all of /S0S1, /S2, and /PT.

Description

If the /FREE qualifier is not specified, this command displays page table entries for the specified range of addresses or section of memory. For each virtual address displayed by the SHOW PAGE_TABLE command, the first eight columns of the listing provide the associated page table entry and describe its location, characteristics, and contents. SDA obtains this information from the system page table or from the process page table if a process_space address is given. The table below describes the information displayed by the SHOW PAGE_TABLE command.

If the /FREE qualifier is specified, this command displays the free PTE list for the specified section of memory.

The /L1, /L2, and /L3 qualifiers are ignored when used with the /FREE, /GLOBAL, and /SPTW qualifiers.

Table 4.4. Virtual Page Information in the SHOW PAGE_TABLE Display

Value	Meaning
MAPPED ADDRESS	Virtual address that marks the base of the virtual page(s) mapped by the PTE.
PTE ADDRESS	Virtual address of the page table entry that maps the virtual page(s).
PTE	Contents of the page table entry, a quadword that describes a system virtual page.
TYPE	Type of virtual page. Table 4.5 shows the eight types and their meanings.
READ	(Alpha only.) A code, derived from bits in the PTE, that designates the processor access modes (kernel, executive, supervisor, or user) for which read access is granted.

Value	Meaning
WRIT	(Alpha only.) A code, derived from bits in the PTE, that designates the processor access modes (kernel, executive, supervisor, or user) for which write access is granted.
MLOA	(Alpha only.) Letters that represent the setting of a bit or a combination of bits in the PTE. These bits indicate attributes of a page. Table 4.6 shows the codes and their meanings.
AR/PL	(Integrity servers only) The access rights and privilege level of the page. Consists of a number (0-7) and a letter (K, E, S, or U) that determines access to a page in each mode.
KESU	(Integrity servers only) The access allowed to the page in each mode. This is an interpretation of the AR/PL values in the previous column. For an explanation of the access codes, see Section 2.8.
MLO	(Integrity servers only) Letters that represent the setting of a bit or a combination of bits in the PTE. These bits indicate attributes of a page. Table 4.6 shows the codes and their meanings.
GH	Contents of granularity hint bits.

Table 4.5. Types of Virtual Pages

Type	Meaning
VALID	Valid page (in main memory).
TRANS	Transitional page (on free or modified page list).
DZERO	Demand-allocated, zero-filled page.
PGFIL	Page within a paging file.
STX	Section table's index page.
GPTX	Index page for a global page table.
IOPAG	Page in I/O address space.
NXMEM	Page not represented in physical memory. The page frame number (PFN) of this page is not mapped by any of the system's memory controllers. This indicates an error condition.

Table 4.6. Bits In the PTE

Column Name	Code	Meaning
M	M	Page has been modified.
L	L	Page is locked into a working set.
L	P	Page is locked in physical memory.
O	K	Owner is kernel mode.

Column Name	Code	Meaning
O	E	Owner is executive mode.
O	S	Owner is supervisor mode.
O	U	Owner is user mode.
A	A	Address space match is set (Alpha only).

If the virtual page has been mapped to a physical page, the last five columns of the listing include information from the page frame number (PFN) database; otherwise, the section is left blank. Table 4.7 describes the physical page information displayed by the SHOW PAGE_TABLE command.

Table 4.7. Physical Page Information in the SHOW PAGE_TABLE Display

Category	Meaning
PGTYP	Type of physical page. Table 4.8 shows the types of physical pages.
LOC	Location of the page within the system. Table 4.9 shows the possible locations with their meaning.
BAK	Place to find information on this page when all links to this PTE are broken: either an index into a process section table or the number of a virtual block in the paging file.
REFCNT	Number of references being made to this page.
WSLX	Working Set List Index. This shows as zero for resident and global pages, and is left blank for transition pages.

Table 4.8. Types of Physical Pages

Page Type	Meaning
PROCESS	Page is part of process space.
SYSTEM	Page is part of system space.
GLOBAL	Page is part of a global section.
GBLWRT	Page is part of a global, writable section.
PPGTBL	Page is part of a process page table.
GPGTBL	Page is part of a global page table.
PHD	Page is part of a process PHD. These page types are variants of the PPGTBL page type.
PPT(Ln)	Page is a process page table page at level <i>n</i> . These page types are variants of the PPGTBL page type.
WSL	Page is part of a process's working list. These page types are variants of the PPGTBL page type.
SPT(Ln)	Page is a system page table page at level <i>n</i> . These page types are variants of the SYSTEM page type.
SHPT	Page is part of a shared page table. These page types are variants of the GBLWRT page type.

Page Type	Meaning
PFNLST	Page is in a Shared Memory Common Property Partition PFN database. These page types are variants of the SYSTEM page type.
SHM_REG	Page is in a Shared Memory Region. These page types are variants of the GBLWRT page type.
UNKNOWN	Unknown.

Table 4.9. Locations of Physical Pages

Location	Meaning
ACTIVE	Page is in a working set.
MFYLST	Page is in the modified page list.
FRELST	Page is in the free page list.
BADLST	Page is in the bad page list.
REL PND	Release of the page is pending.
RDERR	Page has had an error during an attempted read operation.
PAGOUT	Page is being written into a paging file.
PAGIN	Page is being brought into memory from a paging file.
ZROLST	Page is in the zeroed-page list.
UNKNWN	Location of page is unknown.

SDA indicates pages are inaccessible by displaying one of the following messages:

```
----- 1 null page:      VA  FFFFFFFF.E00064000  PTE
FFFFFFFFD.FF800190

----- 974 null pages:  VA  FFFFFFFF.E00064000  PTE
FFFFFFFFD.FF800190
                                -to- FFFFFFFF.E007FDFFF  -to-
FFFFFFFFD.FF801FF8
```

In this case, the page table entries are not in use (page referenced is inaccessible).

```
----- 1 entry not in memory:  VA  FFFFFFFF.E00800000  PTE
FFFFFFFFD.FF802000

----- 784384 entries not in memory:  VA  FFFFFFFF.E00800000  PTE
FFFFFFFFD.FF802000
                                -to- FFFFFFFF.7F7FDFFF  -to-
FFFFFFFFD.FFD7FDFFF8
```

In this case, the page table entries do not exist (PTE itself is inaccessible).

```
----- 1 free PTE:      VA  FFFFFFFF.7F800000  PTE  FFFFFFFFD.FFD7FE000
----- 1000 free PTEs:  VA  FFFFFFFF.7F800000  PTE  FFFFFFFFD.FFD7FE000
```

```
-t0- FFFFFFFF.7FFCDFFF -t0- FFFFFFFD.FFDFFF38
```

In this case, the page table entries are in the list of free system pages.

In each case, VA is the MAPPED ADDRESS of the skipped entry, and PTE is the PTE ADDRESS of the skipped entry.

Examples

1. For an example of SHOW PAGE_TABLE output when the qualifier /FREE has not been given, see the SHOW PROCESS/PAGE_TABLES command.

2. SDA> SHOW PAGE_TABLE/FREE
S0/S1 Space Free PTEs

```
-----
```

MAPPED ADDRESS	PTE ADDRESS	PTE	COUNT
FFFFFFFF.82A08000	FFFFFFFD.FFE0A820	0001FFE0.A8580000	00000003
FFFFFFFF.82A16000	FFFFFFFD.FFE0A858	0001FFE0.A8900000	00000003
FFFFFFFF.82A24000	FFFFFFFD.FFE0A890	0001FFE0.B3C00000	00000003
FFFFFFFF.82CF0000	FFFFFFFD.FFE0B3C0	0001FFE0.B4010000	00000001
FFFFFFFF.82D00000	FFFFFFFD.FFE0B400	0001FFE0.B4680000	00000002
.			
.			
.			
FFFFFFFF.82E48000	FFFFFFFD.FFE0B920	0001FFE0.B9390000	00000001
FFFFFFFF.82E4E000	FFFFFFFD.FFE0B938	0001FFE0.BA200000	00000002
FFFFFFFF.82E88000	FFFFFFFD.FFE0BA20	0001FFE0.C9780000	00000003
FFFFFFFF.8325E000	FFFFFFFD.FFE0C978	0001FFE0.CC980000	00000003
FFFFFFFF.83326000	FFFFFFFD.FFE0CC98	00000000.00000000	0000066D

This example shows the output when you invoke the SHOW PAGE_TABLE/FREE command.

4.59. SHOW PARAMETER

Displays the name, location, and value of one or more SYSGEN parameters currently in use or at the time that the system dump was taken.

Format

```
SHOW PARAMETER [sysgen_parameter]
```

```
[/ACP] [/ALL] [/CLUSTER] [/DYNAMIC] [/GALAXY] [/GEN] [/JOB] [/LGI] [/MAJOR] [/MULTI]
```

Parameter

sysgen_parameter

The name of a specific parameter to be displayed. The name can include wildcards. However, a truncated name is not recognized, unlike with the equivalent SYSGEN and SYSMAN commands.

Qualifiers

/ACP

Displays all Files-11 ACP parameters.

/ALL

Displays the values of all parameters except the special control parameters.

/CLUSTER

Displays all parameters specific to clusters.

/DYNAMIC

Displays all parameters that can be changed on a running system.

/GALAXY

Displays all parameters specific to Galaxy systems.

/GEN

Displays all general parameters.

/JOB

Displays all Job Controller parameters.

/LGI

Displays all LOGIN security control parameters.

/MAJOR

Displays the most important parameters.

/MULTIPROCESSING

Displays parameters specific to multiprocessing.

/OBSOLETE

Displays all obsolete system parameters. SDA displays obsolete parameters only if they are named explicitly (no wildcards) or if /OBSOLETE is given.

/PQL

Displays the parameters for all default and minimum process quotas.

/RMS

Displays all parameters specific to OpenVMS Record Management Services (RMS).

/SCS

Displays all parameters specific to OpenVMS Cluster System Communications Services.

/SPECIAL

Displays all special control parameters.

/STARTUP

Displays the name of the site-independent startup procedure.

/SYS

Displays all active system parameters.

/TTY

Displays all parameters for terminal drivers.

Description

The SHOW PARAMETER command displays the name, location, and value of one or more SYSGEN parameters at the time that the system dump is taken. You can specify either a parameter name, or one or more qualifiers, but not both a parameter and qualifiers. If you do not specify a parameter or qualifiers, then the last parameter displayed is displayed again.

The qualifiers are the equivalent to those available for the SHOW [parameter] command in the SYSGEN utility and the PARAMETERS SHOW command in the SYSMAN utility. See the *VSI OpenVMS System Management Utilities Reference Manual* for more information about these two commands. You can combine qualifiers, and all appropriate SYSGEN parameters are displayed.

Note

To see the entire set of parameters, use the SDA command SHOW PARAMETER /ALL /SPECIAL /STARTUP /OBSOLETE.

Examples

1. SDA> SHOW PARAMETER *SCS*

Parameter	Variable	Address	Value	(decimal)	Offset
SCSBUFFCNT	SCS\$GW_BDTCNT	80C159A0	0032	50	
SCSCONNCNT	SCS\$GW_CDTCNT	80C159A8	0005	5	
SCSRESPCNT	SCS\$GW_RDTCNT	80C159B0	012C	300	
SCSMAXDG	SCS\$GW_MAXDG	80C159B8	0240	576	
SCSMAXMSG	SCS\$GW_MAXMSG	80C159C0	00D8	216	
SCSFLOWCUSH	SCS\$GW_FLOWCUSH	80C159C8	0001	1	
SCSSYSTEMID	SCS\$GB_SYSTEMID	80C159D0	0000FB88	65160	
SCSSYSTEMIDH	SCS\$GB_SYSTEMIDH	80C159D8	00000000	0	
SCSNODE	SCS\$GB_NODENAME	80C159E0	"SWPCTX "		
NISCS_CONV_BOOT	CLU\$GL_SGN_FLAGS	80C15E68	0	0	CLU\$V_NISCS_CONV_BOOT (1)
NISCS_LOAD_PEA0	CLU\$GL_SGN_FLAGS	80C15E68	0	0	CLU\$V_NISCS_LOAD_PEA0 (0)
NISCS_PORT_SERV	CLU\$GL_NISCS_PORT_SERV	80C15E70	00000000	0	
SCSICLUSTER_P1	SGN\$GB_SCSICLUSTER_P1	80C15EF8	" "		
SCSICLUSTER_P2	SGN\$GB_SCSICLUSTER_P2	80C15F00	" "		
SCSICLUSTER_P3	SGN\$GB_SCSICLUSTER_P3	80C15F08	" "		
SCSICLUSTER_P4	SGN\$GB_SCSICLUSTER_P4	80C15F10	" "		
NISCS_MAX_PKT SZ	CLU\$GL_NISCS_MAX_PKT SZ	80C16070	000005DA	1498	
NISCS_LAN_OVRHD	CLU\$GL_NISCS_LAN_OVRHD	80C16078	00000012	18	

This example shows all parameters that have the string "SCS" in their name. For parameters defined as a single bit, the name and value of the bit offset within the location used for the parameter are also given.

2. SDA> SHOW PARAMETER WS*

Parameter	Variable	Address	Value	(decimal)	Offset
WSMAX	SGN\$GL_MAXWSCNT_PAGELETS	80C15710	00006800	26624	
(internal)	SGN\$GL_MAXWSCNT_PAGES	80C15718	00000680	1664	
WSINC	SCH\$GL_WSINC_PAGELETS	80C157F8	00000960	2400	
(internal)	SCH\$GL_WSINC_PAGES	80C15800	00000096	150	
WSDEC	SCH\$GL_WSDEC_PAGELETS	80C15808	00000FA0	4000	
(internal)	SCH\$GL_WSDEC_PAGES	80C15810	000000FA	250	

This example shows all parameters whose names begin with the string "WS". For parameters that have both an external value (pagelets) and an internal value (pages), both are displayed.

```
3. SDA> SHOW PARAMETER /MULTIPROCESSING /STARTUP
```

```
SYSGEN parameters
```

```
-----
```

Parameter	Variable	Address	Value	(decimal)	Offset
SMP_CPUS	SGN\$GL_SMP_CPUS	80C15688	FFFFFFFF	-1	
MULTIPROCESSING	SGN\$GB_MULTIPROCESSING	80C15698	03	3	
SMP_SANITY_CNT	SGN\$GL_SMP_SANITY_CNT	80C156A8	0000012C	300	
SMP_SPINWAIT	SGN\$GL_SMP_SPINWAIT	80C156B8	000186A0	100000	
SMP_LNGSPINWAIT	SGN\$GL_SMP_LNGSPINWAIT	80C156C0	002DC6C0	3000000	
IO_PREFER_CPUS	SMP\$GL_AVAILABLE_PORT_CPUS	80C16130	FFFFFFFF	-1	

```
Startup command file = SYSS$SYSTEM:STARTUP.COM
```

This example shows all the parameters specific to multiprocessing, plus the name of the site-independent startup command procedure.

4.60. SHOW PFN_DATA

Displays information that is contained in the page lists and PFN database.

Format

```
SHOW PFN_DATA { [/qualifier] | pfn [{:end-pfn|;length}] }
```

or

```
SHOW PFN_DATA/MAP
```

Parameters

PFN

Page frame number (PFN) of the physical page for which information is to be displayed.

end-pfn

Last PFN to be displayed. When you specify the **end-pfn** parameter, a range of PFNs is displayed. This range starts at the PFN specified by the **PFN** parameter and ends with the PFN specified by the **end-pfn** parameter.

length

Length of the PFN list to be displayed. When you specify the **length** parameter, a range of PFNs is displayed. This range starts at the PFN specified by the **PFN** parameter and contains the number of entries specified by the **length** parameter.

Qualifiers

```
/ADDRESS=PFN-entry-address
```

Displays the PFN database entry at the address specified. The address specified is rounded to the nearest entry address, so if you have an address that points to one of the fields of the entry, the correct database entry will still be found.

```
/ALL
```

Displays the following lists:

Free page list

Zeroed free page list

Modified page list

Bad page list

Untested page list

Private page lists, if any

Per-color or per-RAD free and zeroed free page lists

Entire database in order by page frame number

This is the default behavior of the SHOW PFN_DATA command. SDA precedes each list with a count of the pages it contains and its low and high limits.

/BAD

Displays the bad page list. SDA precedes the list with a count of the pages it contains, its low limit, and its high limit.

/COLOR [= {*n*|ALL}]

Displays data on page coloring. The table below shows the command options available with the COLOR and RAD qualifiers, which are functionally equivalent.

Table 4.10. Command Options with the /COLOR and /RAD Qualifiers

Options	Meaning
/COLOR 1 with no value	Displays a summary of the lengths of the color 1 page lists for both free pages and zeroed pages.
/COLOR= <i>n</i> where <i>n</i> is a color number	Displays the data in the PFN lists (for the specified color) for both free and zeroed pages.
/COLOR=ALL	Displays the data in the PFN lists (for all colors), for both free and zeroed free pages.
/COLOR= <i>n</i> or /COLOR=ALL with /FREE or /ZERO	Displays only the data in the PFN list (for the specified color or all colors), for either free or zeroed free pages as appropriate. The qualifiers /BAD and /MODIFIED are ignored with /COLOR= <i>n</i> and /COLOR=ALL.
/COLOR without an option specified together with one or more of /FREE, /ZERO, /BAD, or /MODIFIED	Displays the color summary in addition to the display of the requested list.

Wherever COLOR is used in this table, RAD is equally applicable, both in the qualifier name and the meaning.

For more information on page coloring, see *VSI OpenVMS System Management Utilities Reference Manual: M-Z*.

/FREE

Displays the free page list. SDA precedes the list with a count of the pages it contains, its low limit, and its high limit.

/MAP

Displays the contents of the PFN memory map. On platforms that support it, the I/O space map is also displayed. You cannot combine the /MAP qualifier with any parameters or other qualifiers.

/MODIFIED

Displays the modified page list. SDA precedes the list with a count of the pages it contains, its low limit, and its high limit.

/PRIVATE [=address]

Displays private PFN lists. If no address is given, all private PFN lists are displayed; if an address is given, only the PFN list whose head is at the given address is displayed.

/RAD [= {n|ALL}]

Displays data on the disposition of pages among the Resource Affinity Domains (RADs) on applicable systems. /RAD is functionally equivalent to /COLOR. See Table 4.10 for the command options available with /RAD.

/SUMMARY[=(option,...)]

By default, displays a summary of all pages in the system, totaling pages by page location (Free List, Modified List, Active, and so on) and by page type (Process, System, Global, and so on). Also, provides a breakdown of active system pages by their virtual address (S0/S1, S2, and so on).

Additional information is displayed if one or more options are given. If multiple options are given, they must be separated by commas and enclosed in parentheses. Available options are:

- /SUMMARY=PROCESS

Displays a breakdown of active process pages for each process by virtual address (P0, P1, and so on), and of non-active process pages by page location.

- /SUMMARY=GLOBAL

Displays a breakdown for each global section of its in-memory pages by page location.

- /SUMMARY=RAD

If RADs are enabled on the system, displays a breakdown for each RAD of its in-memory pages by location and type.

- /SUMMARY=ALL

Equivalent to /SUMMARY=(PROCESS,GLOBAL,RAD)

You cannot combine the /SUMMARY qualifier with any other qualifiers, but you can specify a range.

/SYSTEM

Displays the entire PFN database in order by page frame number, starting at PFN 0000.

/UNTESTED

Displays the state of the untested PFN list that was set up for deferred memory testing.

/ZERO

Displays the contents of the zeroed free page list.

Description

For each page frame number it displays, the SHOW PFN_DATA command lists information used in translating physical page addresses to virtual page addresses.

The display contains two or three lines: Table 4.11 shows the fields in line one, Table 4.12 shows the fields in line two, and Table 4.13 shows the fields in line three, displayed only if relevant (page table page or non-zero flags).

Table 4.11. PFN Data---Fields in Line One

Item	Contents
PFN	Page frame number.
DB ADDRESS	Address of PFN structure for this page.
PT PFN	PFN of the page table page that maps this page.
BAK	Place to find information on this page when all links to this PTE are broken: either an index into a process section table or the number of a virtual block in the paging file.
FLINK	Forward link within PFN database that points to the next physical page (if the page is on one of the lists: FREE, MODIFIED, BAD, or ZEROED); this longword also acts as the count of the number of processes that are sharing this global section.
BLINK	Backward link within PFN database (if the page is on one of the lists: FREE, MODIFIED, BAD, or ZEROED); also acts as an index into the working set list.
SWP/BO	Either a swap file page number or a buffer object reference count, depending on a flag set in the page state field.
LOC	Location of the page within the system. Table 4.9 shows the possible locations with their meaning.

Table 4.12. PFN Data---Fields in Line Two

Item	Contents
(Blank)	First field of line two is left blank.
PTE ADDRESS	Virtual address of the page table entry that describes the virtual page mapped into this physical page. If no virtual page is mapped into this physical page then "<no backpointer>" is displayed, and the next three fields are left blank.

Item	Contents
PTE Type	If a virtual page is mapped into this physical page, a description of the type of PTE is provided across the next three fields: one of "System-space PTE", "Global PTE (section index <i>nnnn</i>)", "Process PTE (process index <i>nnnn</i>)". If no virtual page is mapped into this physical page, these fields are left blank.
REFCNT	Number of references being made to this page.
PAGETYP	Type of physical page. See Table 4.8 for the types of physical pages and their meanings.

Table 4.13. PFN Data---Fields in Line Three

Item	Contents
COUNTS	If the page is a page table page, then the contents of the PRN\$W_PT_VAL_CNT, PFN\$W_PT_LCK_CNT, and PFN\$W_PT_WIN_CNT fields are displayed. The format is as follows: VALCNT = <i>nnnn</i> LCKCNT = <i>nnnn</i> WINCNT = <i>nnnn</i>
FLAGS	The flags in text form that are set in page state. Table 4.14 shows the possible flags and their meaning.

Table 4.14. Flags Set in Page State

Flag	Meaning
BUFOBJ	Set if any buffer objects reference this page
COLLISION	Indicates an empty collision queue when page read is complete
BADPAG	Indicates a bad page
RPTEVT	Indicates a report event on I/O completion
DELCON	Indicates a delete PFN when REFCNT=0
MODIFY	Indicates a dirty page (modified)
UNAVAILABLE	Indicates PFN is unavailable; most likely a console page
SWPPAG_VALID	Indicated swap file page number is valid
TOP_LEVEL_PT	Level one (1) page table
SLOT	Page is part of process's balance set
SHARED	Shared memory page
ZEROED	Shared memory page that has been zeroed

Examples

- SDA> SHOW PFN_DATA/MAP
System Memory Map

Start PFN	PFN count	Flags	
00000000	000000FA	0009	Console Base
000000FA	00003306	000A	OpenVMS Base
00003C00	000003FF	000A	OpenVMS Base
00003FFF	00000001	0009	Console Base
00003400	00000800	0010	Galaxy_Shared

This example shows the output when you invoke the SHOW PFN/MAP command.

2. SDA> SHOW PFN 598:59f

PFN data base for PFN range

PFN FLINK	DB BLINK	ADDRESS PTE ADDRESS	PT SWP/BO	PFN LOC	BAK
00000000.00000598	FFFFFF802.06C16600	00000000.000001D7	----	FFFFFFF8.84D6F700	
00000000.00000000	00000000.00000000	FFFFFF801.FFD072A0	----	ACTIVE	
			0001	SYSTEM	
00000000.00000599	FFFFFF802.06C16640	00000000.00000000	----	00000000.0001DBD9	
00000000.0001DBD9	00000000.000081B6		----	FRELST	
	<no backpointer>		0000	SYSTEM	
00000000.0000059A	FFFFFF802.06C16680	00000000.00000565	----	FF000000.00000000	
00000000.00000000	00000000.000000D4	000007FF.FF700000	----	ACTIVE	
			0001	PROCESS	
	FLAGS = Modify				
00000000.0000059B	FFFFFF802.06C166C0	00000000.0000493A	----	000000FD.00010000	
00000000.00000003	00000000.00000000	FFFFFF802.0F641680	----	ACTIVE	
			0001	GLOBAL	
00000000.0000059C	FFFFFF802.06C16700	00000000.000005E3	----	FF000000.00000000	
00000000.00000000	00000000.00000136	000007FE.00001C30	----	ACTIVE	
			0001	PROCESS	
00000000.0000059D	FFFFFF802.06C16740	00000000.0000059D	----	00000000.8705A000	
00000000.00000002	00000000.00000001	000007FF.FFFFFFFF8	----	ACTIVE	
			0001	PPT(L1)	
	VALCNT = 0002	LCKCNT = FFFF		WINCNT = FFFF	
	FLAGS = Modify, Top_Level_PT				
00000000.0000059E	FFFFFF802.06C16780	00000000.000001D7	----	FFFFFFF8.84D6F700	
00000000.00000000	00000000.00000000		----	ACTIVE	


```

          FFFFF801.FFD07420 System-space PTE
                        0001 SYSTEM

00000000.0000059F FFFFF802.06C167C0 00000000.000001D7 FFFFFFFF.84D6F700
00000000.00000000 00000000.00000000 ---- ACTIVE
          FFFFF801.FFD07428 System-space PTE
                        0001 SYSTEM

```

This example shows the output from `SHOW PFN` for a range of pages.

4.61. SHOW POOL

Displays the contents of the nonpaged dynamic storage pool, the bus-addressable pool, and the paged dynamic storage pool. You can display part or all of each pool. If you do not specify a range or qualifiers, the default is `SHOW POOL/ALL`. Optionally, you can display the pool history ring buffer and pool statistics.

Format

```

SHOW POOL [range | /ALL (d) | /BAP | /NONPAGED | /PAGED]
[ /BRIEF | /CHECK | /FREE | /HEADER | /MAXIMUM_BYTES [=n] | /SUMMARY | /TYPE=
[/RING_BUFFER[=address]]
[/STATISTICS [=ALL] [/NONPAGED | /BAP | /PAGED]

```

Parameter

range

Range of virtual addresses in pool that SDA is to examine. You can express a range using the following syntax:

<i>m:n</i>	Range of virtual addresses in pool from <i>m</i> to <i>n</i>
<i>m;n</i>	Range of virtual addresses in pool starting at <i>m</i> and continuing for <i>n</i> bytes

Qualifiers

/ALL

Displays the entire contents of the dynamic storage pool, except for those portions that are free (available). This is the default behavior of the `SHOW POOL` command.

/BAP

Displays the contents of the bus-addressable dynamic storage pool currently in use.

/BRIEF

Displays only general information about the dynamic storage pool and its addresses.

/CHECK

Checks all free packets for POOLCHECK-style corruption, in exactly the same way that the system does when generating a POOLCHECK crash dump.

/FREE

Displays the entire contents, both allocated and free, of the specified region or regions of pool. Use the /FREE qualifier with a range to show all of the used and free pool in the given range.

/HEADER

Displays only the first 16 bytes of each data packet found within the specified region or regions of pool.

/MAXIMUM_BYTES [=n]

Displays only the first n bytes of a pool packet; if you specify /MAXIMUM_BYTES without a value, the default is 64 bytes.

/NONPAGED

Displays the contents of the nonpaged dynamic storage pool currently in use.

/PAGED

Displays the contents of the paged dynamic storage pool currently in use.

/RING_BUFFER [=address]

Displays the contents of the pool history ring buffer if pool checking has been enabled. Entries are displayed in reverse chronological order, that is, most to least recent. If *address* is specified, the only entries in the ring buffer displayed are for pool blocks that *address* lies within.

/STATISTICS [= ALL]

Displays usage statistics about each lookaside list and the variable free list. For each lookaside list, its queue header address, packet size, the number of packets, attempts, fails, and deallocations are displayed. (If pool checking is disabled, the attempts, fails, and deallocations are not displayed.) For the variable free list, its queue header address, the number of packets and the size of the smallest and largest packets are displayed. You can further qualify /STATISTICS by using either /NONPAGED, /BAP, or /PAGED to display statistics for a specified pool area. Paged pool only has lookaside lists if the system parameter PAGED_LAL_SIZE has been set to a nonzero value; therefore paged pool lookaside list statistics are only displayed if there has been activity on a list.

If you specify /STATISTICS without the ALL keyword, only active lookaside lists are displayed. Use /STATISTICS = ALL to display all lookaside lists.

/SUBTYPE=*packet-type*

Displays the packets within the specified region or regions of pool that are of the indicated *packet-type*. For information on *packet-type*, see *packet-type* in the Description section.

/SUMMARY

Displays only an allocation summary for each specified region of pool.

/TYPE=*packet-type*

Displays the packets within the specified region or regions of pool that are of the indicated *packet-type*. For information on *packet-type*, see *packet-type* in the Description section.

/UNUSED

Displays only variable free packets and lookaside list packets, not used packets.

Description

The SHOW POOL command displays information about the contents of any specified region of dynamic storage pool. There are several distinct display formats, as follows:

- Pool layout display. This display includes the addresses of the pool structures and lookaside lists, and the ranges of memory used for pool.
- Full pool packet display. This display has a section for each packet, consisting of a summary line (the packet type, its start address and size, and, on systems that have multiple Resource Affinity Domains (RADs), the RAD number), followed by a dump of the contents of the packet in hexadecimal and ASCII.
- Header pool packet display. This display has a single line for each packet. This line contains the packet type, its start address and size, and, on systems that have multiple RADs, the RAD number, followed by the first 16 bytes of the packet, in hexadecimal and ASCII.
- Pool summary display. This display consists of a single line for each packet type, and includes the type, the number of occurrences and the total size, and the percentage of used pool consumed by this packet type.
- Pool statistics display. This display consists of statistics for variable free pool and for each lookaside list. For variable free pool, it includes the number of packets, the total bytes available, and the sizes of the smallest and largest packets. In addition, if pool checking is enabled, the total bytes allocated from the variable list and the number of times pool has been expanded are also displayed.

For lookaside lists, the display includes the listhead address and size, the number of packets (both the maintained count and the actual count), the operation sequence number for the list, the allocation attempts and failures, and the number of deallocations.

On systems with multiple RADs, statistics for on-RAD deallocations are included in the display for the first RAD.

- Ring buffer display. This display is only available when pool checking is enabled. It consists of one line for each packet in the ring buffer and includes the address and size of the pool packet being allocated or deallocated, its type, the PC of the caller and the pool routine called, the CPU and IPL of the call, and the system time.

Optionally, the ring buffer display can be limited to only the entries that contain a given address.

The qualifiers used on the SHOW POOL command determine which displays are generated. The default is the pool layout display, followed by the full pool packet display, followed by the pool summary display, these being generated in turn for Nonpaged Pool, Bus-Addressable Pool (if it exists in the system or dump being analyzed), and then Paged Pool.

If you specify a range, type, or subtype, then the pool layout display is not generated, and the pool summary display is a summary only for the range, type, or subtype, and not for the entire pool.

Not all displays are relevant for all pool types. For example, Paged Pool may have no lookaside lists, in which case the Paged Pool statistics display will consist only of variable free pool information. And because there is a single ring buffer for all pools, only one ring buffer display is generated even if all pools are being displayed.

Packet-type

Each packet of pool has a type field (a byte containing a value in the range of 0-255). Many of these type values have names associated that are defined in \$DYNDDEF in SYSS\$LIBRARY:LIB.MLB. The *packet-type* specified in the /TYPE qualifier of the SHOW POOL command can either be the value of the pool type or its associated name.

Some pool packet types have an additional subtype field (also a byte containing a value in the range of 0--255), many of which also have associated names. The *packet-type* specified in the /SUBTYPE qualifier of the SHOW POOL command can either be the value of the pool type or its associated name. However, if given as a value, a /TYPE qualifier (giving a value or name) must also be specified. Note also that /TYPE and /SUBTYPE are interchangeable if *packet-type* is given by name. The table below shows several examples.

Table 4.15. /TYPE and /SUBTYPE Qualifier Examples

/TYPE and /SUBTYPE Qualifiers	Meaning
/TYPE = CI	All CI packets regardless of subtype
/TYPE = CI_MSG	All CI packets with subtype CI_MSG
/TYPE = MISC/SUBTYPE = 120	All MISC packets with subtype 120
/TYPE = 0 or /TYPE = UNKNOWN	All packets with an unknown TYPE/SUBTYPE combination

Examples

1.

```

SDA> SHOW POOL
Non-Paged Dynamic Storage Pool
-----
NPOOL address:                81009088
Pool map address:             81562900
Number of lookaside lists:    128
Granularity size:             64
Ring buffer address:          81552200
Most recent ring buffer entry: 815553A0

LSTHDS(s)
-----
RAD      LSTHDS      Variable      Lookaside
address  listhead    listheads
-----
00  FFFFFFFF.81008830  FFFFFFFF.8100883C  FFFFFFFF.81008868
01  FFFFFFFF.7FFFE000  FFFFFFFF.7FFFE00C  FFFFFFFF.7FFFE038
02  FFFFFFFF.7FFFC000  FFFFFFFF.7FFFC00C  FFFFFFFF.7FFFC038
03  FFFFFFFF.7FFFA000  FFFFFFFF.7FFFA00C  FFFFFFFF.7FFFA038

Segment(s)
-----
Start      End      Length  RAD
-----
81548000  8172B9FF 001E3A00 00
81735A00  8173D53F 00007B40 00
81747540  8174BDBF 00004880 00
81755DC0  81AFDFFF 003A8240 00
81APE000  81C43FFF 00146000 01
81C44000  81D89FFF 00146000 02
81D8A000  81ECFFFF 00146000 03
81ED0000  81F1FFFF 00050000 02

Per-RAD Totals
-----
RAD      Length
---
00      00598000
01      00146000
02      00196000
03      00146000

Non-Paged total: 009BA000

Dump of packets allocated from Non-Paged Pool
-----
Packet: MP_CPU                               Start address: 81548000      Length: 000009C0      RAD: 00
00000000 00000000 0000003E 00000001 00000002 026A09C0 AcD1A180 81C52F40 @/A..iN~A.j.....>..... 81548000
81548038 81548038 81548030 81548030 81548028 81548028 00000000 00000001 .....(.T.(.T.O.T.O.T.8.T.8.T. 81548020
81548058 81548058 81548050 81548050 81548048 81548048 81548040 81548040 @.T.@.T.H.T.H.T.P.T.P.T.X.T.X.T. 81548040
.
.
.
Packet: Unknown                               Start address: 815489C0      Length: 00000180      RAD: 00
FFFFFFFF AD332000 00500000 00008020 FFFFFFFF 81548B00 FFFFFFFF 81548A80 ..T.....T.....P.. 3-.... 815489C0
.
.
.
Packet: DDB                                   Start address: 81548B40      Length: 00000300      RAD: 00
AD410000 81564480 81548Bc0 000F4240 00000000 63060300 008B798F 962DA431 1H-.y....c....eB..A.T..DV...A- 81548B40
.
.
.
Summary of Non-Paged Pool contents
-----
Packet type/subtype      Packet count      Packet bytes      Percent
-----
Unknown                  000001E4          00145BC0          (50.7%)
ADP                      00000009          00000A00          (0.1%)
ACB                      0000008D          00002500          (0.4%)
AQB                      00000002          00001080          (0.2%)
.
.
.
LOADCODE                0000003D          00004C40          (0.7%)
LDRIMG                  0000003D          00004C40          (0.7%)
INIT                    00000008          00003B80          (0.6%)
PCBVEC                  00000001          00001BC0          (0.3%)
PHVEC                  00000001          00000700          (0.1%)
MPWMAP                  00000005          00001840          (0.2%)
PRCMAP                  00000001          00000080          (0.0%)
.
.
.
Total space used: 002825C0 (2631104.) bytes out of 009BA000 (10199040.) bytes
in 0000184C (6220.) packets
Total space utilization: 25.8%
.
.
.

```

This example shows the Nonpaged Pool portion of the default SHOW POOL display.

2. SDA> SHOW POOL/TYPE=IPC/HEADER 8156E140:815912C0

Non-Paged Dynamic Storage Pool

Dump of packets allocated from Non-Paged Pool

Packet type/subtype Header contents	Start	Length	RAD		
IPC_TDB 00000040 81591180 ..Y.@...@.{...Y.	8156E140	00000040	00	81591180	057B0040
IPC_LIST 0057A740 8158D100 .ÑX.@\$W.@.{...L.	815838C0	00009840	00	004C0200	087B9840
IPC_LIST 00570F00 8158E940 @éX...W.@.{.....	8158D100	00001840	00	00040400	087B1840
IPC_LIST 0056F6C0 81591180 ..Y.ÀöV.@({.....	8158E940	00002840	00	00140200	087B2840
IPC_TPCB 0056CE80 81591200 ..Y..ÎV...{.....	81591180	00000080	00	00000000	067B0080
IPC 0056CE00 815912C0 À.Y..ÎV.À.{.....	81591200	000000C0	00	00000000	007B00C0

Summary of Non-Paged Pool contents

Packet type/subtype	Packet count	Packet bytes	Percent
IPC (100.0%)	00000006	0000DA40	
IPC (0.3%)	00000001	000000C0	
IPC_TDB (0.1%)	00000001	00000040	
IPC_TPCB (0.2%)	00000001	00000080	
IPC_LIST (99.3%)	00000003	0000D8C0	

Total space used: 0000DA40 (55872.) bytes out of 00023180 (143744.) bytes
in 00000006 (6.) packets

Total space utilization: 38.9%

This example shows how you can specify a pool packet type and a range of addresses.

3. SDA> SHOW POOL/STATISTICS

Non-Paged Pool statistics for RAD 00

```

On-RAD deallocations (all RADs):          1221036
Total deallocations (all RADs):          1347991
Percentage of on-RAD deallocations:      90.6%
    
```

Variable list statistics

```

-----
Number of packets on variable list:      7
Total bytes on variable list:           3613376
Smallest packet on variable list:       256
Largest packet on variable list:        3598016
Bytes allocated from variable list:     2140480
Times pool expanded:                    0
    
```

Lookaside list statistics

```

-----
List      Packets      Packets      Operation
Allocation Allocation
Listhead address  size  (approx)  (actual)  sequence #
attempts  failures  Deallocs
-----
FFFFFFFF.81008870    64      5          5          10057
10549          492     10062
FFFFFFFF.81008878   128     21          21          366
4881          4515    387
FFFFFFFF.81008880   192     33          33         27376
27542          166     27409
FFFFFFFF.81008888   256     4           4          8367
8476          118     8362
.
.
.
    
```

This example shows the Nonpaged Pool portion of the SHOW POOL/STATISTICS display.

4. SDA> SHOW POOL/RING_BUFFER

Pool History Ring-Buffer

```

-----
(2048 entries: Most recent first)
-----
Packet      Size  Type/Subtype      Caller's PC      Operation      IPL CPU      Time
-----
FFFFFFFF.81C65F40  320 SECURITY_PSB      80283A9C NSA_STDSFREE_PSB_C+0024C  DEALLO_POOL_NPP  0  8  009F1E47.549449F0
FFFFFFFF.81C44E00  192 SECURITY_PXB_ARRAY 80283A30 NSA_STDSFREE_PSB_C+001E0  DEALLO_POOL_NPP  0  8  009F1E47.549449F0
FFFFFFFF.81C45A40   64 ACB              8014A09C SCH$INIT? C+00F18      DEALLO_POOL_NPP_SIZ  2  8  009F1E47.549449F0
FFFFFFFF.81C44E00  140 SECURITY_PXB_ARRAY 80283B8C NSA$GET_PSB_C+0005C  ALLO_POOL_NPP      0  8  009F1E47.549449F0
FFFFFFFF.81C65F40  320 SECURITY_PSB      80283B70 NSA$GET_PSB_C+00040  ALLO_POOL_NPP      0  8  009F1E47.549449F0
FFFFFFFF.81C45A40   64 ACB              801281F8 PROCESS_MANAGEMENT_MON+001F  ALLO_POOL_NPP      2  8  009F1E47.549449F0
FFFFFFFF.81C52380   576 IRP              8014A09C SCH$INIT? C+00F18      DEALLO_POOL_NPP_SIZ  2  8  009F1E47.549449F0
FFFFFFFF.81C65F40  320 SECURITY_PSB      80283A9C NSA_STDSFREE_PSB_C+0024C  DEALLO_POOL_NPP      2  8  009F1E47.549449F0
FFFFFFFF.81C44E00  192 SECURITY_PXB_ARRAY 80283A30 NSA_STDSFREE_PSB_C+001E0  DEALLO_POOL_NPP      2  8  009F1E47.549449F0
FFFFFFFF.81C47400   256 BUFIO           800F6270 IOC_STDSWAKACP_C+00650  DEALLO_POOL_NPP_SIZ  2  8  009F1E47.549449F0
.
.
.
    
```

This example shows the output of the SHOW POOL/RING_BUFFER display.

5. SDA> SHOW POOL/PAGED/STATISTICS

Paged Pool statistics

Variable list statistics

```

-----
Number of packets on variable list:          30
Total bytes on variable list:              4778288
Smallest packet on variable list:         16
Largest packet on variable list:         4777440

```

Lookaside list statistics

```

-----
Listhead address      List      Packets      Operation
                      size          sequence #
-----
      ...
FFFFFFFFF.882119D0    80          0             1
      ...

```

This example shows the output of paged pool statistics when the system parameter PAGED_LAL_SIZE has been set to a nonzero value.

4.62. SHOW PORTS

Displays those portions of the port descriptor table (PDT) that are port independent.

Format

```
SHOW PORTS [/qualifier[,...]]
```

Parameters

None.

Qualifiers

/ADDRESS=*pd_t-address*

Displays the specified port descriptor table (PDT). You can find the *pd_t-address* for any active connection on the system in the **PDT summary page** display of the SHOW PORTS command. This command also defines the symbol PE_PDT. The connection descriptor table (CDT) addresses are also stored in many individual data structures related to System Communications Services (SCS) connections, for instance, in the path block displays of the SHOW CLUSTER/SCS command.

/BUS=*bus-address*

Displays bus (LAN device) structure data.

/CHANNEL=*channel-address*

Displays channel (CH) data.

/DEVICE

Displays the network path description for a channel.

/MESSAGE

Displays the message data associated with a virtual circuit (VC).

/NODE=node

Shows only the virtual circuit block associated with the specific node. When you use the */NODE* qualifier, you must also specify the address of the PDT using the */ADDRESS* qualifier.

/VC=vc-address

Displays the virtual circuit data.

Description

The SHOW PORTS command provides port-independent information from the port descriptor table (PDT) for those CI ports with full System Communications Services (SCS) connections. This information is used by all SCS port drivers.

The SHOW PORTS command also defines symbols for PEDRIVER based on the cluster configuration. These symbols include the following information:

- Virtual circuit (VC) control blocks for each of the remote systems
- Bus data structure for each of the local LAN adapters
- Some of the data structures used by both PEDRIVER and the LAN drivers

The following symbols are defined automatically:

- VC_nodename---Example: VC_NODE1, address of the local node's virtual circuit to node NODE1.
- CH_nodename---The preferred channel for the virtual circuit. For example, CH_NODE1, address of the local node's preferred channel to node NODE1.
- BUS_busname---Example: BUS_ETA, address of the local node's bus structure associated with LAN adapter ETA0.
- PE_PDT---Address of PEDRIVER's port descriptor table.
- MGMT_VCRP_busname---Example: MGMT_VCRP_ETA, address of the management VCRP for bus ETA.
- HELLO_VCRP_busname---Example: HELLO_VCRP_ETA, address of the HELLO message VCRP for bus ETA.
- VCIB_busname---Example: VCIB_ETA, address of the VCIB for bus ETA.
- UCB_LAVC_busname---Example: UCB_LAVC_ETA, address of the LAN device's UCB used for the local-area OpenVMS Cluster protocol.
- UCB0_LAVC_busname---Example: UCB0_LAVC_ETA, address of the LAN device's template UCB.
- LDC_LAVC_busname---Example: LDC_LAVC_ETA, address of the LDC structure associated with LAN device ETA.
- LSB_LAVC_busname---Example: LSB_LAVC_ETA, address of the LSB structure associated with LAN device ETA.

These symbols equate to system addresses for the corresponding data structures. You can use these symbols, or an address, in SHOW PORTS qualifiers that require an address, as in the following:

```
SDA> SHOW PORTS/BUS=BUS_ETA
```

The SHOW PORTS command produces several displays. The initial display, the **PDT summary page**, lists the PDT address, port type, device name, and driver name for each PDT. Subsequent displays provide information taken from each PDT listed on the summary page.

You can use the /ADDRESS qualifier to the SHOW PORTS command to produce more detailed information about a specific port. The first display of the SHOW PORTS/ADDRESS command duplicates the last display of the SHOW PORTS command, listing information stored in the port's PDT. Subsequent displays list information about the port blocks and virtual circuits associated with the port.

Examples

1. SDA> SHOW PORTS

```
OpenVMS Cluster data structures
```

```
-----
```

```
--- PDT Summary Page ---
```

PDT Address	Type	Device	Driver Name
80E2A180	pn	PNA0	SYS\$PNDRIVER
80EC3C70	pe	PEA0	SYS\$PEDRIVER

```
--- Port Descriptor Table (PDT) 80E2A180 ---
```

```
Type: 09 pn
```

```
Characteristics: 0000
```

Msg Header Size	104	Flags	0000	Message Sends
3648575				
Max Xfer Bcnt	00100000	Counter CDRP	00000000	Message Recvs
4026887				
Poller Sweep	21	Load Vector	80E2DFCC	Mess Sends NoFP
3020422				
Fork Block W.Q.	80E2A270	Load Class	60	Mess Recvs NoFP
3398732				
UCB Address	80E23380	Connection W.Q.	80E4BF94	Datagram Sends
0				
ADP Address	80E1BF00	Yellow Q.	80E2A2E0	Datagram Recvs
0				
Max VC timeout	16	Red Q.	80E2A2E8	Portlock
80E1ED80				
SCS Version	2	Disabled Q.	80FABB74	Res Bundle Size
208				
		Port Map	00000001	

```
--- Port Descriptor Table (PDT) 80EC3C70 ---
```

```
Type: 03 pe
```

```
Characteristics: 0000
```

Msg Header Size	32	Flags	0000	Message Sends
863497				
Max Xfer Bcnt	FFFFFFFF	Counter CDRP	00000000	Message Recvs
886284				

Poller Sweep 863497	30	Load Vector	80EDBF8C	Mess Sends NoFP
Fork Block W.Q. 886284	80EC3D60	Load Class	10	Mess Recvs NoFP
UCB Address 0	80EC33C0	Connection W.Q.	80EFF5D4	Datagram Sends
ADP Address 0	00000000	Yellow Q.	80EC3DD0	Datagram Recvs
Max VC timeout 00000000	16	Red Q.	80EC3DD8	Portlock
SCS Version 0	2	Disabled Q.	812E72B4	Res Bundle Size
		Port Map	00000000	

This example illustrates the default output of the SHOW PORTS command.

2. SDA> SHOW PORTS/ADDRESS=80EC3C70
OpenVMS Cluster data structures

```
-----
--- Port Descriptor Table (PDT) 80EC3C70 ---

Type: 03 pe
Characteristics: 0000

Msg Header Size      32  Flags          0000  Message Sends
 864796
Max Xfer Bcnt       FFFFFFFF  Counter CDRP  00000000  Message Recvs
 887086
Poller Sweep        30  Load Vector    80EDBF8C  Mess Sends NoFP
 864796
Fork Block W.Q.     80EC3D60  Load Class     10  Mess Recvs NoFP
 887086
UCB Address         80EC33C0  Connection W.Q. 80EFF5D4  Datagram Sends
 0
ADP Address         00000000  Yellow Q.      80EC3DD0  Datagram Recvs
 0
Max VC timeout      16  Red Q.        80EC3DD8  Portlock
 00000000
SCS Version         2  Disabled Q.   812E72B4  Res Bundle Size
 0
                    Port Map      00000000
                    Port Map      00000000

--- Port Block 80EC4540 ---

Status: 0001 authorize
VC Count: 20
Secs Since Last Zeroed: 77020

SBUF Size          824  LBUF Size      5042  Fork Count
 1943885
SBUF Count         28  LBUF Count     1  Refork Count
 0
SBUF Max           768  LBUF Max      384  Last Refork
 00000000
SBUF Quo           28  LBUF Quo      1  SCS Messages
 1154378
```

SBUF Miss 361349	1871	LBUF Miss	3408	VC Queue Cnt
SBUF Allocs 770201	1676801	LBUF Allocs	28596	TQE Received
SBUFs In Use 770201	2	LBUFs In Use	0	Timer Done
Peak SBUF In Use 30288	101	Peak LBUF In Use	10	RWAITQ Count
SBUF Queue Empty 32868	0	LBUF Queue Empty	0	LDL Buf/Msg
TR SBUF Queue Empty 1000000	0	Ticks/Second	10	ACK Delay
No SBUF for ACK 30	0	Listen Timeout	8	Hello Interval

Bus Addr	Bus	LAN Address	Error Count	Last Error	Time of Last Error
80EC4C00	LCL	00-00-00-00-00-00	0		
80EC5400	EXA	08-00-2B-17-CF-92	0		
80EC5F40	FXA	08-00-2B-29-E1-40	0		

--- Virtual Circuit (VC) Summary ---

VC Addr Time	Node	SCS ID	Lcl ID	Status Summary	Last Event
80E566C0 16:01:57.58	ARUSHA	19617	223/DF	open,path	8-FEB-2001
80E98840 16:01:58.41	ETOSHA	19699	222/DE	open,path	8-FEB-2001
80E98A80 16:01:58.11	VMS	19578	221/DD	open,path	8-FEB-2001
.					
.					
.					

This example illustrates the output produced by the SHOW PORTS command for the PDT at address 80EC3C70.

4.63. SHOW PROCESS

Displays the software and hardware context of any process in the system. If the process is suspended (ANALYZE/SYSTEM), then some displays may be incomplete or unavailable. If the process was outswapped at the time of the system crash, or not included in a selective dump (ANALYZE/CRASH_DUMP), then some displays may be incomplete or unavailable. Please see descriptions of the individual qualifiers for details not included in the syntax definition.

Format

SHOW PROCESS

SHOW PROCESS

Select which process to show:

```
[ process -name
  ALL
  /ADDRESS= pcb_address
  /ID=nn
  /INDEX=nn
  /NEXT
  /SYSTEM
```

WM-1217A-A1

Select what to show about a process (see next page):

```
/ALL
/BUFFER_OBJECTS
/CHANNELS [/FID_ONLY]
/FANDLES
/IMAGES [= { name } ]
/LOCKS [/BRIEF]

{ /PAGE_TABLES } ♦ [ =ALL
  range
  [/PTE_ADDRESS]
  [ [/PO (D)] [/P1] [/P2] [/PT] ]
  /GSTX=index
  /SECTION_INDEX=n
  { /RDE [=id]
    { /REGIONS [=id] } ♦ ] ] [ /INVALID_PFN [=option]
  [ /NONMEMORY_PFN [=option] ]
  [ /L1
  [ /L2
  [ /L3 (D) ] ] ] ]

/PCB (D)
/PERSONA [=address] [/RIGHTS[/AUTHORIZED]]
/PHD

/POOL [ = { { PO
  P1
  IMGACT } }
  range
  ALL (D) ] [ /BRIEF
  /CHECK
  { /FREE
  { /UNUSED } }
  /HEADER
  /MAXIMUM_BYTES [=n]
  /RING_BUFFER[=ALL [address]]
  /STATISTICS
  { /SUBTYPE=packet-type }
  { /TYPE=packet-type } ]
  /SUMMARY

{ /PROCESS_SECTION_TABLE } ♦ [ /FID_ONLY
  /PST ] [ /SECTION_INDEX=n ]

{ /RDE [=id]
  { /REGIONS [=id] } ♦ ]

/REGISTERS
/RMS [=option [, . . .]]
/SEMAPHORE
/THREADS
/TQE [=ALL]
/UNWIND_TABLE [= { name } ]
  ALL ]

{ /WORKING_SET_LIST [=option] } ♦
  /WSL [=option] ]
```

♦ indicates that stacked entries in braces are functionally equivalent.

Parameters

ALL

Information is to be displayed about all processes that exist in the system.

process-name

Name of the process for which information is to be displayed. Use of the **process-name** parameter or one of the /ADDRESS, /ID, /INDEX, /NEXT, or /SYSTEM qualifiers causes the SHOW PROCESS command to perform an implicit SET PROCESS command, making the indicated process the current process for subsequent SDA commands.

When you analyze a crash dump from a multiprocessing system, changing process context may require a switch of CPU context as well. When you issue a SET PROCESS command, SDA automatically changes its CPU context to that of the CPU on which that process is, or was most recently, current. You can determine the names of the processes in the system by issuing a SHOW SUMMARY command.

The **process-name** can contain up to 15 uppercase letters, numerals, the underscore (_), dollar sign (:), and some other printable characters. If it contains any other characters (including lowercase letters), you may need to enclose the **process-name** in quotation marks (" ").

Qualifiers

/ADDRESS=pcb-address

Specifies the process control block (PCB) address of a process in order to display information about the process.

/ALL

Displays all information shown by the following qualifiers:

/BUFFER_OBJECTS

/CHANNELS

/FANDLES

/IMAGES=ALL

/LOCKS

/PAGE_TABLES=ALL

/PCB

/PERSONA/RIGHTS

/PHD

/POOL/HEADER/RING_BUFFER/STATISTICS

/PROCESS_SECTION_TABLE

/REGIONS

/REGISTERS

/RMS

/SEMAPHORE

/THREADS

/TQE

/UNWIND_TABLE (Integrity servers only.)

/WORKING_SET_LIST

/AUTHORIZED

Used with the ***/PERSONA/RIGHTS*** qualifiers. See the ***/PERSONA/RIGHTS/AUTHORIZED*** description for the use of the ***/AUTHORIZED*** qualifier.

/BRIEF

When used with the **/LOCKS** qualifier, causes SDA to display each lock owned by the current process in brief format, that is, one line for each lock. When used with the **/POOL** qualifier, causes SDA to display only general information about process pool and its addresses.

/BUFFER_OBJECTS

Displays all the buffer objects that a process has created.

/CHANNELS

Displays information about the I/O channels assigned to the process.

/CHECK

Checks all free process pool packets for POOLCHECK-style corruption in exactly the same way that the system does when generating a POOLCHECK crash dump.

/FHANDLES

Displays the data on the process' fast I/O handles.

/FID_ONLY

When used with **/CHANNEL** or **/PROCESS_SECTION_TABLE (/PST)**, causes SDA to not attempt to translate the FID (File ID) to a file name when invoked with **ANALYZE/SYSTEM**.

/FREE

When used with **/POOL**, displays the entire contents, both allocated and free, of the specified region or regions of pool. Use the **/FREE** qualifier with a range to show all of the used and free pool in the given range.

/GSTX=*index*

When used with the **/PAGE_TABLES** qualifier, displays only page table entries for the specific global section.

/HEADER

When used with **/POOL**, displays only the first 16 bytes of each data packet found within the specified region or regions of pool.

/IMAGES [= {*name*|ALL}]

For all images in use by this process, displays the address of the image control block, the start and end addresses of the image, the activation code, the protected and shareable flags, the image name, and the major and minor IDs of the image. The **/IMAGES=ALL** qualifier also displays the base, end, image offset, section type, and global pointer for all images (Integrity servers) or for all installed resident images (Alpha) in use by this process. The **/IMAGE=*name*** qualifier displays this information for just the specified images; *name* may contain wildcards.

See the *VSI OpenVMS Linker Utility Manual* and the Install utility chapter in the *VSI OpenVMS System Management Utilities Reference Manual* for more information on images installed using the **/RESIDENT** qualifier.

/ID=*nn*

/INDEX=*nn*

Specifies the process for which information is to be displayed by its index into the system's list of software process control blocks (PCBs), or by its process identification (ID). /ID and /INDEX can be used interchangeably. You can supply the following values for *nn*:

- The process index itself.
- The process identification (PID) or extended PID longword, from which SDA extracts the correct index. You can specify the PID or extended PID of any thread of a process with multiple kernel threads. Any thread-specific data displayed by SHOW PROCESS will be for the given thread.

To obtain these values for any given process, issue the SDA command SHOW SUMMARY/THREADS.

/INVALID_PFN [=option]

The /INVALID_PFN qualifier, which is valid only on platforms that supply an I/O memory map, causes SDA to display only page table entries that map to PFNs that are not in the system's private memory or in Galaxy-shared memory, and which are not I/O access pages. Use of /INVALID_PFN implies /PAGE_TABLES.

The /INVALID_PFN qualifier allows two optional keywords, READONLY and WRITABLE. If neither keyword is given, all relevant pages are displayed. If you specify READONLY, only pages marked for no write access are displayed. If you specify WRITABLE, only pages that allow write access are displayed. For example, SHOW PROCESS ALL/PAGE_TABLE=ALL/INVALID_PFN=WRITABLE would display all process pages (for all processes) whose protection allows write, but which map to PFNs that do not belong to this system.

/L1**/L2****/L3 (D)**

Used with the /PAGE_TABLES qualifier to specify the level for which page table entries are to be displayed. You can specify only one level. /L3 is the default.

/LOCKS [/BRIEF]

Displays the lock management locks owned by the current process.

When specified with /BRIEF, produces a display similar in format to that produced by the SHOW LOCKS command; that is, it causes SDA to display each lock owned by the current process in brief format with one line for each lock. Table 4.3 contains additional information.

/MAXIMUM_BYTES [=n]

When used with /POOL, displays only the first *n* bytes of a pool packet; if you specify /MAXIMUM_BYTES without a value, the default is 64 bytes.

/NEXT

Locates the next valid process in the system's process list and selects that process. If there are no further valid processes in the system's process list, SDA returns an error.

/NONMEMORY_PFN [=option]

The /NONMEMORY_PFN qualifier causes SDA to display only page table entries that are in neither the system's private memory nor in Galaxy-shared memory. Use of /NONMEMORY_PFN implies /PAGE_TABLES.

The /NONMEMORY_PFN qualifier allows two optional keywords, READONLY and WRITABLE. If neither keyword is given, all relevant pages are displayed. If you specify READONLY, only pages marked for no write access are displayed. If you specify WRITABLE, only pages that allow write access are displayed. For example, SHOW PROCESS ALL/PAGE_TABLE=ALL/NONMEMORY_PFN=WRITABLE would display all process pages (for all processes) whose protection allows write, but which map to PFNs that are in neither the system's private memory nor Galaxy-shared memory.

/P0 (D)**/P1****/P2****/PT**

When used with the /PAGE_TABLES qualifier, /P0, /P1, /P2, and /PT specify one or more regions for which page table entries should be displayed. You can specify any or none of these values. The default is /P0.

/PAGE_TABLES

Displays the page tables of the process P0 (process), P1 (control), P2, or PT (page table) region, or, optionally, page table entries for a **range** of addresses. You can use /PAGE_TABLES=ALL to display page tables of all four regions. With /L*n*, the page table entries at the level specified by /L1, /L2, or /L3 (the default) are displayed.

With /RDE=*id* or /REGIONS=*id*, SDA displays the page tables for the address range of the specified address region. When you do not specify an ID, the page tables are displayed for all the process-permanent and user-defined regions.

If /PTE_ADDRESS is given, the range is expressed using the following syntax:

<i>m</i>	Displays the single page table entry at address <i>m</i>
<i>m:n</i>	Displays the page table entries from address <i>m</i> to address <i>n</i>
<i>m;n</i>	Displays <i>n</i> bytes of page table entries starting at address <i>m</i>

If /PTE_ADDRESS is not given, then range is expressed using the following syntax:

<i>m</i>	Displays the single page table entry that corresponds to virtual address <i>m</i>
<i>m:n</i>	Displays the page table entries that correspond to the range of virtual addresses from <i>m</i> to <i>n</i>
<i>m;n</i>	Displays the page table entries that correspond to a range of <i>n</i> bytes starting at virtual address <i>m</i>

See Section 2.8 for information on page protections and access.

The `/GSTX=index` qualifier causes SDA to display only the page table entries for the pages in the specified global section.

The `/SECTION_INDEX=n` qualifier causes SDA to display only the page table entries for the pages in the specified process section.

/PCB

Displays the information contained in the process control block (PCB). This is the default behavior of the SHOW PROCESS command.

/PERSONA [=*address*]

Displays all persona security blocks (PSBs) held in the PERSONA ARRAY of the process, and then lists selected information contained in each initially listed PSB. The selected information includes the contents of the following cells inside the PSB:

Flags

Reference count

Execution mode

Audit status

Account name

UIC

Privileges

Rights enabled mask

If you specify a PSB address, this information is provided for that specific PSB only.

If you also specify `/RIGHTS`, SDA expands the display to provide additional selected information, including all the rights and their attributes currently held and active for each persona security block (PSB) specified with the `/PERSONA` qualifier.

If you specify `/RIGHTS/AUTHORIZED`, SDA also displays additional selected information, including all the rights and their attributes authorized for each persona security block (PSB) specified with the `/PERSONA` qualifier.

/PHD

Lists the information included in the process header (PHD).

/POOL [= {P0 | P1 | IMGACT | ALL (D)} | *range*]

Displays the dynamic storage pool in the process' P0 (process) region, the P1 (control) region, or the image activator's reserved pages, or optionally, a range of addresses. The default action is to display all dynamic storage pools.

You can express a **range** using the following syntax:

<i>m:n</i>	Displays the process pool in the range of virtual addresses from <i>m</i> to <i>n</i> .
------------	---

<i>m;n</i>	Displays process pool in a range of <i>n</i> bytes, starting at virtual address <i>m</i> .
------------	--

/PPT

See the description of /PAGE_TABLES, which is functionally equivalent to /PPT.

/PROCESS_SECTION_TABLE [/SECTION_INDEX=*id*]/[FID_ONLY]

Lists the information contained in the process section table (PST). The /SECTION_INDEX=*id* qualifier used with /PROCESS_SECTION_TABLE displays the process section table entry for the specified section.

/PST

Is a synonym for /PROCESS_SECTION_TABLE.

/PT

When used with the /PAGE_TABLES qualifier, displays the page table entries for the page table space of the process. By default, P0 space is displayed.

/PTE_ADDRESS

When used with the /PAGE_TABLES qualifier, specifies that the range is of PTE addresses instead of the virtual addresses mapped by the PTE.

/RDE [=*id*]**/REGIONS [=*id*]**

Lists the information contained in the process region table for the specified region. If you do not specify a region, the entire table is displayed, including the process-permanent regions. /RDE and /REGIONS are functionally equivalent. When used with /PAGE_TABLES, this qualifier causes SDA to display the page tables for only the specified region or, by default, for all regions.

/REGISTERS

Lists the hardware context of the process, as reflected in the process registers stored in the hardware privileged context block (HWPCB), in its kernel stack, and possibly, in its PHD.

/RIGHTS

Used with the /PERSONA qualifier. See the /PERSONA/RIGHTS description for use of the /RIGHTS qualifier.

/RING_BUFFER [= {ALL | *address*}]

Displays the contents of the process-pool history ring buffer. Entries are displayed in reverse chronological order (most recent to least recent). If you specify /RING_BUFFER without the ALL keyword or an address, SDA displays all unmatched current allocations and deallocations. Use /RING_BUFFER=ALL to display matched allocations and deallocations and any non-current entries not yet overwritten. Use /RING_BUFFER=*address* to limit the display to only allocations and deallocations of blocks that contain the given address (including matched allocations and deallocations).

/RMS [= (*option*[,...])]

Displays certain specified RMS data structures for each image I/O or process-permanent I/O file the process has open. To display RMS data structures for process-permanent files, specify the PIO option to this qualifier. Other guidelines for specifying this qualifier include the following:

- If you specify only one option, you can omit the parentheses.
- You can add additional structures to those already set by the SET RMS command by beginning the list of options with an asterisk (*).
- You can exclude a structure from those set by the SET RMS command by specifying its keyword option preceded by NO (for example, NOPIO).

SDA determines the structures to be displayed according to either of the following methods:

- If you provide the name of a structure or structures in the **option** parameter, SHOW PROCESS/RMS displays information from only the specified structures. (See Table 4.2 in the SET RMS command description for a list of keywords that you can supply as options.)
- If you do not specify an **option**, SHOW PROCESS/RMS displays the current list of options as shown by the SHOW RMS command and set by the SET RMS command.

/SECTION_INDEX=*n*

When used with the /PAGE_TABLES qualifier, displays the page table for the range of pages in the specified process section. You can also specify one of the qualifiers /L1, /L2, or /L3.

When used with the /PROCESS_SECTION_TABLE qualifier, displays the PST for the specified process section.

The /SECTION_INDEX=*n* qualifier is ignored if you do not specify either the /PAGE_TABLES or the /PROCESS_SECTION_TABLE qualifier.

/SEMAPHORE

Displays the Inner Mode Semaphore for a multithreaded process.

/STATISTICS

When used with /POOL, displays statistics on the free list(s) in process pool.

/SUBTYPE=*packet-type*

When used with /POOL, displays only packets of the specified subtype. Pool packet types found in the process pool can include logical names (LNM) and image control blocks (IMCB). /SUBTYPE is functionally equivalent to /TYPE.

/SUMMARY

When used with /POOL, displays only an allocation summary for each packet type.

/SYSTEM

Displays the system's process control block. The system PCB and process header (PHD) parallel the data structures that describe processes. They contain the system working set, global section table, global page table, and other systemwide data.

/THREADS

Displays the software and hardware context of all the threads associated with the current process.

/TQE [=ALL]

Displays all timer queue entries associated with the current process. If specified as /TQE, a one-line summary is output for each TQE. If specified as /TQE=ALL, a detailed display of each TQE is output. See Table 4-32 for an explanation of TQE types in the one-line summary.

/TYPE=*packet-type*

When used with /POOL, displays only packets of the specified type. Pool packet types found in the process pool can include logical names (LNM) and image control blocks (IMCB). /TYPE is functionally equivalent to /SUBTYPE.

/UNUSED

When used with /POOL, displays only free packets.

/UNWIND_TABLE [= {ALL | *name* }]

Valid for Intergrity server systems only.

If specified without a keyword, displays the master unwind table for the process. SHOW PROCESS/UNWIND=ALL displays the details of every process unwind descriptor. SHOW PROCESS/UNWIND=*name* displays the details of every unwind descriptor for the named image or images implied by a wildcard. To look at unwind data for a specific PC in process space, use SHOW UNWIND *address*.

If some or all unwind data for an image is not included in the system dump (for example, if it was not in the working set of the process at the time of the system crash), a SHOW PROCESS/UNWIND command can fail with a %SDA-W-NOREAD error because the unwind data is inaccessible. Collecting unwind data using the SDA commands COLLECT and COPY/COLLECT will not correct this because the collected unwind data is used only by SHOW UNWIND *address* and SHOW CALL.

/WORKING_SET_LIST [= {PPT|PROCESS|LOCKED|GLOBAL|MODIFIED|*n* }]

Displays the contents of the requested entries of the working set list for the process. If you do not specify an option, all working set list entries are displayed. This qualifier is functionally equivalent to /WSL.

The table shows the options available with SHOW PROCESS/WORKING_SET_LIST.

Table 4.16. Options for the /WORKING_SET_LIST Qualifier

Options	Results
PPT	Displays process page table pages
PROCESS	Displays process-private pages
LOCKED	Displays pages locked into the process' working set
GLOBAL	Displays global pages currently in the working set of the process

Options	Results
MODIFIED	Displays working set list entries marked modified
<i>n</i>	Displays a specific working set list entry, where <i>n</i> is the working set list index (WSLX) of the entry of interest

/WSL

See /WORKING_SET_LIST, which is functionally equivalent to /WSL.

Description

The SHOW PROCESS command displays information about the process specified by **process-name**, the process specified in the /ID or /INDEX qualifier, the next process in the system's process list, the system process, or all processes. The SHOW PROCESS command performs an implicit SET PROCESS command under certain uses of its qualifiers and parameters, as noted previously. By default, the SHOW PROCESS command produces information about the SDA current process, as defined in Section 2.5.

The default of the SHOW PROCESS command provides information taken from the software process control block (PCB) and the kernel threads block (KTB) of the SDA current thread. This is the first display provided by the /ALL qualifier and the only display provided by the /PCB qualifier. This information describes the following characteristics of the process:

- Software context
- Condition-handling information
- Information on interprocess communication
- Information on counts, quotas, and resource usage

Among the displayed information are the process PID, EPID, priority, job information block (JIB) address, and process header (PHD) address. SHOW PROCESS also describes the resources owned by the process, such as event flags and mutexes. The "State" field records the current scheduling state for the thread, and indicates the CPU ID of any thread whose state is CUR. See Table 4.26 for a list of all possible states.

The /THREADS qualifier (also part of SHOW PROCESS/ALL), displays information from the KTBs of all threads in the process, instead of only the SDA current thread.

The SHOW PROCESS/ALL command displays additional process-specific information, also provided by several of the individual qualifiers to the command.

The **process registers** display, also produced by the /REGISTERS qualifier, describes the process hardware context, as reflected in its registers. The registers displayed are those of the SDA current thread, or of all threads if either the /THREADS or the /ALL qualifier have been specified.

A process hardware context is stored in the following locations:

- If the process is currently executing on a processor in the system (that is, in the CUR scheduling state), its hardware context is contained in that processor's registers. (That is, the process registers and the processor's registers contain identical values, as illustrated by a SHOW CPU command for that processor or a SHOW CRASH command, if the process was current at the time of the system failure.)

- If the process is not executing, its privileged hardware context is stored in the part of the PHD known as the HWPCB. Its integer register context is stored on its kernel stack. Its floating-point registers are stored in its PHD.

The **process registers** display first lists those registers stored in the HWPCB, kernel stack, and PHD ("Saved process registers"). If the process to be displayed is currently executing on a processor in the system, the display then lists the processor's registers ("Active registers for the current process"). In each section, the display lists the registers in groups.

For Alpha:

- Integer registers (R0 through R29)
- Special-purpose registers (PC and PS)
- Stack pointers (KSP, ESP, SSP, and USP)
- Page table base register (PTBR)
- AST enable and summary registers (ASTEN and ASTSR)
- Address space number register (ASN)

For Integrity servers:

- Integer registers (R1 through R11, R13 through R31). Note that R1 is displayed as GP (Global Pointer) and R12 is omitted.
- Special-purpose registers (PC, PSR, ISR). Note: The PC is the combination of the IP and the slot number from the PSR.
- Stack pointers (KSP, ESP, SSP, and USP)
- Register stack pointers (KBSP, EBSP, SBSP, and UBSP)
- Page table base register (PTBR0)
- AST enable and summary registers (ASTEN and ASTSR)
- Address space number registers (ASN0)
- Floating point registers (F2 through F31, possibly F32 through F127)

The **semaphore** display, also produced by the /SEMAPHORE qualifier, provides information on the inner-mode semaphore used to synchronize kernel threads. The PC history log, recorded if the system parameter SYSTEM_CHECK is enabled, is also displayed.

The **process header** display, also produced by the /PHD qualifier, provides information taken from the PHD, which is swapped into memory when the process becomes part of the balance set. Each item listed in the display reflects a quantity, count, or limit for the process use of the following resources:

- Process memory
- The pager
- The scheduler
- Asynchronous system traps
- I/O activity

- CPU activity

The **working set information** and **working set list** displays, also produced by the /WORKING_SET_LIST qualifier, describe those virtual pages that the process can access without a page fault. After a brief description of the size, scope, and characteristics of the working set list itself, SDA displays information for each entry in the working set list as shown in the table below.

Table 4.17. Working Set List Entry Information in the SHOW PROCESS Display

Column	Contents
INDEX	Index into the working set list at which information for this entry can be found
ADDRESS	Virtual address of the page that this entry describes
STATUS	Four columns that list the following status information: <ul style="list-style-type: none"> • Page status of VALID • Type of physical page (See Table 4.8) • Indication of whether the page has been modified • Indication of whether the page is locked into the working set

When SDA locates either one or more unused working set entries, or entries that do not match the specified option, it issues the following message:

```
---- n entries not displayed
```

The **process section table information** and **process section table** displays, also produced by the /PROCESS_SECTION_TABLE or /PST qualifier, list each entry in the process section table (PST) and display the offsets to, and the indexes of, the first free entry and last used entry.

SDA displays the information listed in the table below for each PST entry.

Table 4.18. Process Section Table Entry Information in the SHOW PROCESS Display

Part	Definition
INDEX	Index number of the entry. Entries in the process section table begin at the highest location in the table, and the table expands toward lower addresses.
ADDRESS	Address of the process section table entry.
SECTION ADDRESS	Virtual address that marks the beginning of the first page of the section described by this entry.
CCB	Address of the channel control block on which the section file is open.
PAGELETS	Length of the process section. This is in units of pagelets, except for a PFN-mapped section in which the units are pages.

Part	Definition
VBN	Virtual block number. The number of the file's virtual block that is mapped into the section's first page.
WINDOW	Address of the window control block on which the section file is open.
REFCNT	Number of pages of this section that are currently mapped.
FLINK	Forward link. The pointer to the next entry in the PST list.
BLINK	Backward link. The pointer to the previous entry in the PST list.
FLAGS	Flags that describe the access that processes have to the process section.

In addition, for each process section that has an associated file, the device and/or file name is displayed. For details of this display, see Table 4.20.

The **regions** display, also produced by either of the `/RDE` or `/REGIONS` qualifiers, shows the contents of the region descriptors. This includes the three default regions (P0, P1, P2), plus any others created by the process. A single region will be displayed if you specify its identifier. The information displayed for each region includes the RDE address, the address range of the region, its identifiers and protection, and links to other RDEs.

If you use the `/PAGE_TABLE` or `/PPT` qualifier with `/RDE` or `/REGION`, the page table for the region is also displayed, as described below.

The **P0 page table**, **P1 page table**, **P2 page table**, and **PT page table** displays, also produced by the `/PAGE_TABLES` qualifier, display listings of the process page table entries in the same format as that produced by the `SHOW PAGE_TABLE` command (see Tables Table 4.4 through Table 4.9).

The **RMS** display, also produced by the `/RMS` qualifier, provides information on the RMS internal data structures for all RMS-accessed open files. The data structures displayed depend on the current setting of RMS options, as described under the `SET RMS` command and Table 4.2.

The **locks** display, also produced by the `/LOCKS` qualifier, provides information on the locks held by the process. For a full description of the information displayed for process locks, see the `SHOW LOCKS` command and Table 4.3. You can also specify the `/BRIEF` qualifier, which provides single-line summary of each process lock; however, no other qualifiers from `SHOW LOCKS` apply to `SHOW PROCESS/LOCKS`.

The **process active channels** display, also produced by the `/CHANNEL` qualifier, displays the information in Table 4.19 for each I/O channel assigned to the process.

Table 4.19. Process Active Channels in the SHOW PROCESS Display

Column	Contents
Channel	Number of the channel.
CCB	The address of the channel control block (CCB).
Window	Address of the window control block (WCB) for the file if the device is a file-oriented device; zero otherwise.

Column	Contents
Status	Status of the device: "Busy" if the device has an I/O operation outstanding; "Dpnd" if the device is deaccess pending; blank otherwise.
Device/file accessed	Name of the device and, if applicable, name of the file being accessed on that device.

The information listed under the heading "Device/file accessed" varies from channel to channel and from process to process. SDA displays certain information according to the conditions listed in the table below.

Table 4.20. Process I/O Channel Information in the SHOW PROCESS Display

Information Displayed1	Type of Channel
<i>dcuu:</i>	SDA displays this information for devices that are not file structured, such as terminals, and for processes that do not open files in the normal way.
<i>dcuu: filespec</i>	SDA displays this information only if you are examining a running system, and only if your process has enough privilege to translate the <i>file-id</i> into the <i>filespec</i> , or if you are examining a dump for which file identification data 2 has been collected.
<i>dcuu:(file-id)</i>	The <i>file-id</i> no longer points to a valid <i>filespec</i> , as when you look at a dump that does not have file identification data 2; or the process in which you are running SDA does not have enough privilege to translate the <i>file-id</i> into the corresponding <i>filespec</i> .
(section file)	The file in question is mapped into the process' memory.

The **images** display, also produced by the /IMAGES qualifier, describes the activated images in the process. SDA displays the information listed in the table below for each image, plus a summary line giving the total image and total page counts.

Table 4.21. Image Information in the SHOW PROCESS Display

Item	Description
Image Name	The name of the image.
Link Time	The date and time the image was linked. These items are only displayed with SHOW PROCESS/IMAGE=ALL or SHOW PROCESS/ALL.
Section Type	For shareable images, the data for each image section is displayed on a separate line. For privileged shareable images, data for the change mode vector is also displayed on a separate line. These items are only displayed with SHOW PROCESS/IMAGE=ALL or SHOW PROCESS/ALL.

Item	Description
Start	Start address of the image in process memory. For resident shareable images, this is the start address of the process-space portion of the image. Alpha only.
End	End address of the image in process memory. For resident shareable images, this is the end address of the process-space portion of the image. Alpha only.
Type	The image type and/or activation method, plus "PROT" for protected images and "SHR" for shareable images.
File ID	The File ID for the image file. No attempt is made to translate this to a filename. These items are only displayed with SHOW PROCESS/IMAGE=ALL or SHOW PROCESS/ALL.
IMCB	The address of the Image Management Control Block.
GP	The Global Pointer for the image. Integrity servers only.
Sym Vect	The address of the image's symbol vector, if any. These items are only displayed with SHOW PROCESS/IMAGE=ALL or SHOW PROCESS/ALL.
Maj, Minor ID	The major and minor revision IDs for the image. These items are only displayed with SHOW PROCESS/IMAGE=ALL or SHOW PROCESS/ALL. Alpha only.
Maj, Min ID, Match	The major and minor revision IDs for the image, plus the match control bits. These items are only displayed with SHOW PROCESS/IMAGE=ALL or SHOW PROCESS/ALL. Integrity servers only.
Base	For Alpha shareable images and all Integrity server images, the base address of each image section and/or the change mode vector. These items are only displayed with SHOW PROCESS/IMAGE=ALL or SHOW PROCESS/ALL.
End	For Alpha shareable images and all Integrity server images, the end address of each image section and/or the change mode vector. These items are only displayed with SHOW PROCESS/IMAGE=ALL or SHOW PROCESS/ALL.
ImageOff	For Alpha shareable images and all Integrity server images, the virtual offset within the image file for each image section. These items are only displayed with SHOW PROCESS/IMAGE=ALL or SHOW PROCESS/ALL.

The **buffer objects** display, also produced by the `/BUFFER_OBJECTS` qualifier, describes the buffer objects in use by the process. Information displayed by SDA for each buffer object includes its address, access mode, size, flags, plus the base virtual address of the object in process space and system space.

The **fast I/O handles** display, also produced by the `/FANDLES` qualifier, describes the fast I/O handles used by the process. Information displayed by SDA includes the address and size of the fast I/O handle vector header, then the address, corresponding IRP, state, and buffer object handles for each fast I/O handle, plus information on free vector entries.

The **persona** display, also produced by the `/PERSONA` qualifier, describes the Persona status block data structures. The default output of `/PERSONA` consists of summary information for all personae in use by the process (the PSB address, flags, user name) and information for each persona (privilege masks, UIC, and so on). When you specify `/PERSONA/RIGHTS` (as in `SHOW PROCESS/ALL`), all the rights currently held and active for each persona are also displayed. When you specify `/PERSONA/RIGHTS/AUTHORIZED`, all the rights authorized for each persona are displayed instead.

The **pool** display, also produced by the `/POOL` qualifier, describes the P0, P1 and IMGACT process pools. The default output of `/POOL` is the entire contents of each used block of pool. When you specify `/POOL/HEADER` (as in `SHOW PROCESS/ALL`), only the first 16 bytes of each used pool block is displayed. By default, all process pools are displayed. You can limit this using `/POOL=P0`, `/POOL=P1` or `/POOL=IMGACT`. See the description of the `SHOW POOL` command for explanations of other qualifiers.

The **Timer Queue Entry (TQE)** display, also produced by the `/TQE` qualifier, describes all timer queue entries that affect the process. The default display (as in `SHOW PROCESS/ALL`) is a one-line summary of each TQE. If you specify `/TQE=ALL`, a detailed display of each TQE is given. No other qualifiers from the `SHOW TQE` command apply to `SHOW PROCESS/TQE`.

Examples

```
SDA> SHOW PROCESS
Process index: 0028   Name: SYSTEM   Extended PID: 000000E8
-----
Process status:      02040001   RES, PHDRES, INTER
      status2:      00000000

PCB address          81444A40   JIB address          81443600
PHD address          821AA000   Swapfile disk address 00000000
KTB vector address  81444D2C   HWPCB address        821AA080
Callback vector address 00000000   Termination mailbox    0000
Master internal PID  00030028   Subprocess count       0
Creator extended PID 00000000   Creator internal PID   00000000
Previous CPU Id      00000000   Current CPU Id         00000000
Previous ASNSEQ      0000000000000003   Previous ASN           0000000000000017
Initial process priority 4   # open files remaining 100/100
Delete pending count 0   Direct I/O count/limit 150/150
UIC                  [00001,000004]   Buffered I/O count/limit 149/150
Abs time of last event 01F1A51D   BUFIO byte count/limit
99424/99808
# of threads         1   ASTs remaining        248/250
Swapped copy of LEFC0 00000000   Timer entries remaining 20/20
Swapped copy of LEFC1 00000000   Active page table count 0
Global cluster 2 pointer 00000000   Process WS page count  43
Global cluster 3 pointer 00000000   Global WS page count   28

Thread index: 0000
```

```

-----
Current capabilities:   System: 0000000C  QUORUM, RUN
                       User:   00000000
Permanent capabilities: System: 0000000C  QUORUM, RUN
                       User:   00000000
Current affinities:   00000000
Permanent affinities: 00000000
Thread status:        02040001
                       status2: 00000000

KTB address           81444A40      HWPCB address         821AA080
PKTA address          7FFEFF98      Callback vector address 00000000
Internal PID          00030028      Callback error         00000000
Extended PID          000000E8      Current CPU id         00000000
State                 LEF           Flags                  00000000
Base priority         4             Current priority       5
Waiting EF cluster    0             Event flag wait mask   DFFFFFFF
CPU since last quantum FFF8       Mutex count            0
ASTs active           NONE

```

The SHOW PROCESS command displays information taken from the software PCB of SYSTEM, the SDA current process. According to the State field in the display, process SYSTEM is in Local Event Flag Wait.

```
SDA> SHOW PROCESS/BUFFER_OBJECTS/FANDLES
```

```
Process index: 0022   Name: NODEA_RT1:   Extended PID: 00000062
```

Process Buffer Objects

ADDRESS	ACMODE	SEQUENCE	REFCNT	PID	PAGCNT	BASE PVA
BASE SVA						
8151AE00	User	00000011	00000031	00010022	00000001	00000000.00084000
FFFFFFFF		.7DE68000	S2_WINDOW			
814A6CC0	User	00000012	00000009	00010022	00000001	00000000.80000000
FFFFFFFF		.7DE66000	S2_WINDOW			
814FBA00	User	00000013	00000009	00010022	00000001	00000000.80000000
FFFFFFFF		.FFFFFFFF	NOSVA			
81512200	User	00000014	00000009	00010022	00000001	00000000.80028000
FFFFFFFF		.7DE64000	S2_WINDOW			
8151A8C0	User	00000015	00000009	00010022	00000001	00000000.80028000
FFFFFFFF		.FFFFFFFF	NOSVA			
81438580	User	00000016	00000009	00010022	00000001	FFFFFFE8.FF800000
FFFFFFFF		.7DE62000	S2_WINDOW			
81464480	User	00000017	00000009	00010022	00000001	FFFFFFE8.FF800000
FFFFFFFF		.FFFFFFFF	NOSVA			
81416F00	Kernel	00000018	00000001	00010022	00000001	00000000.7FF76000
FFFFFFFF		.8120C000	NOQUOTA			

Fandle Vector Header

```

-----
Address      Maxfix      Real_Size  CCB buffer handle
-----
7FF68290    00000043   00000880  00000018.81416F00

```

Fandles

```

Address      IRP          fastio_done  Orgfun      Data bo handle      IOSA bo handle
-----
DBYLEN
-----
7FF682B0    815CEF40     set          00020031    00000016.81438580  00000011.8151AE00
00000000.00002000
7FF682D0    815CE4C0     set          00020030    00000016.81438580  00000011.8151AE00
00000000.00002000
7FF682F0    815CE200     set          00000031    00000016.81438580  00000011.8151AE00
00000000.00002000
7FF68310    815D4B80     set          00000030    00000016.81438580  00000011.8151AE00
00000000.00002000
7FF68330    815D65C0     set          00020031    00000015.8151A8C0  00000011.8151AE00
00000000.00002000
7FF68350    815D6880     set          00020030    00000015.8151A8C0  00000011.8151AE00
00000000.00002000
.
.
.
7FF68810    815D6B40     set          00020031    00000013.814FBA00  00000011.8151AE00
00000000.00002000
7FF68830    815D5880     set          00020030    00000013.814FBA00  00000011.8151AE00
00000000.00002000
.
.
.
VA      7FF68850
-----
      00000013 free FVEs (IRP = 00000000)
      -to- 7FF68A90
7FF68AB0    815D9840     set          00020031    00000017.81464480  00000011.8151AE00
00000000.00002000
7FF68AD0    815CD040     set          00020030    00000017.81464480  00000011.8151AE00
00000000.00002000
7FF68AF0    815CB480     set          00000031    00000017.81464480  00000011.8151AE00
00000000.00002000)

```

The **SHOW PROCESS/BUFFER_OBJECTS/FANDLES** command displays all the buffered objects and fast I/O handles that a process has created.

```

SDA> SHOW PROCESS JOB_CONTROL/TQE
Process index: 000C   Name: JOB_CONTROL   Extended PID: 0000004C
-----

```

Timer queue entries

TQE address	Expiration Time	Type
81504080	00A05ABD.895F93C5 27-NOV-2001 11:17:17.37	TSD---
815026C0	00A05AC3.80D0E000 27-NOV-2001 12:00:00.00	TSA---
81502180	00A0C160.635594EF 7-APR-2002 02:00:00.12	TSA---

This example shows the timer queue entries for the process JOB_CONTROL. See Table 4.27 for an explanation of the Type codes.

```
SDA> SHOW PROCESS /IMAGE
```

```
Process index: 0005   Name: SA_STARTUP_DCL   Extended PID: 00000025
-----)
```

Process activated images

Image Name	Type	IMCB	GP
SDA	MAIN	7FE86EB0	00000000.00230000
SDA\$SHARE	GLBL	7FE86190	00000000.00636000
SMGSHR	GLBL	7FE87830	00000000.00706000
...			

Total images = 17

Pages allocated = 2165

This example includes the GP (global pointer) for all images in the process.

```
SDA> SHOW PROCESS/IMAGE=SDA
```

```
Process index: 0005   Name: SA_STARTUP_DCL   Extended PID: 00000025
-----)
```

Process activated images

Image Name/Link Maj,Min ID,Match	Time/Section	Type	Type/File Id	IMCB	Sym Vect
----- *** see below ***					
SDA			MAIN	7FE86EB0	
231F,85F10A8C,01					
17-MAY-2004 10:55:33.89			(1346,1,0)		
			Code		
			Data (read only)		
			Short data		
			Fixup		

*** Rightmost columns from above output moved here ***

Base	End	ImageOff

GP = 00000000.00230000		

```
00000000.00010000 00000000.0001022F 00010000
00000000.00020000 00000000.000200EF 00020000
00000000.00030000 00000000.00030077 00030000
00000000.80000000 00000000.800003FF 80000000
```

This example includes the GP (global pointer) for the SDA image.

4.64. SHOW RAD

Displays the settings and explanations of the RAD_SUPPORT system parameter fields, and the assignment of CPUs and memory to the Resource Affinity Domains (RADs). This command is only useful on platforms that support RADs. By default, the SHOW RAD command displays the settings of the RAD_SUPPORT system parameter fields.

Format

```
SHOW RAD [number | /ALL | /PXML]
```

Parameter

number

Displays information on CPUs and memory for the specified RAD.

Qualifiers

/ALL

Displays settings of the RAD_SUPPORT parameter fields and the CPU and memory assignments for all RADs.

/PXML (Integrity servers only)

SDA displays the proximity database derived from the Advanced Configuration and Power Interface (ACPI) tables. The proximity database is used to set up the RAD data structures.

Examples

1. SDA> SHOW RAD

```
Resource Affinity Domains
```

```
-----
```

```
RAD information header address: FFFFFFFF.81032340
Maximum RAD count:                00000008
RAD containing SYS$BASE_IMAGE:    00000000
RAD support flags:                 0000004F
```

```

  3          2 2          1 1
  1          4 3          6 5          8 7          0
+-----+-----+-----+-----+
|...|...| skip|ss|gg|ww|pp|...|...|...|...|p|fs|cr|ae|
+-----+-----+-----+-----+
|...|...|  0| 0| 0| 0| 0|...|...|...|...|.1|00|11|11|
+-----+-----+-----+-----+
```

```
Bit 0 = 1:                RAD support is enabled
```



```

Bit 1 = 1:      Soft RAD affinity support is enabled
                 (Default scheduler skip count of 16 attempts)

Bit 2 = 1:      System-space replication support is enabled

Bit 3 = 1:      Copy on soft fault is enabled

Bit 4 = 0:      Default RAD-based page allocation in use

Allocation Type          RAD choice
-----
Process-private pagefault  Home
Process creation or inswap  Random
Global pagefault           Random
System-space page allocation  Current

Bit 5 = 0:      RAD debug feature is disabled

Bit 6 = 1:      Per-RAD non-paged pool is enabled

```

This example shows the settings of the RAD_SUPPORT system parameter fields.

- SDA> SHOW RAD 2
Resource Affinity Domain 0002

```

-----
CPU sets:

Active      08 10 11
Active      08 10 11
Configure   08 09 10 11
Potential   08 10 11

PFN ranges:

Start PFN   End PFN     PFN count   Flags
-----
01000000    0107FFE7   0007FFE8    000A  OpenVMS Base
0107FFE8    0107FFFF   00000018    0009  Console Base

SYSPTBR:    01002A01

RAD data:    B817C000

```

This example shows information on the CPUs and memory for RAD 2.

4.65. SHOW RESOURCES

Displays information about all resources in the system or about a resource associated with a specific lock.

Format

SHOW RESOURCES [/ADDRESS=*n*

| /ALL (*d*)

```
| /BRIEF  
| /CACHED  
| /CONTENTION [=ALL][ /FULL]  
| /LOCKID=lock-id  
| /LIST  
| /NAME=name  
| /OWNED  
| /STATUS=(keyword[ ,... ] )
```

Parameters

None.

Qualifiers

/ADDRESS=*n*

Displays information from the resource block at the specified address.

/ALL

Displays information from all resource blocks (RSBs) in the system. This is the default behavior of the SHOW RESOURCES command.

/BRIEF

Displays a single line of information for each resource.

/CACHED

Displays resource blocks that are no longer valid. The memory for these resources is saved so that later requests for resources can use them.

/CONTENTION [=ALL]

Displays only resources that have at least one lock on either the waiting or conversion queue. Unless you specify the ALL keyword, resources with locks on the waiting or conversion queues that are not participating in deadlock searches are ignored. (Locks not participating in deadlock searches are requested with either the LCK\$M_NODLCKWT or LCK\$M_NODLCKBLK flags.) By default, a single line summary is displayed for each resource, followed by a single line summary for each lock on the resource. Use /FULL to obtain a detailed display for each resource that is in contention.

/FULL

When used with /CONTENTION [=ALL], causes SDA to display details of each resource that is in contention instead of a single line summary.

/LIST

Displays summary information for each resource, followed by a list of all locks associated with the resource.

/LOCKID=*lock-id*

Displays information on the resource associated with the lock with the specified *lock-id*.

/NAME=*name*

Displays information about the specific resource. Name may be the actual name of the resource, if it only contains uppercase letters, numerals, the underscore (_), dollar sign, colon (:), and some other printable characters, as for example, /NAME=MY_LOCK. If it contains other printable characters (including lowercase letters), you may need to enclose the name in quotation marks (""), as for example, /NAME="My_Lock/47". If it contains nonprintable characters, the name may be specified as a comma-separated list comprised of strings and hexadecimal numbers, as for example, /NAME=("My_Lock",0C00,"/47") would specify the name "My_Lock<NUL><FF>/47". The hexadecimal number can be no more than 8 digits (4 bytes) in length. Nonprintable sequences or more than 4 bytes must be split into multiple hexadecimal numbers. The maximum length of a resource name is 32 characters.

/OWNED

Displays only owned resources.

/STATUS=(*keyword*[,...])

Displays only resources that have the specified status bits set in the RSB\$L_STATUS field. If you specify only one keyword, you can omit the parentheses. Status keywords are as follows:

Keyword	Meaning
2PC_IP	Indicates a two-phase convert operation in progress
BRL	Indicates byte range resource
CHK_BTR	Checks for better master
CVTFULRNG	Indicates full-range requests in convert queue
CVTSUBRNG	Indicates sub-range requests in convert queue
DIRENTRY	Indicates directory entry during failover
DIR_IP	Creates directory entry
DIR_RQD	Indicates directory entry required
INVPEND	Checks for value block invalidation
RBLD_ACT	Indicates lock rebuild active for this tree
RBLD_IP	Indicates rebuild operation in progress
RBLD_RQD	Indicates rebuild required for this resource tree
RM_ACCEPT	Accepts new master
RM_DEFLECT	Deflects remote interest
RM_FORCE	Forces tree move
RM_FREEZE	Freeze resource tree on this node
RM_INTEREST	Remaster due to master having no interest
RM_IP	Indicates resource remaster in progress
RM_PEND	Indicates a pending resource remaster operation

Keyword	Meaning
RM_RBLD	Indicates to always rebuild resource tree
RM_WAIT	Blocks local activity
VALCUR	Indicates value block is current
VALINVLD	Indicates value block invalid
WTFULRNG	Indicates full-range requests in wait queue
WTSUBRNG	Indicates a sub-range requests in wait queue
XVAL_VALID	Indicates last value block was long block

Description

The SHOW RESOURCES command displays the information listed in Table 4.22 either for each resource in the system or for the specific resource associated with the specified lock-id, address, or name.

Table 4.22. Resource Information in the SHOW RESOURCES Display

Field (in order of display)	Contents
RSB	Address of the resource block (RSB) that describes this resource.
GGMODE	Indication of the most restrictive mode in which a lock on this resource has been granted. Table 4.23 shows the values and their meanings. For information on conflicting and incompatible lock modes, see the <i>VSI OpenVMS System Services Reference Manual</i> .
Status	The contents of the resource block status field.
Parent RSB	Address of the RSB that is the parent of this RSB. This field is 00000000 if the RSB itself is a parent block.
CGMODE	Indication of the most restrictive lock mode to which a lock on this resource is waiting to be converted. This does not include the mode for which the lock at the head of the conversion queue is waiting. See Table 4.23.
Sub-RSB count	Number of RSBs of which this RSB is the parent. This field is 0 if the RSB has no sub-RSBs.
FGMODE	Indication of the full-range grant mode. See Table 4.23.
Lock Count	The total count of all locks on the resource.
RQSEQNM	Sequence number of the request.
BLKAST count	Number of locks on this resource that have requested a blocking AST.
CSID	Cluster system identification number (CSID) and name of the node that owns the resource.
Resource	Dump of the name of this resource, as stored at the end of the RSB. The first two columns are the

Field (in order of display)	Contents
	hexadecimal representation of the name, with the least significant byte represented by the rightmost two digits in the rightmost column. The third column contains the ASCII representation of the name, the least significant byte being represented by the leftmost character in the column. Periods in this column represent values that correspond to nonprinting ASCII characters.
Valblk	Hexadecimal and ASCII dump of the first 16 bytes of the value block associated with this resource. See Extended Value Block later in this table for the display of the rest of the value block.
Length	Length in bytes of the resource name.
<i>x</i> mode	Processor mode of the namespace in which this RSB resides (Group, Kernel, User).
<i>owner</i>	Owner of the resource. Certain resources, owned by the operating system, list "System" as the owner. Locks owned by a group have the number (in octal) of the owning group in this field.
Seqnum	Sequence number associated with the resource's value block. If the number indicates that the value block is not valid, the words "Not valid" appear to the right of the number.
Extended Valblk	If any of the last 48 bytes of the value block (see Valblk earlier in this table) are non-zero, then the entire 64-byte value block is displayed as hexadecimal and ASCII dumps. Otherwise this display is omitted. The display appears only when value block contents are non-zero, without regard to the state of the RSB\$M_XVAL_VALID flag.
Granted queue	List of locks on this resource that have been granted. For each lock in the list, SDA displays the number of the lock and the lock mode in which the lock was granted.
Conversion queue	List of locks waiting to be converted from one mode to another. For each lock in the list, SDA displays the number of the lock, the mode in which the lock was granted, and the mode to which the lock is to be converted.
Waiting queue	List of locks waiting to be granted. For each lock in the list, SDA displays the number of the lock and the mode requested for that lock.

Table 4.23. Lock Modes on Resources

Value1	Meaning
NL	Null mode
CR	Concurrent-read mode

Value1	Meaning
CW	Concurrent-write mode
PR	Protected-read mode
PW	Protected-write mode
EX	Exclusive mode

Values are shown in order from the least restrictive mode to the most restrictive.

Examples

1. SDA> SHOW RESOURCES

Resource Database

```
RSB:          FFFFFFFF.7FEECE40  GGMODE:      PW  Status: VALID   XVALID
Parent RSB:   00000000.00000000  CGMODE:      PW
Sub-RSB count:      0          FGMODE:      PW
Lock Count:      1          RQSEQNM:   0000
BLKAST count:      0          CSID: 00000000  (SAND41)
```

```
Resource:      00000000 0043524A  JRC.....  Valblk: 5F73695F
73696854
Length 3      00000000 00000000  .....  6F5F7473
65745F61
User mode     00000000 00000000  .....  This_is_a_test_o
Group 001     00000000 00000000  .....  Seqnum: 00000001
```

```
Extended Valblk: 6F5F7473 65745F61 5F73695F 73696854 This_is_a_test_o
565F6465 646E6574 78455F65 68745F66 f_the_Extended_V
00000000 00006B63 6F6C425F 65756C61 alue_Block.....
00000000 00000000 00000000 00000000 .....
```

Granted queue (Lock ID / Gr mode / Range):

```
1500082F PW 00000000-FFFFFFFF
```

Conversion queue (Lock ID / Gr mode / Range -> Rq mode / Range):

```
*** EMPTY QUEUE ***
```

Waiting queue (Lock ID / Rq mode / Range):

```
*** EMPTY QUEUE ***
```

SDA> SHOW RESOURCES

Resource Database

```
RSB:          FFFFFFFF.7FEECE40  GGMODE:      PW  Status: VALID
Parent RSB:   00000000.00000000  CGMODE:      PW
Sub-RSB count:      0          FGMODE:      PW
Lock Count:      1          RQSEQNM:   0002
BLKAST count:      0          CSID: 00000000  (SAND41)
```

```
Resource:      00000000 0043524A  JRC.....  Valblk: 5F74726F
68735F41
Length 3      00000000 00000000  .....  00000000
00656E6F
User mode     00000000 00000000  .....  A_short_one.....
```

```

Group    001          00000000 00000000  ....    Seqnum: 00000003

Extended Valblk:    00000000 00656E6F 5F74726F 68735F41  A_short_one.....
                   565F6465 646E6574 78455F65 68745F66  f_the_Extended_V
                   00000000 00006B63 6F6C425F 65756C61  alue_Block.....
                   00000000 00000000 00000000 00000000  .....

Granted queue (Lock ID / Gr mode / Range):
3900080C PW 00000000-FFFFFFFF

Conversion queue (Lock ID / Gr mode / Range -> Rq mode / Range):
*** EMPTY QUEUE ***

Waiting queue (Lock ID / Rq mode / Range):
*** EMPTY QUEUE ***

```

These examples for Alpha and Integrity server systems show two cases:

- output from a program writing a longer block
- output where the last writer wrote a short value block (XVALID not set), but because a previous writer wrote non-zero data to the high portion of the block and these data are still present, the data in the Extended Value Block are shown.

2.

```

SDA> SHOW RESOURCE/CONTENTION
Resource Contention Information:
-----
   RSB Address   Parent RSB Addr   Resource Name   LkB Address   PID   Node   Lockid   GR   RQ   Queue
-----
FFFFFFFF.7FAAC550 FFFFFFFFF.7FB47A50 P.....
                                                     FFFFFFFFF.7FAEC350 00010027 SWORKS 04001158 PW   Granted
                                                     FFFFFFFFF.7FB34550 00000000 CMOS   08000E46 CR   Granted
                                                     FFFFFFFFF.7FA93250 00000000 CMOS   030015A3 CR   Granted
                                                     FFFFFFFFF.7FB3EA50 00000000 CMOS   09000DC0 CR   Granted
                                                     FFFFFFFFF.7FAE7B50 00000000 CMOS   080011C6 CR   Granted
                                                     FFFFFFFFF.7FA36050 00010023 SWORKS 060019F3 CR   Granted
                                                     FFFFFFFFF.7FA7BE50 00000000 CMOS   020016A1 NL   Granted
                                                     FFFFFFFFF.7FAAC650 00000000 SWORKS 010014AC NL   Granted
                                                     FFFFFFFFF.7FA62C50 00010028 SWORKS 020017C1 CR   PW Convert
                                                     FFFFFFFFF.7FAF9950 00010024 SWORKS 040010E5 CR   PW Convert
                                                     FFFFFFFFF.7FA33C50 00000000 CMOS   02001A36 PW   Waiting
                                                     FFFFFFFFF.7FB14550 00000000 CMOS   0F00010E PW   Waiting

FFFFFFFF.7FB39050 FFFFFFFFF.7FB47A50 P...8...
                                                     FFFFFFFFF.7FB3CC50 00010024 SWORKS 0B000DDC PW   Granted
                                                     FFFFFFFFF.7FAC0E50 00010023 SWORKS 03001400 CR   Granted
                                                     FFFFFFFFF.7FA74950 00000000 CMOS   030016DE CR   Granted
                                                     FFFFFFFFF.7FA4C050 00010026 SWORKS 020018CE CR   Granted
                                                     FFFFFFFFF.7FAC5050 00010022 SWORKS 070013C3 CR   Granted
                                                     FFFFFFFFF.7FB38450 00010025 SWORKS 09000E0E CR   Granted
                                                     FFFFFFFFF.7FACD450 00010028 SWORKS 0700134E CR   Granted
                                                     FFFFFFFFF.7FAD2250 00000000 CMOS   080012DF CR   Granted
                                                     FFFFFFFFF.7FAE0750 00000000 CMOS   0100120F NL   Granted
                                                     FFFFFFFFF.7FB37B50 00000000 SWORKS 01000E3D NL   Granted
                                                     FFFFFFFFF.7FB14A50 00010027 SWORKS 2500011C CR   PR Convert
                                                     FFFFFFFFF.7FAD4950 00000000 CMOS   070012CA CR   PR Convert
                                                     FFFFFFFFF.7FAC9550 00000000 CMOS   0900138D CR   PR Convert
                                                     FFFFFFFFF.7FB03250 00000000 CMOS   0C001069 CR   PR Convert
                                                     FFFFFFFFF.7FD70C50 00000000 CMOS   080005AF CR   PR Convert

FFFFFFFF.7FD7A250 00000000.00000000 †...T...&.a!....
                                                     FFFFFFFFF.7FDC5650 00010026 SWORKS 1A00084C PW   Granted
                                                     FFFFFFFFF.7FDF4950 00010020 SWORKS 010009A1 PW   Waiting

FFFFFFFF.7FD9A250 00000000.00000000 †...T...$.a!....
                                                     FFFFFFFFF.7FD07550 00010024 SWORKS 2E0004EB PW   Granted
                                                     FFFFFFFFF.7FDF4A50 00010020 SWORKS 010009A2 PW   Waiting

FFFFFFFF.7FD36450 FFFFFFFFF.7FD0EC50 QMAN$JBC_ALIVE_01
                                                     FFFFFFFFF.7FD27050 00000000 CMOS   1A0002CA EX   Granted
                                                     FFFFFFFFF.7FD7B450 00000000 CMOS   050007D4 CR   Waiting

```

This example of the SHOW RESOURCES/CONTENTION command shows all the resources for which there is contention, and which are to be included in deadlock searches.

3. SDA> SHOW RESOURCES/LIST

Resource Database									
RSB Address	Parent RSB Addr	Resource Name	LKB Address	PID	Node	Lockid	GR	RQ	Queue
FFFFFFFFE.DD058180	00000000.00000000	F11B\$b\$217\$DKC200:			QTV11				
			FFFFFFFFE.DD04E580	00000000	MHERTZ	02000DDF	CR		Granted
FFFFFFFFE.DCF6F080	00000000.00000000	F11B\$v\$22\$DKB12:			QTV11				
			FFFFFFFFE.DD063180	00000000	MHERTZ	0200122D	CR		Granted
FFFFFFFFE.DCFAC680	00000000.00000000	SYSS_\$70\$DKA302:			QTV11				
			FFFFFFFFE.DCF21180	00000000	MHERTZ	03001130	CR		Granted
FFFFFFFFE.DCFBA580	FFFFFFFFE.DCEFBC80	F11B\$s\$.#..			BACH				
			FFFFFFFFE.DD032380	00000000	MHERTZ	0D000C9F	NL		Granted
FFFFFFFFE.DD00E380	00000000.00000000	CACHE\$cmRAVEN_BACKUPù...			MHERTZ				
			FFFFFFFFE.DCF54A80	00000000	B8OVEN	03000280	PR		Granted
			FFFFFFFFE.DCF8780	00000000	QTV9	12000C51	PR		Granted
			FFFFFFFFE.DD029880	00000000	KHERTZ	07000A6B	PR		Granted
			FFFFFFFFE.DD002780	00000000	MHERTZ	16000829	PR		Granted
FFFFFFFFE.DD060A80	00000000.00000000	SYSS_DSA71:			QTV11				
			FFFFFFFFE.DCF91580	00000000	MHERTZ	1A00115D	CR		Granted
FFFFFFFFE.DCF22B80	00000000.00000000	CACHE\$cmB_PICCHUBCK ù...			WHAMOO				
FFFFFFFFE.DCF57E80	00000000.00000000	\$DSA7779_\$SEQCMD			QTV9				
			FFFFFFFFE.DCF37D80	00000000	MHERTZ	0300011C	PR		Granted
FFFFFFFFE.DCFDD780	00000000.00000000	CACHE\$cmPAGE_SWAP ù...			QTV11				
			FFFFFFFFE.DCFD3880	00000000	MHERTZ	0D00062A	PR		Granted
:									
:									
FFFFFFFFE.DCFA6480	00000000.00000000	VCC\$v\$1\$DUA126:			QTV11				
			FFFFFFFFE.DD053980	00000000	MHERTZ	23000E09	PR		Granted
FFFFFFFFE.DCF9BA80	00000000.00000000	\$DSA7778_\$WATCHR			EBJB17				
			FFFFFFFFE.DCFFA280	00000000	MHERTZ	02000AF3	EX		Waiting
FFFFFFFFE.DCF50380	00000000.00000000	F11B\$aRAVEN_BACKUPö...			KHERTZ				
			FFFFFFFFE.DCEED980	00000000	MHERTZ	01000025	PR		Granted

This example shows the output from the SHOW RESOURCES/LIST command.

4.66. SHOW RMD

Displays information contained in the reserved memory descriptors. Reserved memory is used within the system by memory-resident global sections.

Format

SHOW RMD [/qualifiers]

Parameters

None.

Qualifiers

/ADDRESS=*n*

Displays a specific reserved memory descriptor entry, given its address.

/ALL

Displays information in all the reserved memory descriptors. This qualifier is the default.

Description

The SHOW RMD command displays information that resides in the reserved memory descriptors. The table below shows the fields and their meanings.

Table 4.24. RMD Fields

Field	Meaning
Address	Gives the address of the reserved memory descriptor.
Name	Gives the name of the reserved memory descriptor.
Group	Gives the UIC group that owns the reserved memory. This is given as -S- for system global reserved memory.
RAD	Gives the required RAD for the reserved memory. Displays "Any" if no RAD specified.
PFN	Gives starting page number of the reserved memory.
Count	Gives the number of pages reserved.
In_Use (Error)	Gives the number of pages in use. If an error occurred when the reserved memory was being allocated, the error condition code is displayed in parentheses. A second line, giving the text of the error, is also displayed in this case.
Zero_PFN	Gives the next page number to be zeroed.
Flags	Gives the settings of flags for specified reserved memory descriptor as a hexadecimal number, then displays key flag bits by name. The names may use multiple lines in the display.

Examples

1. SDA> SHOW RMD

```
Reserved Memory Descriptor List
-----
Address  Name              Group RAD   PFN     Count      In_Use
Zero_PFN  Flags
-----  -
-----  -
814199C0 LARGE                00022 Any   00000000 000004E2 00000000
00000000 000000E0 Group Page_Tables
                GBLSec
81419940 LARGE                00022 Any   00000000 00138800 (0000244C)
00000000 000001A0 Error Group GBLSec
                Error = %SYSTEM-F-INSFLPGS, insufficient Fluid Pages available
81419AC0 SMALL                00011 0001 00000180 00000001 00000000
00000180 000000E1 Alloc Group
                Page_Tables GBLSec
81419A40 SMALL                00011 0001 00000E00 00000080 00000000
00000E00 000000A1 Alloc Group GBLSec
```

This example shows the default output of a SHOW RMD command.

4.67. SHOW RMS

Displays the RMS data structures selected by the SET RMS command to be included in the default display of the SHOW PROCESS/RMS command.

Format

SHOW RMS

Parameters

None.

Qualifiers

None.

Description

The SHOW RMS command lists the names of the data structures selected for the default display of the SHOW PROCESS/RMS command.

For a description of the significance of the options listed in the SHOW RMS display, see the description of the SET RMS command and Table 4.2.

For an illustration of the information displayed by the SHOW PROCESS/RMS command, see the examples included in the description of the SHOW PROCESS command.

Examples

1. SDA> SHOW RMS

```
RMS Display Options:
  IFB, IRB, IDX, BDB, BDBSUM, ASB, CCB, WCB, FCB, FAB, RAB, NAM,
  XAB, RLB, BLB, BLBSUM, GBD, GBH, FWA, GBDSUM, JFB, NWA, RU, DRC, SFSB, GBSB
Display RMS structures for all IFI values.
```

The SHOW RMS command displays the full set of options available for display by the SHOW PROCESS/RMS command. SDA, by default, selects the full set of RMS options at the beginning of an analysis.

2. SDA> SET RMS=(IFAB=1, CCB, WCB)
SDA> SHOW RMS

```
RMS Display Options:  IFB, CCB, WCB
Display RMS structures only for IFI = 0001
```

The SET RMS command establishes the IFB, CCB, and WCB as the structures to be displayed, and only for the file whose internal File Identifier has the value 1, when the SHOW PROCESS/RMS command is issued. The SHOW RMS command verifies this selection of RMS options.

4.68. SHOW RSPID

Displays information about response IDs (RSPIDs) of all System Communications Services (SCS) connections or, optionally, about a specific SCS connection.

Format

```
SHOW RSPID [ /CONNECTION=cdt-address ]
```

Parameters

None.

Qualifier

/CONNECTION=cdt-address

Displays RSPID information for the specific SCS connection whose connection descriptor table (CDT) address is provided in *cdt-address*. You can find the *cdt-address* for any active connection on the system in the **CDT summary page** display of the SHOW CONNECTIONS command. CDT addresses are also stored in many individual data structures related to SCS connections. These data structures include class driver request packets (CDRPs) and unit control blocks (UCBs) for class drivers that use SCS and cluster system blocks (CSBs) for the connection manager.

Description

Whenever a local system application (SYSAP) requires a response from a remote SYSAP, a unique number, called an RSPID, is assigned to the response by the local system. The RSPID is transmitted in the original request (as a means of identification), and the remote SYSAP returns the same RSPID in its response to the original request.

The SHOW RSPID command displays information taken from the response descriptor table (RDT), which lists the currently open local requests that require responses from SYSAPs at a remote node. For each RSPID, SDA displays the following information:

- RSPID value
- Address of the class driver request packet (CDRP), which generally represents the original request
- Address of the CDT that is using the RSPID
- Name of the local process using the RSPID
- Remote node from which a response is required (and has not yet been received)

Examples

```
1. SDA> SHOW RSPID
    --- Summary of Response Descriptor Table (RDT) 805E6F18 ---
RSPID      CDRP Address      CDT Address      Local Process Name
Remote Node
-----
-----
```

39D00000 VANDQ1	8062CC80	805E8710	VMS\$VMScLuster
EE210001 ROMRDR	80637260	805E8C90	VMS\$DISK_CL_DRVR
EE240002 VANDQ1	806382E0	805E8DF0	VMS\$DISK_CL_DRVR
EE440003 VANDQ1	806393E0	805E8F50	VMS\$TAPE_CL_DRVR
5DB90004 ROMRDR	80636BC0	805E8870	VMS\$VMScLuster
5C260005 ROMRDR	80664040	805E8870	VMS\$VMScLuster
38F80006 VANDQ1	80664A80	805E8710	VMS\$VMScLuster

This example shows the default output for the SHOW RSPID command.

```
2. SDA> SHOW RSPID/CONNECTION=805E8F50
    --- Summary of Response Descriptor Table (RDT) 805E6F18 ---
RSPID      CDRP Address      CDT Address      Local Process Name
Remote Node
-----
-----
EE440003   806393E0           805E8F50         VMS$TAPE_CL_DRVR
VANDQ1
```

This example shows the output for a SHOW RSPID/CONNECTION command.

4.69. SHOW SHM_CPP

Displays information about the shared memory common property partitions (CPPs). The default display shows a single-page summary that includes a single line for each CPP.

Format

```
SHOW SHM_CPP [/qualifiers]
```

Parameters

None.

Qualifiers

/ADDRESS=*n*

Displays a detailed page of information about an individual shared memory CPP given the address of the SHM_CPP structure.

/ALL

Displays a detailed page of information about each shared memory CPP.

/IDENT=*n*

Displays a detailed page of information about an individual shared memory CPP.

/PFN [=(*option*[,*option*,...])]

Displays PFN data in addition to the basic SHM_CPP. The default is to display all lists (free, bad, untested), plus the PFN database pages and the complete range of PFNs in the CPP.

You can limit which lists are displayed by specifying one or more keywords from the following table. If you specify multiple keywords, enclose them in parentheses and separate keywords with a comma.

ALL_FRAGMENTS	Displays the complete range of PFNs in the CPP.
BAD	Displays only the bad page list.
FREE	Displays only the free page list.
PFNDB	Displays the PFNs containing the PFN database.
UNTESTED	Displays only the untested page list.

If you specify /PFN without /ALL, /IDENT, or /ADDRESS, the system displays the PFN lists from the last shared memory CPP accessed.

Examples

1. SDA> SHOW SHM_CPP

Summary of Shared Memory Common Property Partitions

```
-----
Base address of SHM_CPP array:          FFFFFFFF.7F2BA140
Maximum number of SHM_CPP entries:      00000007
Size of each SHM_CPP:                   00000240
Maximum fragment count per SHM_CPP:     00000010

Valid CPP count:                         00000001
```

```
  ID   SHM_CPP address      MinPFN  MaxPFN  Page count  Free pages
  Flags
-----
```

```
-- SHM_CPP IDs 0000 to 0002: VALID flag clear --
```

```
0003 FFFFFFFF.7F2BA800    00060000 0007FFFF    00020000    0001FCF7
00000001  VALID
```

```
-- SHM_CPP IDs 0004 to 0006: VALID flag clear --
```

This example shows the default output for the SHOW SHM_CPP command.

2. SDA> SHOW SHM_CPP/IDENT=3

Shared Memory CPP 0003

```
-----
SHM_CPP address:          FFFFFFFF.7F2BA800

  Version:                00000001  Flags:
00000001  VALID
  Size:                   00000000.000000C0  Page count:
00020000
  Actual fragment count:  00000001  Minimum PFN:
00060000
```

```

Maximum fragment count:      00000010   Maximum PFN:
0007FFFF

Length of free page list:    0001FCF7
Length of bad page list:     00000000
Length of untested page list: 00000000

PMAP array for PFN database pages

  PMAP      Start PFN      PFN count
  -----      -
    0.      00060053      00000280

PMAP array for all fragments

  PMAP      Start PFN      PFN count
  -----      -
    0.      00060000      00020000

GLock address:              FFFFFFFF.7F2BA8C0   Handle:
80000000.00010D19

GLock name:                 SHM_CPP00000003   Flags:
00
Owner count:                 00   Owner node:
00
Node sequence:              0000   Owner:
000000
IPL:                        08   Previous IPL:
00
Wait bitmask:               00000000.00000000   Timeout:
00249F00
Thread ID:                  00000000.00000000

Connected GNode bitmask: FFFFFFFF.7F2BA900

Valid bits:                 00000004   State:
00000000.00000000
Unit count:                 0001   Unit size:
QUADWORD

Unit bitmask:
.....7 00000000
Ranges of free pages

  Range      Start PFN      PFN count
  -----      -
    1.      000602F6      00000002
    2.      0006030B      0001FCF5

```

This example shows the details for a single SHM_CPP.

4.70. SHOW SHM_REG

Displays information about shared memory regions. The default display shows a single page summary that includes a single line for each region.

Format

```
SHOW SHM_REG [/qualifiers] [name]
```

Parameter

name

Detailed page of information about the named region.

Qualifiers

/ADDRESS=*n*

Displays a detailed page of information about an individual region given the address of the SHM_REG structure.

/ALL

Displays a detailed page of information about each region.

/IDENT=*n*

Displays a detailed page of information about the specified region.

Examples

1. SDA> SHOW SHM_REG

```

Summary of Shared Memory Regions
-----
Base address of SHM_REG array:      FFFFFFFF.7F2BB140
Maximum number of SHM_REG entries:  00000040
Size of each SHM_REG:               00000208
Base address of SHM_DESC array:     FFFFFFFF.7F2DC000

Valid region count:                 00000009

ID   SHM_REG address                Region Tag                SysVA / GSTX
Flags
-----
0000 FFFFFFFF.7F2BB140 SYS$GALAXY_MANAGEMENT_DATABASE FFFFFFFF.7F234000
00000001 VALID
0001 FFFFFFFF.7F2BB348 SYS$SHARED_MEMORY_PFN_DATABASE FFFFFFFF.00000000
00000001 VALID
0002 FFFFFFFF.7F2BB550 SMCI$SECTION_PBA_04001          --<None>--
00000001 VALID
0003 FFFFFFFF.7F2BB758 GLX$CPU$BALANCER$SYSGBL          0000013F
00000005 VALID SHARED_CONTEXT_VALID
0004 FFFFFFFF.7F2BB960 SMCI$CHANNEL_PBA_0_1          FFFFFFFF.8F3AE000
00000001 VALID
0005 FFFFFFFF.7F2BBB68 SMCI$CHANNEL_PBA_0_2          FFFFFFFF.8FAEE000
00000001 VALID
0006 FFFFFFFF.7F2BBD70 SMCI$CHANNEL_PBA_1_2          --<Not Attached>--
00000001 VALID

```

```

0007 FFFFFFFF.7F2BBF78 LAN$SHM_REG                FFFFFFFF.7F20C000
00000009  VALID ATTACH_DETACH
0008 FFFFFFFF.7F2BC180 GLX$CPU_BAL_GLOCK  $000006          00000140
00000005  VALID SHARED_CONTEXT_VALID

```

-- SHM_REG IDs 0009 to 003F: never used --

This example shows the summary of all shared memory regions in the system.

2. SDA> SHOW SHM_REG SMCI\$CHANNEL_PBA_0_1

```

-----
SHM_REG address:          FFFFFFFF.7F2BB960

  Version:                00000001  Flags:
00000001  VALID
  Index/Sequence:        0004/00000003  Size:
00000000.00000120

  Region tag:            SMCI$CHANNEL_PBA_0_1
  Creation time:         31-MAR-1999 14:11:11.37

SHM_DESC address:       FFFFFFFF.7F2DC200

  Version:                00000001  Flags:
00000005  ATTACHED SYS_VA_VALID
  System VA:             FFFFFFFF.8F3AE000  Virtual size:
00000000.00274000
  I/O ref count:        00000000.00000000
  Index/Sequence:        0004/00000003  Context:
FFFFFFFF.80F42480
  Callback:             FFFFFFFF.8F38E5C0  SYS$PBDRIVER+185C0

MMAP address:           FFFFFFFF.7F2BB9E0

  Level count:           0001  Flags:
0001  VALID
  Top page count:        00000001  Virtual size:
00000000.00274000
  PFN list page count:   00000001  First PFN:
000602D4
  Data page count:       00000009

GLock address:          FFFFFFFF.7F2BBA80  Handle:
80000000.00010F51

  GLock name:            SHM_REG00000004  Flags:
00
  Owner count:           00  Owner node:
00
  Node sequence:         0000  Owner:
000000
  IPL:                   08  Previous IPL:
00
  Wait bitmask:          00000000.00000000  Timeout:
002DC6C0
  Thread ID:             00000000.00000000

```



```

Attached GNode bitmask:  FFFFFFFF.7F2BBAC0

  Valid bits:                00000004  State:
00000000.00000012  AUTO_LOCK SET_COUNT
  Unit count:                0001      Unit size:
QUADWORD
  Lock IPL:                  08        Saved IPL:
00000008
  Count of bits set:        00000002

  Unit bitmask:
      .....3  00000000

I/O in progress bitmask: FFFFFFFF.7F2BBAF8

  Valid bits:                00000004  State:
00000000.00000012  AUTO_LOCK SET_COUNT
  Unit count:                0001      Unit size:
QUADWORD
  Lock IPL:                  08        Saved IPL:
00000000
  Count of bits set:        00000000

  Unit bitmask:
      .....0  00000000

SHM_CPP bitmask:          FFFFFFFF.7F2BBB30

  Valid bits:                00000007  State:
00000000.00000000
  Unit count:                0001      Unit size:
QUADWORD

  Unit bitmask:
      .....08  00000000 )

```

This example shows the details for a single shared memory region.

4.71. SHOW SPINLOCKS

Displays the multiprocessing synchronization data structures.

Format

```

SHOW SPINLOCKS {[name]|/ADDRESS=expression|/INDEX=expression}

[{/BRIEF | /COUNTS | /FULL}]

[/CACHED_PCB | /DEVICE | /DYNAMIC | /MAILBOX

| /MISCELLANEOUS | /OWNED | /PCB | /PORT

| /Pshared | /STATIC]

```

Parameters

name

Name of the spinlock to be displayed. Device spinlock names are of the form node\$lock, where node indicates the OpenVMS Cluster node name and lock indicates the device and controller identification (for example, HAETAR\$DUA). If there is no OpenVMS Cluster node name, the dollar sign (\$) is also skipped (for example, DUA).

Qualifiers

/ADDRESS=expression

Displays the spinlock at the address specified in *expression*. You can use the */ADDRESS* qualifier to display a specific device, mailbox, PCB, cached PCB, or process-shared spinlock; however, the name of the spinlock may be listed as "Unknown" in the display.

/BRIEF

Produces a condensed display of the spinlock information displayed by default by the SHOW SPINLOCKS command, including the following: address, spinlock name or device name, IPL or device IPL, rank, ownership depth, and CPU ID of the owner CPU. If the system under analysis was executing with full-checking multiprocessing enabled (according to the setting of the MULTIPROCESSING or SYSTEM_CHECK system parameter), then the number of waiting CPUs and interlock status are also displayed.

/CACHED_PCB

Displays all PCB-specific spinlocks associated with PCBs of deleted processes.

/COUNTS

Produces a display of Spin, Wait, and Acquire counts for each spinlock (only if full-checking multiprocessing is enabled).

/DYNAMIC

Displays information for all dynamic spinlocks in the system (device, port, mailbox, PCB, cached PCB, process-shared, and miscellaneous spinlocks).

/FULL

Displays full descriptive and diagnostic information for each displayed spinlock.

/INDEX=expression

Displays the static spinlock whose index is specified in *expression*. You can only use the */INDEX* qualifier to display a named static spinlock.

/MAILBOX

Displays all mailbox-specific spinlocks.

/MISCELLANEOUS

Display all spinlocks that are not included in existing groups such as mailbox and PCB spinlocks. Miscellaneous spinlocks include the XFC, PEDRIVER, TCP/IP, and various other spinlocks. The list of miscellaneous spinlocks varies from system to system.

/OWNED

Displays information for all spinlocks owned by a CPU. If no processors own any spinlocks, SDA displays the following message:

```
%SDA-I-NOSPLOWNED, all requested spinlocks are unowned
```

/PCB

Displays all PCB-specific spinlocks.

/PORT

Displays all port spinlocks.

/PSHARED

Displays all process-shared (Pthreads) spinlocks.

/STATIC

Displays information for all static spinlocks in the system.

Description

The SHOW SPINLOCKS command displays status and diagnostic information about the multiprocessing synchronization structures known as **spinlocks**.

A **static spinlock** is a spinlock whose data structure is permanently assembled into the system. Static spinlocks are accessed as indexes into a vector of longword addresses called the **spinlock vector**, the address of which is contained in SMP\$AR_SPNLKVEC. The table below lists the static spinlocks.

A **dynamic spinlock** is a spinlock that is created based on the configuration of a particular system. One such dynamic spinlock is the device lock SYSMAN creates when configuring a particular device. This device lock synchronizes access to the device's registers and certain UCB fields. The system creates a dynamic spinlock by allocating space from nonpaged pool, rather than assembling the lock into the system as it does in creating a static spinlock. Other types of dynamic spinlocks are: port spinlocks, mailbox spinlocks, PCB, cached PCB, process-shared, and miscellaneous spinlocks.

See the *Writing OpenVMS Alpha Device Drivers in C* for a full discussion of the role of spinlocks in maintaining synchronization of kernel-mode activities in a multiprocessing environment.

Name	Description
QUEUEAST	Spinlock for queuing ASTs at IPL 6
FILSYS	Spinlock on file system structures
LCKMGR	Spinlock on all lock manager structures
IOLOCK8/SCS	Spinlock for executing a driver fork process at IPL 8
TX_SYNCH	Transaction processing spinlock
TIMER	Spinlock for adding and deleting timer queue entries and searching the timer queue
PORT	Template structure for dynamic spinlocks for ports with multiple devices

Name	Description
IO_MISC	Miscellaneous short-term I/O spinlocks
MMG	Spinlock on memory management, PFN database, swapper, modified page writer, and creation of per-CPU database structures
SCHED	Spinlock on some process data structures and the scheduler database.
IOLOCK9	Spinlock for executing a driver fork process at IPL 9
IOLOCK10	Spinlock for executing a driver fork process at IPL 10
IOLOCK11	Spinlock for executing a driver fork process at IPL 11
MAILBOX	Spinlock for sending messages to the permanent system (OPCOM, JOBCTL, and so on) mailboxes
POOL	Spinlock on nonpaged pool database
PERFMON	Spinlock for I/O performance monitoring
INVALIDATE	Spinlock for system space translation buffer (TB) invalidation
HWCLK	Spinlock on hardware clock database, including the quadword containing the due time of the first timer queue entry (EXE\$GQ_1ST_TIME) and the quadword containing the system time (EXE\$GQ_SYSTIME)
MEGA	Spinlock for serializing access to fork-wait queue
EMB/MCHECK	Spinlock for allocating and releasing error-logging buffers and synchronizing certain machine error handling

For each spinlock in the system, SHOW SPINLOCKS provides the following information:

- Name of the spinlock (or device name for the device lock)
- Address of the spinlock data structure (SPL)
- The owning CPU's CPU ID
- IPL at which allocation of the lock is synchronized on a local processor
- Number of nested acquisitions of the spinlock by the processor owning the spinlock (Ownership Depth)
- Rank of the spinlock
- Timeout interval for spinlock acquisition (in terms of 10 milliseconds)
- Shared array (shared spinlock context block pointer)
- Number of processors waiting to obtain the spinlock

- Interlock (synchronization mutex used when full-checking multiprocessing is enabled)

The last two items (CPUs waiting and Interlock) are only displayed if full-checking multiprocessing is enabled.

SHOW SPINLOCKS/BRIEF produces a condensed display of this same information, excluding the share array and timeout interval.

SHOW SPINLOCKS/COUNTS displays only the Spin, Wait, and Acquire counts for each spinlock.

If the system under analysis was executing with full-checking multiprocessing enabled, SHOW SPINLOCKS/FULL adds to the spinlock display the Spin, Wait, and Acquire counts and the last sixteen PCs at which the lock was acquired or released. If applicable, SDA also displays the PC of the last release of multiple, nested acquisitions of the lock.

If no spinlock name, address, or index is given, then information is displayed for all applicable spinlocks.

Examples

1. SDA> SHOW SPINLOCKS

System static spinlock structures

```
-----
EMB                               Address      810AE300
Owner CPU ID                      None         IPL          0000001F
Ownership Depth                   FFFFFFFF    Rank         00000000
Timeout Interval                   000186A0    Share Array  00000000
CPUs Waiting                       00000000    Interlock    Free

MCHECK                            Address      810AE300
Owner CPU ID                      None         IPL          0000001F
Ownership Depth                   FFFFFFFF    Rank         00000000
Timeout Interval                   000186A0    Share Array  00000000
CPUs Waiting                       00000000    Interlock    Free

MEGA                               Address      810AE400
Owner CPU ID                      None         IPL          0000001F
Ownership Depth                   FFFFFFFF    Rank         00000002
Timeout Interval                   000186A0    Share Array  00000000
CPUs Waiting                       00000000    Interlock    Free

HWCLK                             Address      810AE500
Owner CPU ID                      None         IPL          00000016
Ownership Depth                   FFFFFFFF    Rank         00000004
Timeout Interval                   000186A0    Share Array  00000000
CPUs Waiting                       00000000    Interlock    Free

.
.
.
```

System dynamic spinlock structures

```
-----
QTV14$OPA                         Address      8103FB00
Owner CPU ID                      None         DIPL         00000015
Ownership Depth                   FFFFFFFF    Rank         FFFFFFFF
Timeout Interval                   000186A0    Share Array  00000000
CPUs Waiting                       00000000    Interlock    Free
```

```

QTV14$MBA                               Address      810AE900
Owner CPU ID          None                IPL          0000000B
Ownership Depth       FFFFFFFF        Rank         0000000C
Timeout Interval     000186A0        Share Array  00000000
CPUs Waiting         00000000        Interlock    Free

QTV14$NLA                               Address      810AE900
Owner CPU ID          None                IPL          0000000B
Ownership Depth       FFFFFFFF        Rank         0000000C
Timeout Interval     000186A0        Share Array  00000000
CPUs Waiting         00000000        Interlock    Free

QTV14$PKA                               Address      814AA100
Owner CPU ID          None                DIPL        00000015
Ownership Depth       FFFFFFFF        Rank         FFFFFFFF
Timeout Interval     000186A0        Share Array  00000000
CPUs Waiting         00000000        Interlock    Free
.
.
.

```

This excerpt illustrates the default output of the SHOW SPINLOCKS command.

2. SDA> SHOW SPINLOCKS/BRIEF
System static spinlock structures

```

-----
Address      Spinlock
            Name      IPL      Rank      Depth      Owner      CPUs
            CPU      Waiting Interlock
-----
810AE300 EMB                001F 00000000 FFFFFFFF   None      00000000   Free
810AE300 MCHECK       001F 00000000 FFFFFFFF   None      00000000   Free
810AE400 MEGA         001F 00000002 FFFFFFFF   None      00000000   Free
810AE500 HWCLK        0016 00000004 FFFFFFFF   None      00000000   Free
810AE600 INVALIDATE    0015 00000006 FFFFFFFF   None      00000000   Free
810AE700 PERFMON      000F 00000008 FFFFFFFF   None      00000000   Free
810AE800 POOL         000B 0000000A FFFFFFFF   None      00000000   Free
810AE900 MAILBOX      000B 0000000C FFFFFFFF   None      00000000   Free
810AEA00 IOLOCK11     000B 0000000E FFFFFFFF   None      00000000   Free
810AEB00 IOLOCK10     000A 0000000F FFFFFFFF   None      00000000   Free
810AEC00 IOLOCK9      0009 00000010 FFFFFFFF   None      00000000   Free
810AED00 SCHED        0008 00000012 00000000 00000000 00000001   Free
810AEE00 MMG          0008 00000014 FFFFFFFF   None      00000000   Free
810AEF00 IO_MISC       0008 00000016 FFFFFFFF   None      00000000   Free
810AF000 PORT         0008 00000017 FFFFFFFF   None      00000000   Free
810AF100 TIMER         0008 00000018 00000000 00000000 00000000   Free
810AF200 TX_SYNCH      0008 00000019 FFFFFFFF   None      00000000   Free
810AF300 SCS           0008 0000001A FFFFFFFF   None      00000000   Free
810AF400 LCKMGR        0008 0000001B FFFFFFFF   None      00000000   Free
810AF500 FILSYS        0008 0000001C FFFFFFFF   None      00000000   Free
810AF600 QUEUEAST        0006 0000001E FFFFFFFF   None      00000000   Free

```

System dynamic spinlock structures

Address	Device Name	DIPL	Rank	Depth	Owner CPU	CPUs Waiting	Interlock
8103FB00	QTV14\$OPA	0015	FFFFFFFF	FFFFFFFF	None	00000000	Free
810AE900	QTV14\$MBA	000B	0000000C	FFFFFFFF	None	00000000	Free
810AE900	QTV14\$NLA	000B	0000000C	FFFFFFFF	None	00000000	Free
814AA100	QTV14\$PKA	0015	FFFFFFFF	FFFFFFFF	None	00000000	Free
.

This excerpt illustrates the condensed form of the display produced in the first example.

3. SDA> SHOW SPINLOCKS/FULL SCHED
System static spinlock structures

```
-----
SCHED                                     Address      810AED00
Owner CPU ID                             00000000    IPL          00000008
Ownership Depth                           00000000    Rank         00000012
Timeout Interval                           002DC6C0    Share Array  00000000
CPUs Waiting                               00000001    Interlock    Free

Spins                                     00000000.0458E8DC  Busy waits   00252E8D
Acquires                                  00000000.01279BE0
```

```
Spinlock SPL$C_SCHED was last acquired or released from:
(Most recently)
. 8004AD00 EXE$SWTIMER_FORK_C+00170
. 8004B1D4 EXE$SWTIMER_FORK_C+00644
. 8004AD00 EXE$SWTIMER_FORK_C+00170
. 8004B1D4 EXE$SWTIMER_FORK_C+00644
. 8004AD00 EXE$SWTIMER_FORK_C+00170
. 8004B1D4 EXE$SWTIMER_FORK_C+00644
. 8004AD00 EXE$SWTIMER_FORK_C+00170
. 8004B1D4 EXE$SWTIMER_FORK_C+00644
. 8004AD00 EXE$SWTIMER_FORK_C+00170
. 80136A2C SCH$INTERRUPT+0070C
. 80117580 SCH$IDLE_C+002A0
. 8004B230 EXE$SWTIMER_FORK_C+006A0
. 8004AFC4 EXE$SWTIMER_FORK_C+00434
. 80117360 SCH$IDLE_C+00080
. 8012E5F4 EXE$HIBER_INT_C+00074
(Least recently) 80132150 EXE$SCHDWK_C+00110
```

```
Last release of multiple acquisitions occurred at:
80262A54 EXE$CHECK_VERSION_C+009F4
```

This display shows the detailed information on the SCHED spinlock, including the PC history.

4.72. SHOW STACK

Displays the location and contents of the process stacks (of the SDA current process) and the system stack.

Format

```
SHOW STACK {range | /ALL | [/EXECUTIVE | /INTERRUPT | /KERNEL | /PHYSICAL | /
```

```
{/LONG | /QUAD (d)}
```

Parameters

range

Range of memory locations you want to display in stack format. You can express a range using the following syntax:

<i>m:n</i>	Range of addresses from <i>m</i> to <i>n</i>
<i>m;n</i>	Range of addresses starting at <i>m</i> and continuing for <i>n</i> bytes

Qualifiers

/ALL

Displays the locations and contents of the four process stacks for the SDA current process and the system stack.

/EXECUTIVE

Shows the executive stack for the SDA current process.

/INTERRUPT

Shows the system stack and is retained for compatibility with OpenVMS VAX. The interrupt stack does not exist on OpenVMS Alpha and OpenVMS Integrity servers.

/KERNEL

Shows the kernel stack for the SDA current process.

/LONG

Displays longword width stacks. If you do not specify this qualifier, SDA by default displays quadword width stacks.

/PHYSICAL

Treats the start and end addresses in the given range as physical addresses. This qualifier is only relevant when a range is specified. By default, SDA treats range addresses as virtual addresses.

/QUAD

Displays quadword width stacks. This is the default.

/SUMMARY

Displays a list of all known stack ranges and the current stack pointer for each range.

/SUPERVISOR

Shows the supervisor stack for the SDA current process.

/SYSTEM

Shows the system stack.

/USER

Shows the user stack for the SDA current process.

Description

The SHOW STACK command, by default, displays the stack that was in use when the system failed, or, in the analysis of a running system, the current operating stack. For a process that became the SDA current process as the result of a SET PROCESS command, the SHOW STACK command by default shows its current operating stack.

The various qualifiers to the command allow display of any of the four per-process stacks for the SDA current process, as well as the system stack for the SDA current CPU. In addition, any given range can be displayed in stack format.

You can define SDA process and CPU context by using the SET CPU, SHOW CPU, SHOW CRASH, SET PROCESS, and SHOW PROCESS commands as indicated in their command descriptions. A complete discussion of SDA context control appears in Section 2.5.

SDA provides the following information in each stack display:

Section	Contents
Identity of stack	SDA indicates whether the stack is a process stack (user, supervisor, executive, or kernel) or the system stack.
Stack pointer	The stack pointer identifies the top of the stack. The display indicates the stack pointer by the symbol SP => .
Stack address	SDA lists all the addresses that the operating system has allocated to the stack. The stack addresses are listed in a column that increases in increments of 8 bytes (one quadword) unless you specify the /LONG qualifier, in which case addresses are listed in increments of 4 (one longword).
Stack contents	SDA lists the contents of the stack in a column to the right of the stack addresses.
Symbols	SDA attempts to display the contents of a location symbolically, using a symbol and an offset. If the stack is being displayed in quadword width and the location cannot be symbolized as a quadword, SDA attempts to symbolize the least significant longword and then the most significant longword. If the address cannot be symbolized, this column is left blank.
Canonical stack	When displaying the kernel stack of a noncurrent process in a crash dump, SDA identifies the stack locations used by the scheduler to store the register contents of the process.
Mechanism array Signal array Exception frame	When displaying the current stack in a FATALEXCPT, INVEXCEPTN, SSRVEXCEPT, or UNXSIGNAL bugcheck, SDA identifies the

Section	Contents
	stack locations used to store registers and other key data for these structures.

If a stack is empty, the display shows the following:

```
SP => (STACK IS EMPTY)
```

Examples

1. SDA> SHOW STACK

Current Operating Stack (SYSTEM):

```

          FFFFFFFF.8244BD08  FFFFFFFF.800600FC  SCH
$REPORT_EVENT_C+000FC
          FFFFFFFF.8244BD10  00000000.00000002
          FFFFFFFF.8244BD18  00000000.00000005
          FFFFFFFF.8244BD20  FFFFFFFF.8060C7C0
          SP => FFFFFFFF.8244BD28  FFFFFFFF.8244BEE8
          FFFFFFFF.8244BD30  FFFFFFFF.80018960  EXE
$HWCLKINT_C+00260
          FFFFFFFF.8244BD38  00000000.000001B8
          FFFFFFFF.8244BD40  00000000.00000050
          FFFFFFFF.8244BD48  00000000.00000210  UCB$N_RSID
+00002
          FFFFFFFF.8244BD50  00000000.00000000
          FFFFFFFF.8244BD58  00000000.00000000
          FFFFFFFF.8244BD60  FFFFFFFF.804045D0  SCH
$GQ_IDLE_CPUS
          FFFFFFFF.8244BD68  FFFFFFFF.8041A340  EXE
$GL_FKWAITFL+00020
          FFFFFFFF.8244BD70  00000000.00000250  UCB
$T_MSGDATA+00034
          FFFFFFFF.8244BD78  00000000.00000001
CHF$IS_MCH_ARGS          FFFFFFFF.8244BD80  00000000.0000002B
CHF$PH_MCH_FRAME        FFFFFFFF.8244BD88  FFFFFFFF.8244BFB0
CHF$IS_MCH_DEPTH        FFFFFFFF.8244BD90  80000000.FFFFFFFD  G
CHF$PH_MCH_DADDR        FFFFFFFF.8244BD98  00000000.00001600  CTL
$C_CLIDATASZ+00060
CHF$PH_MCH_ESF_ADDR     FFFFFFFF.8244BDA0  FFFFFFFF.8244BF40
CHF$PH_MCH_SIG_ADDR     FFFFFFFF.8244BDA8  FFFFFFFF.8244BEE8
CHF$IH_MCH_SAVR0        FFFFFFFF.8244BDB0  FFFFFFFF.8041FB00  SMP
$RELEASEL+00640
CHF$IH_MCH_SAVR1        FFFFFFFF.8244BDB8  00000000.00000000
CHF$IH_MCH_SAVR16       FFFFFFFF.8244BDC0  00000000.0000000D
CHF$IH_MCH_SAVR17       FFFFFFFF.8244BDC8  0000FFF0.00007E04
CHF$IH_MCH_SAVR18       FFFFFFFF.8244BDD0  00000000.00000000
CHF$IH_MCH_SAVR19       FFFFFFFF.8244BDD8  00000000.00000001
CHF$IH_MCH_SAVR20       FFFFFFFF.8244BDE0  00000000.00000000
CHF$IH_MCH_SAVR21       FFFFFFFF.8244BDE8  FFFFFFFF.805AE4B6  SISR+0006E
CHF$IH_MCH_SAVR22       FFFFFFFF.8244BDF0  00000000.00000001
CHF$IH_MCH_SAVR23       FFFFFFFF.8244BDF8  00000000.00000010
CHF$IH_MCH_SAVR24       FFFFFFFF.8244BE00  00000000.00000008
CHF$IH_MCH_SAVR25       FFFFFFFF.8244BE08  00000000.00000010
CHF$IH_MCH_SAVR26       FFFFFFFF.8244BE10  00000000.00000001
CHF$IH_MCH_SAVR27       FFFFFFFF.8244BE18  00000000.00000000
CHF$IH_MCH_SAVR28       FFFFFFFF.8244BE20  FFFFFFFF.804045D0  SCH
$GQ_IDLE_CPUS

```

	FFFFFFFF.8244BE28	30000000.00000300	UCB
\$L_PI_SVA			
	FFFFFFFF.8244BE30	FFFFFFFF.80040F6C	EXE
\$REFLECT_C+00950			
	FFFFFFFF.8244BE38	18000000.00000300	UCB
\$L_PI_SVA			
	FFFFFFFF.8244BE40	FFFFFFFF.804267A0	EXE
\$CONTSIGNAL+00228			
	FFFFFFFF.8244BE48	00000000.7FFD00A8	PIO
\$GW_IIOIMPA			
	FFFFFFFF.8244BE50	00000003.00000000	
	FFFFFFFF.8244BE58	FFFFFFFF.8003FC20	EXE
\$CONNECT_SERVICES_C+00920			
	FFFFFFFF.8244BE60	FFFFFFFF.8041FB00	SMP
\$RELEASEL+00640			
	FFFFFFFF.8244BE68	00000000.00000000	
	FFFFFFFF.8244BE70	FFFFFFFF.8042CD50	SCH
\$WAIT_PROC+00060			
	FFFFFFFF.8244BE78	00000000.0000000D	
	FFFFFFFF.8244BE80	0000FFF0.00007E04	
	FFFFFFFF.8244BE88	00000000.00000000	
	FFFFFFFF.8244BE90	00000000.00000001	
	FFFFFFFF.8244BE98	00000000.00000000	
	FFFFFFFF.8244BEA0	FFFFFFFF.805AE4B6	SISR+0006E
	FFFFFFFF.8244BEA8	00000000.00000001	
	FFFFFFFF.8244BEB0	00000000.00000010	
	FFFFFFFF.8244BEB8	00000000.00000008	
	FFFFFFFF.8244BEC0	00000000.00000010	
	FFFFFFFF.8244BEC8	00000000.00000001	
	FFFFFFFF.8244BED0	00000000.00000000	
	FFFFFFFF.8244BED8	FFFFFFFF.804045D0	SCH
\$GQ_IDLE_CPUS			
	FFFFFFFF.8244BEE0	00000000.00000001	
CHF\$L_SIG_ARGS		FFFFFFFF.8244BEE8	0000000C.00000005
CHF\$L_SIG_ARG1		FFFFFFFF.8244BEF0	FFFFFFFFC.00010000
\$K_VERSION_08			SYS
	FFFFFFFF.8244BEF8	00000300.FFFFFFFFC	UCB
\$L_PI_SVA			
	FFFFFFFF.8244BF00	00000002.00000001	
	FFFFFFFF.8244BF08	00000000.0000000C	
	FFFFFFFF.8244BF10	00000000.00000000	
	FFFFFFFF.8244BF18	00000000.FFFFFFFFC	
	FFFFFFFF.8244BF20	00000008.00000000	
	FFFFFFFF.8244BF28	00000000.00000001	
	FFFFFFFF.8244BF30	00000008.00000000	
	FFFFFFFF.8244BF38	00000000.FFFFFFFFC	
INTSTK\$Q_R2		FFFFFFFF.8244BF40	FFFFFFFF.80404668
\$GL_ACTIVE_PRIORITY			SCH
INTSTK\$Q_R3		FFFFFFFF.8244BF48	FFFFFFFF.8042F280
\$WAIT_KERNEL_MODE			SCH
INTSTK\$Q_R4		FFFFFFFF.8244BF50	FFFFFFFF.80615F00
INTSTK\$Q_R5		FFFFFFFF.8244BF58	00000000.00000000
INTSTK\$Q_R6		FFFFFFFF.8244BF60	FFFFFFFF.805AE000
INTSTK\$Q_R7		FFFFFFFF.8244BF68	00000000.00000000
INTSTK\$Q_PC		FFFFFFFF.8244BF70	00000000.FFFFFFFFC
INTSTK\$Q_PS		FFFFFFFF.8244BF78	30000000.00000300
\$L_PI_SVA			UCB

```

          FFFFFFFF.8244BF80  FFFFFFFF.80404668  SCH
$GL_ACTIVE_PRIORITY
          FFFFFFFF.8244BF88  00000000.7FFD00A8  PIO
$GW_IIOIMPA
          FFFFFFFF.8244BF90  00000000.00000000
          FFFFFFFF.8244BF98  FFFFFFFF.8042CD50  SCH
$WAIT_PROC+00060
          FFFFFFFF.8244BFA0  00000000.00000044
          FFFFFFFF.8244BFA8  FFFFFFFF.80403C30  SMP
$GL_FLAGS
Prev SP (8244BFB0) => FFFFFFFF.8244BFB0  FFFFFFFF.8042CD50  SCH
$WAIT_PROC+00060
          FFFFFFFF.8244BFB8  00000000.00000000
          FFFFFFFF.8244BFC0  FFFFFFFF.805EE040
          FFFFFFFF.8244BFC8  FFFFFFFF.8006DB54
PROCESS_MANAGEMENT_NPRO+0DB54
          FFFFFFFF.8244BFD0  FFFFFFFF.80404668  SCH
$GL_ACTIVE_PRIORITY
          FFFFFFFF.8244BFD8  FFFFFFFF.80615F00
          FFFFFFFF.8244BFE0  FFFFFFFF.8041B220  SCH
$RESOURCE_WAIT
          FFFFFFFF.8244BFE8  00000000.00000044
          FFFFFFFF.8244BFF0  FFFFFFFF.80403C30  SMP
$GL_FLAGS
          FFFFFFFF.8244BFF8  00000000.7FF95E00

```

The SHOW STACK command displays a system stack on an OpenVMS Alpha system. The data shown before the stack pointer may not be valid. The mechanism array, signal array, and exception frame symbols displayed on the left appear only for INVEXCEPTN, FATALEXCPT, UNXSIGNAL, and SSRVEXCEPT bugchecks.

2. SDA> SHOW STACK/SUMMARY

Stack Ranges

Memory Stack:

Stack Notes	Stack Base	Stack Limit	Stack Pointer
Kernel	00000000.7FF44000	00000000.7FF2C000	
00000000.7FF43EB0	Current		
Executive	00000000.7FF68000	00000000.7FF58000	
00000000.7FF68000			
Supervisor	00000000.7FFAC000	00000000.7FFA8000	
00000000.7FFAC000			
User	00000000.3FFE2000	00000000.3FFCA000	
00000000.3FFE1FB0	KPstack		
User	00000000.3FFFE000	00000000.3FFE6000	
00000000.3FFFDB0	KPstack		
User	00000000.7AC9E000	00000000.7AC9A000	
00000000.7AC9D830			
System	FFFFFFFF.86970000	FFFFFFFF.86958000	
FFFFFFFF.8696FFC0			

Register Stack:

Stack Notes	Stack Base	Stack Limit	Stack Pointer
Kernel	00000000.7FF12000	00000000.7FF2A000	
00000000.7FF12250	Current		
Executive	00000000.7FF46000	00000000.7FF56000	
00000000.7FF46000			
Supervisor	00000000.7FF6A000	00000000.7FF8A000	
00000000.7FF6A000			
User	000007FD.BFF3C000	000007FD.BFF54000	
000007FD.BFF3C160	KPstack		
User	000007FD.BFF58000	000007FD.BFF70000	
000007FD.BFF58108	KPstack		
User	000007FD.C0000000	000007FD.C0002000	
000007FD.C0000268			
System	FFFFFF802.0F236000	FFFFFF802.0F24E000	
FFFFFF802.0F236278			

This example shows the stack ranges for a process on an OpenVMS Integrity server system.

4.73. SHOW SUMMARY

Displays a list of all active processes and the values of the parameters used in swapping and scheduling these processes.

Format

```
SHOW SUMMARY [/IMAGE | /PAGES | /PROCESS_NAME=process_name
| /TOTALS | /THREAD | /USER=username]
```

Parameters

None.

Qualifiers

/IMAGE

Causes SDA to display, if possible, the name of the image being executed within each process.

/PAGES

Outputs an additional line for each process, displaying the number of process-private pages and the number of global pages in the process's working set.

/PROCESS_NAME=*process_name*

Displays only processes with the specified process name. You can use wildcards in *process_name*, in which case SDA displays all matching processes. The default action is for SDA to display data for all processes, regardless of process name.

/TOTALS

At the end of the list of active processes, SDA will output two sets of totals:

- The total number of process-private and global pages in the working sets of all processes. The totals for resident and non-resident processes are displayed separately.
- The total number of processes (or, if /THREADS was also specified, the total number of kernel threads) in each scheduling state. The totals for resident and non-resident processes or kernel threads are displayed separately.

/THREAD

Displays information on all the kernel threads associated with the current process.

/USER=*username*

Displays only the processes of the specified user. You can use wildcards in *username*, in which case SDA displays processes of all matching users. The default action is for SDA to display data for all processes, regardless of user name.

Description

The SHOW SUMMARY command displays the information in the table below for each active process in the system.

Table 4.25. Process Information in the SHOW SUMMARY Display

Column	Contents
Extended PID	The 32-bit number that uniquely identifies the process or thread.
Indx	Index of this process into the PCB array. When SHOW SUMMARY/THREAD is used, for all threads of a process other than the initial thread, displays the thread number.
Process name	Name assigned to the process. When SHOW SUMMARY/THREAD is used, this column is blank for all threads other than the initial thread.
Username	Name of the user who created the process. When SHOW SUMMARY/THREAD is used, this column is blank for all threads other than the initial thread.
State	Current state of the process. Table 4.26 shows the 14 states and their meanings.
Pri	Current scheduling priority of the process.
PCB/KTB	Address of the process control block or address of the kernel thread block.
PHD	Address of the process header. When SHOW SUMMARY/THREAD is used, this column is blank for all threads other than the initial thread.
Wkset	Number (in decimal) of pages currently in the process working set. When SHOW SUMMARY/THREAD is used, this column is blank for all threads other than the initial thread.

Table 4.26. Current State Information

State	Meaning
COM	Computable and resident in memory
COMO	Computable, but outswapped
CUR <i>nnn</i>	Currently executing on CPU ID <i>nnn</i>
CEF	Waiting for a common event flag
LEF	Waiting for a local event flag
LEFO	Outswapped and waiting for a local event flag
HIB	Hibernating
HIBO	Hibernating and outswapped
SUSP	Suspended
SUSPO	Suspended and outswapped
PFW	Waiting for a page that is not in memory (page-fault wait)
FPG	Waiting to add a page to its working set (free-page wait)
COLPG	Waiting for a page collision to be resolved (collided-page wait); this usually occurs when several processes cause page faults on the same shared page
MWAIT	Miscellaneous wait
RW _{xxx}	Waiting for system resource <i>xxx</i> . These states represent additional interpretation by SDA of one of the 14 scheduler states.
TBS	Waiting "To Be Scheduled" by class scheduler. These states represent additional interpretation by SDA of one of the 14 scheduler states.
TBSO	Waiting "To Be Scheduled" and outswapped. These states represent additional interpretation by SDA of one of the 14 scheduler states.
TBSP	"To Be Scheduled" state is pending. These states represent additional interpretation by SDA of one of the 14 scheduler states.
TBSPO	"To Be Scheduled" state is pending and outswapped. These states represent additional interpretation by SDA of one of the 14 scheduler states.
WTBYT	Waiting for BYTCNT quota. These states represent additional interpretation by SDA of one of the 14 scheduler states.
WTTQE	Waiting for TQCNT quota. These states represent additional interpretation by SDA of one of the 14 scheduler states.

Examples

1. SDA> SHOW SUMMARY

Current process summary

```

-----
Extended Indx Process name   Username   State   Pri PCB/KTB   PHD
Wkset
-- PID -- ----
-----
00000041 0001 SWAPPER                HIB      16 80C641D0 80C63E00
  0
00000045 0005 IPCACP                SYSTEM   HIB      10 80DC0780 81266000
 39
00000046 0006 ERRFMT                SYSTEM   HIB       8 80DC2240 8126C000
 57
00000047 0007 OPCOM                SYSTEM   HIB       8 80DC3340 81272000
 31
00000048 0008 AUDIT_SERVER        AUDIT$SERVER HIB      10 80D61280 81278000
152
00000049 0009 JOB_CONTROL          SYSTEM   HIB      10 80D620C0 8127E000
 50
0000004A 000A SECURITY_SERVER      SYSTEM   HIB      10 80DC58C0 81284000
253
0000004B 000B TP_SERVER            SYSTEM   HIB      10 80DC8900 8128A000
 75
0000004C 000C NETACP              DECNET   HIB      10 80DBFE00 8125A000
 78
0000004D 000D EVL                 DECNET   HIB       6 80DCA080 81290000
 76
0000004E 000E REMACP              SYSTEM   HIB       8 80DE4E00 81296000
 14
00000050 0010 DECW$SERVER_0        SYSTEM   HIB       8 80DEF940 812A2000
739
00000051 0011 DECW$LOGINOUT        <login>  LEF       4 80DF0F00 812A8000
273
00000052 0012 SYSTEM              SYSTEM   LEF       9 80D772C0 81260000
 75

```

The SHOW SUMMARY command describes all active processes in the system at the time of the system failure. Note that there was no process in the CUR state at the time of the failure.

2. SDA> SHOW SUMMARY /IMAGE/PAGES/THREADS/TOTALS

Current process summary

```

-----
Extended Indx Process name   Username   State   Pri PCB/KTB   PHD
Wkset
-- PID -- ----
-----
00000201 0001 SWAPPER                SYSTEM   HIB      16 8230CD48 8230C000
  4
      Process pages:      4      Global pages:      0
.
.
.
00000212 0012 ACME_SERVER            SYSTEM   HIB       8 83673540 87740000
 553
      Process pages:     505      Global pages:     48

```



```

$30$DKB400:[SYS0.SYSCOMMON.] [SYSEXE]ACME_SERVER.EXE
00000412      1                      HIB      10 83684DC0
.
.
.
00000224 0024  LATACP              SYSTEM      HIB      14 83760BC0 8775C000
  170
      Process pages:      170      Global pages:      0
      $30$DKB400:[SYS0.SYSCOMMON.] [SYSEXE]LATACP.EXE
      Total Pages              Process              Global
      -----
-----
      Resident Processes              4490
842
      Nonresident Processes              0
0

          Scheduling   Resident   Nonresident
          State         Threads     Threads     Total
          -----
LEF              1             0             1
HIB              20            0             20
CUR              1             0             1
          -----
Total            22            0             22

```

This example shows the output from `SHOW SUMMARY` when all the qualifiers (`/image /pages /threads /totals`) that display additional data are used.

4.74. SHOW SWIS (Integrity servers Only)

Displays the SWIS (SoftWare Interrupt Services) data structure addresses or the SWIS ring buffer.

Format

```
SHOW SWIS [ /RING_BUFFER [ /CPU=(m,n,...) ] ]
```

Qualifiers

/CPU=(m,n,...)

When used with `/RING_BUFFER`, displays only the entries for the specified CPUs. If you specify only one CPU, you can omit the parentheses.

/RING_BUFFER

Displays the SWIS ring buffer (also known as the SWIS log), with the most recent entry first, and assigns meaning to certain values, such as trap type and system service invoked. For best results, execute `READ/EXEC` or `READ/IMAGE SYS$PUBLIC_VECTORS` first so that the system service codes are recognized.

Examples

```
SDA> read/exec
```

```
SDA> define ssendry 8692B8F0
SDA> define intstk 8692B9F0
SDA> show swis/ring_buffer
```

SWIS ring buffer for all CPUs

```
-----
                        8192. entries: Most recent first

Clock      Data 1      Data 2      Data 3      CPU  Ident      *** See below.
***
-----
2CEDAD3C  82D66400a  83814080  FFFFFFFF.86B04000  00  SWPCXout
2CEDA929  82D66400a  83814080  FFFFFFF802.0EE370A8  00  SWPCTXin
2CED9F16  0000001F  0000001F  FFFFFFFF.8046C270a  00  RaisIPL
2CED928F  8692B8F0a  00000000  FFFFFFFF.8046B760b  00  SSSwRet
2CED8FED  8692B8E0  00000000  0000002C.DC0351F2  00  RetKSrvc
2CED8B2E  8692B8F0a  06900660b  FFFFFFFF.8046B760c  00  EntKSrvc
                               EntKSrvc
2CED72C1  8692B9F0a  00000000  FFFFFFFF.8692BFC0b  00  ExcpDsp2
2CED70B4  8692B9F0a  00000041b  FFFFFFFF.80322F50c  00  ExcpDisp
                               ExcpDisp
2CED6E84  00000001  00000000  00000000.0001001Fa  00  GetDpth
2CED6822  00000016  0000001F  FFFFFFFF.80322EB0a  00  RSetIPL
2CED62F0  8692BCF0a  00000003  FFFFFFFF.8066C000b  00  IPDisp
```

```

                               Symbolized value 'a'      Symbolized value
'b' & 'c'
-----
                               BUG$GQ_HWPCB
                               BUG$GQ_HWPCB
                               EXE$BUGCHECK_SWAPPED_C+000E0
                               SSENTRY                               EXE
$BUGCHECK_CONTINUE_C+003C0
                               SSENTRY                               SYS$RPCC_64_C
                               EXE
$BUGCHECK_CONTINUE_C+003C0
                               INTSTK                               INTSTK+005D
                               INTSTK                               Bugcheck
Breakpoint Trap
SYSTEM_SYNCHRONIZATION_MIN+42F50
                               LNM$C_DEL_OVERLAY+0001B
                               SYSTEM_SYNCHRONIZATION_MIN+42EB0
                               INTSTK+00300                               SCH$IDLE_C+00290
                               .
                               .
                               .
```

The SHOW SWIS example displays the most recent entries in the SWIS log at the time of a system crash. Note the a, b, c alongside the data values. These indicate which column contains the symbolization for the value. 'a' is always in the first column; 'b' is in the second column, and 'c' is also in the second

column on the next line. If some or all data values cannot be symbolized, the columns are left blank or there is no continuation line.

4.75. SHOW SYMBOL

Displays the hexadecimal value of a symbol and, if the value is equal to an address location, the contents of that location.

Format

```
SHOW SYMBOL [/ALL [/ALPHA|/VALUE]] [/BASE_ADDRESS=n] symbol-name
```

Parameter

symbol-name

Name of the symbol to be displayed. You must provide a **symbol-name**, unless you specify the /ALL qualifier. Symbols that include lowercase letters must be enclosed in quotation marks. **symbol-name** may include wildcards unless /ALL is also specified.

Qualifiers

/ALL

Displays information on all symbols whose names begin with the characters specified in **symbol-name**. If no symbol name is given, all symbols are displayed.

/ALPHA

When used with the /ALL qualifier, displays the symbols sorted only in alphabetical order. The default is to display the symbols twice, sorted alphabetically and then by value.

When used with a wildcard symbol name, displays the symbols in alphabetical order. This is the default action.

/BASE_ADDRESS=*n*

The given address is added to the value of each matching symbol to construct the address used when obtaining the contents of the symbol's location. By default, SDA uses the actual value of the symbol as the address to be used. See the description of SHOW SYMBOL for more information.

/VALUE

When used with the /ALL qualifier, displays the symbols sorted only in value order. The default is to display the symbols twice, sorted alphabetically and then by value.

When used with a wildcard symbol name, displays the symbols in value order.

Description

The SHOW SYMBOL command with the /ALL qualifier outputs all symbols whose names begin with the characters specified in **symbol-name** in both alphabetical order and in value order. If no **symbol-name** is given, all symbols are output.

The SHOW SYMBOL/ALL command is useful for determining the values of symbols that belong to a symbol set, as illustrated in the second example below.

The SHOW SYMBOL command without the /ALL qualifier allows for standard wildcards in the **symbol-name** parameter. By default, matching symbols are displayed only in alphabetical order. If you specify SHOW SYMBOL/VALUE, then matching symbols are output sorted by value. If you specify SHOW SYMBOL/ALPHA/VALUE, then matching symbols are displayed twice, sorted alphabetically and then by value.

The SHOW SYMBOL command without the /ALL qualifier and no wildcards in the **symbol-name** parameter outputs the value associated with the given symbol.

When displaying any symbol value, SDA also treats the value as an address (having added the value from /BASE_ADDRESS if specified) and attempts to obtain the contents of the location. If successful, the contents are also displayed.

Examples

```
1. SDA> SHOW SYMBOL G
   G = FFFFFFFF.80000000 : 6BFA8001.201F0104
```

The SHOW SYMBOL command evaluates the symbol G as FFFFFFFF.8000000016 and displays the contents of address FFFFFFFF.8000000016 as 6BFA8001.201F010416.

```
2. SDA> SHOW SYMBOL/ALL BUG
   Symbols sorted by name
   -----
   BUG$L_BUGCHK_FLAGS      = FFFFFFFF.804031E8 : 00000000.00000001
   BUG$L_FATAL_SPSAV       = FFFFFFFF.804031F0 : 00000000.00000001
   BUG$REBOOT              = FFFFFFFF.8042E320 : 00000000.00001808
   BUG$REBOOT_C            = FFFFFFFF.8004F4D0 : 47FB041D.47FD0600
   .
   .
   .
   Symbols sorted by value
   -----
   BUG$REBOOT_C            = FFFFFFFF.8004F4D0 :47FB041D.47FD0600
   BUG$L_BUGCHK_FLAGS      = FFFFFFFF.804031E8 :00000000.00000001
   BUG$L_FATAL_SPSAV       = FFFFFFFF.804031F0 :00000000.00000001
   BUG$REBOOT              = FFFFFFFF.8042E320 :00000000.00001808
   .
   .
   .
```

This example shows the display produced by the SHOW SYMBOL/ALL command. SDA searches its symbol table for all symbols that begin with the string "BUG" and displays the symbols and their values. Although certain values equate to memory addresses, it is doubtful that the contents of those addresses are actually relevant to the symbol definitions in this instance.

4.76. SHOW TQE

Displays the entries in the timer queue. The default output is a summary display of all timer queue entries (TQEs) in chronological order.

Format

```
SHOW TQE [/ADDRESS=n] [/ALL] [/BACKLINK] [/PID=n] [/ROUTINE=n]
```

Parameters

None.

Qualifiers

/ADDRESS=*n*

Outputs a detailed display of the TQE at the specified address.

/ALL

Outputs a detailed display of all TQEs.

/BACKLINK

Outputs the display of TQEs, either detailed (**/ALL**) or brief (default), in reverse order, starting at the entry furthest into the future.

/PID=*n*

Limits the display to the TQEs that affect the process with the specified internal PID. The PID format required is the entire internal PID, including both the process index and the sequence number, and not the extended PID or process index alone, as used elsewhere in SDA. You can also display TQEs specific to a process using **SHOW PROCESS/TQE**.

/ROUTINE=*n*

Limits the display to the TQEs for which the specified address is the fork PC.

Description

The **SHOW TQE** command allows the timer queue to be displayed. By default a summary display of all TQEs is output in chronological order, beginning with the next entry to become current.

The **/ADDRESS**, **/PID**, and **/ROUTINE** qualifiers are mutually exclusive. The **/ADDRESS** and **/BACKLINK** qualifiers are mutually exclusive.

In the summary display, the TQE type is given as a six-character code, as shown in the table below.

Table 4.27. TQE Types in Summary TQE Display

Column	Symbol	Meaning
1	T	Timer (\$SETIMR) entry
	S	System subroutine entry
	W	Scheduled wakeup (\$SCHDWK) entry
2	S	Single-shot entry
	R	Repeated entry
3	D	Delta time
	A	Absolute time

Column	Symbol	Meaning
4	C	CPU time
	--	Elapsed time
5	E	Extended format (64-bit TQE)
	--	32-bit TQE
6	N	TQE not to be deallocated at AST completion
	--	TQE to be deallocated at AST completion

Examples

1. SDA> SHOW TQE

```

Timer queue entries
-----

System time:      15-NOV-2001 15:09:06.92
First TQE time:  15-NOV-2001 15:09:06.92

TQE address          Expiration Time          Type          PID/
-----
815AB8C0  00A0516F.EF279B0F  15-NOV-2001  15:09:06.92  SSD---  835FCC48
TCPIP$INTERNET_SERVICES+9EC48
812CB3C0  00A0516F.EF279B0F  15-NOV-2001  15:09:06.92  SRD---  812CCEC8
SYS$PPPDRIVER+0EEC8
81514140  00A0516F.EF29FD5F  15-NOV-2001  15:09:06.94  TSD---  0001000F
SECURITY_SERVER
815C8040  00A0516F.EF2B2E87  15-NOV-2001  15:09:06.95  SRD---  81361BA0
SYS$LTDRIVER+31BA0
8148CF98  00A0516F.EF2C52AD  15-NOV-2001  15:09:06.95  SRD---  812786B0
LAN$CREATE_LAN+000B0
81318290  00A0516F.EF2FDC84  15-NOV-2001  15:09:06.98  SRD---  813187B8
PWIPDRIVER+047B8
814FB080  00A0516F.EF3238D0  15-NOV-2001  15:09:06.99  TSD---  0001000F
SECURITY_SERVER
8140FF40  00A0516F.EF32851A  15-NOV-2001  15:09:06.99  TSD---  0001000F
SECURITY_SERVER
...

81503100  00A05177.0AED8000  15-NOV-2001  16:00:00.00  TSA---  0001000C
JOB_CONTROL
815030C0  00A0C160.63CD14D9  7-APR-2002  02:00:00.91  TSA---  0001000C
JOB_CONTROL

```

This example shows the summary display of all TQEs.

2. SDA> SHOW TQE/ADDRESS=898DA1A8

```

Timer queue entry 898DA1A8
-----
TQE address:          898DA1A8  Type:
00000005  SYSTEM_SUBROUTINE REPEAT

```

```

Requestor process ID:      00000000  Access mode:
00000000

Expiration time:          00A97229.C9E5FF60  6-JAN-2010 07:24:47.06
+20000
Delta repeat time:        00000000.00030D40      0 00:00:00.02

Fork PC:                  88520460  SYS$GHDRIIVER+50260
Fork R3:                  898D9540.00000000
Fork R4:                  00000000.00000000

```

This example shows the detailed display for a single TQE.

4.77. SHOW TQEIDX

Displays the contents of the timer queue entry index (TQEIDX) structures. The default display is a summary of all TQEIDX structures.

Format

```
SHOW TQEIDX [/ADDRESS=address | /ALL]
```

Parameters

None.

Qualifiers

/ADDRESS=address

Causes SDA to output a detailed display of the contents of the TQEIDX at the specified address. Cannot be specified with /ALL.

/ALL

Causes SDA to output a detailed display of the contents of all TQEIDX structures. Cannot be specified with /ADDRESS.

Description

The SHOW TQEIDX command allows the timer queue entry index structures to be displayed. The default display is a summary of all TQEIDX structures. The /ADDRESS and /ALL qualifiers are mutually exclusive.

Examples

1. SDA> show tqeidx

```
Timer queue index buckets
-----
```

```
Time index buckets
-----
```

TQEIDX address	Level	Parent	Free count	Maximum key
872B6700	00000001	00000000	0000003C	FFFFFFFF.FFFFFFFFFF
875ED640	00000000	872B6700	00000005	00A39404.827C01CF
87312E80	00000000	872B6700	00000032	00A39A11.9DABF957
8726A300	00000000	872B6700	0000003D	FFFFFFFF.FFFFFFFFFF

Time index overflow list is empty

ID index buckets

TQEIDX address	Level	Parent	Free count	Maximum key
872AF900	00000001	00000000	0000003D	FFFFFFFF.FFFFFFFFFF
86C29C80	00000000	872AF900	00000016	0002C000.83374030
872FD780	00000000	872AF900	0000001F	FFFFFFFF.FFFFFFFFFF

ID index overflow list is empty

This example shows the summary TQEIDX display.

4.78. SHOW UNWIND (Integrity servers Only)

Displays the master unwind table for system space (by default) or for a specified target.

Format

```
SHOW UNWIND [address | /ALL | /IMAGE=name ]
```

Parameters

address

Address of the program counter (PC) (IIP) whose unwind data is to be displayed. The address can be in system space or process space.

Qualifiers

/ALL

Displays the details of every system unwind descriptor.

/IMAGE

Displays the details of every unwind descriptor for the specified system images (wildcards allowed).

Description

Displays the master unwind table for system space. This is the default. If /ALL is given, the details of every system unwind descriptor are displayed. If an address is given, the unwind descriptor for the

program counter (PC) (IIP) is located and displayed. The address can be in system space or process space.

Also see SHOW PROCESS/UNWIND.

Examples

1. SDA> show unwind

```

System Unwind Table
-----

Page Header VA          Entries          Region ID
-----
FFFFFFFF.7FFFC000      00000000.00000018  00000000.00000000
FFFFFFFF.7FFFA000      00000000.00000018  00000000.00000000
FFFFFFFF.7FFF8000      00000000.00000018  00000000.00000000
FFFFFFFF.7FF44000      00000000.00000018  00000000.00000000
FFFFFFFF.7F7A0000      00000000.00000018  00000000.00000000
FFFFFFFF.7F56C000      00000000.00000006  00000000.00000000

Image name              Code Base VA      UT Base
VA      Unwind Info Base  Flags
              MUTE VA          Mode          Code End VA      UT
Size              GP
-----

EXCEPTION_MON              FFFFFFFF.80480000
FFFFFFFF.82D53800  FFFFFFFF.82D53800
              FFFFFFFF.7FFFC020  00000000  FFFFFFFF.8055CDCF
00000000.00002AD8  FFFFFFFF.82F6F400

EXCEPTION_MON              FFFFFFFF.86AB0000
FFFFFFFF.86AB4000  FFFFFFFF.86AB4000  Obsolete
              FFFFFFFF.7FFFC170  00000000  FFFFFFFF.86AB207F
00000000.00000060  FFFFFFFF.82F6F400

IO_ROUTINES_MON              FFFFFFFF.80560000
FFFFFFFF.82D78600  FFFFFFFF.82D78600
              FFFFFFFF.7FFFC2C0  00000000  FFFFFFFF.8064A7AF
00000000.00004B00  FFFFFFFF.82FA2800

IO_ROUTINES_MON              FFFFFFFF.86AB6000
FFFFFFFF.86AB8000  FFFFFFFF.86AB8000  Obsolete
              FFFFFFFF.7FFFC410  00000000  FFFFFFFF.86AB73AF
00000000.000000A8  FFFFFFFF.82FA2800

SYSDEVICE              FFFFFFFF.80650000
FFFFFFFF.82DA7A00  FFFFFFFF.82DA7A00
              FFFFFFFF.7FFFC560  00000000  FFFFFFFF.8065E90F
00000000.00000240  FFFFFFFF.82FA9400

```

This example shows the master unwind table for the system, the pages that are being read and the images whose unwind data is present.

2. SDA> show unwind 00000000.00020130

Unwind Table Entry for 00000000.00020130

Image name: X

```
MUTE VA:          000007FD.BFFC62C0   Mode:
00000001
Code Base VA:     00000000.00020000   Code End VA:
00000000.000201FF
UT Base VA:       00000000.00030000   UT Size:
00000000.00000030
Unwind Info Base: 00000000.00030000   GP:
00000000.00240000
Flags:              0000
```

```
Unwind Descriptor: 00000000.00030090   PC range =
00000000.00020130:00000000.000201DF
```

```
Unwind Descriptor flags:   No handler present, No OSSD present
```

```
Unwind descriptor records: R1 Region Header: Short Prologue, PC range
= 00000000.00020130:00000000.00020131
```

```
    P7: MEM_STACK_V PC=00000000.00020131
    P3: PSP_GR      R41
    P3: PFS_GR      R40
```

```
    R1 Region Header: Short Body, PC range =
00000000.00020132:00000000.000201B0
```

```
    B1: Short Label_State LABEL=00000001
    B2: Short Epilogue ECOUNT=00000000
```

```
PC=00000000.000201A0
```

```
    R1 Region Header: Short Body, PC range =
00000000.000201B1:00000000.000201D1
```

```
    B1: Short Copy_State LABEL=00000001
```

This example shows the unwind data for PC 20130, giving image name, location of unwind data and all unwind descriptors. For an explanation of the unwind descriptors, see the appendixes in the *VSI OpenVMS Calling Standard*.

4.79. SHOW VHPT (Integrity servers Only)

Displays data from the Virtual Hash Page Table.

Format

```
SHOW VHPT [ /CPU = {n|*} [/ALL] [range] ]
```

Parameters

range

The entry or range of entries to be displayed, expressed using the following syntax:

<i>m</i>	Displays the VHPT entry <i>m</i>
<i>m:n</i>	Displays the VHPT entries from <i>m</i> to <i>n</i>
<i>m;n</i>	Displays <i>n</i> VHPT entries starting at <i>m</i>

A range can be provided only if a single CPU is specified with the /CPU qualifier.

Qualifiers

/CPU = {*n*|*}

Indicates that the detailed contents of the VHPT for one or all CPUs is to be displayed. The default action is for a summary of VHPT information to be displayed.

/ALL

Displays all VHPTs for the specified CPUs. Without /ALL, only entries that have a valid tag are displayed.

Description

Displays contents of the Virtual Hash Page Table on an OpenVMS Integrity server system. By default, a summary of the VHPT entries is displayed. If CPUs are specified, details of individual VHPT entries are displayed for the CPUs. If a single CPU is specified, specific VHPT entries for that CPU are displayed.

In the detailed display, the columns are as follows:

Table 4.28. VHPT Fields

Column	Contents
Entry	VHPT Entry Number
Bits	One or more of the following flags: P---Present A---Accessed D---Dirty E---Exception deferral I--Tag invalid (only seen if /ALL is specified)
MA	One of the following memory attributes: WB---Write Back UC---Uncacheable UCE---Uncacheable Exported WC---Write Coalescing NaT---NaTPage
AR/PL	The access rights and privilege level of the page. Consists of a number (0-7) and a letter (K, E, S,

Column	Contents
	or U) that determines access to the page in each mode.
KESU	The access allowed to the page in each mode. This is an interpretation of the AR/PL values in the previous column. For an explanation of the access codes, refer to Section 2.8.
Physical address	The starting physical address for this VHPT entry.
Page size	The size of the page represented by this VHPT entry. Page sizes for VHPT entries range from 4KB to 4GB. Not all possible pages sizes are used by OpenVMS for Integrity servers.
Tag	The translation tag for the VHPT entry.
Quad4	Information recorded by OpenVMS for Integrity servers for debugging purposes. The contents of this quadword are subject to change.

Examples

- SDA> SHOW VHPT
Virtual Hash Page Table Summary

CPU 0000

VHPT address: FFFFFFFF.7FFF0000
Translation registers: 00000002
VHPT page size: 0000000E

CPU 0001

VHPT address: FFFFFFFF.7FF88000
Translation registers: 00000002
VHPT page size: 0000000E

This example shows the default behavior of the SHOW VHPT command.

- SDA> SHOW VHPT /CPU=0
Virtual Hash Page Table for CPU 0000

VHPT address: FFFFFFFF.7FFF0000
Translation registers: 00000002
VHPT page size: 0000000E

Entry	Bits	MA	AR/PL	KESU	Physical Address	Page Size	Tag
Quad4							
-----	-----	-----	-----	-----	-----	-----	-----
00000000	PADE	WB	4 E	wr--	00000000.09806000	4MB	0000FE7F.FFFC2C03
					FF000003.85806004		

```

00000001 PADE WB 4 E wr-- 00000000.09804000 4MB 0000FE7F.FFFC2C02
FF000003.85805184
00000002 PADE WB 4 E wr-- 00000000.09802000 4MB 0000FE7F.FFFC2C01
FF000003.85803184
00000003 PADE WB 4 E wr-- 00000000.09800000 4MB 0000FE7F.FFFC2C00
FF000003.858008C4
00000004 PADE WB 2 K w--- 00000000.03726000 8KB 0000FE7F.FFFA0007
FF000003.4000FAB8
00000005 PADE WB 2 K w--- 00000000.03724000 8KB 0000FE7F.FFFA0006
FF000003.4000C478
00000006 PADE WB 2 K w--- 00000000.03722000 8KB 0000FE7F.FFFA0005
FF000003.4000A988
00000007 PADE WB 2 K w--- 00000000.071DA000 8KB 0000FE7F.FFFA1804
FF000003.43008000
00000008 PADE WB 2 K w--- 00000000.0372E000 8KB 0000FE7F.FFFA000B
FF000003.40017C30
00000009 PADE WB 4 E wr-- 00000000.03356000 8KB 0000FE7F.FFFBFC0A
FF000003.7F814CCC
0000000E PADE WB 3 U WWW 00000000.10E78000 8KB 7FFD7C80.000002F7
00FFFAF9.005EE004
00000012 PADE WB 4 E wr-- 00000000.03348000 8KB 0000FE7F.FFFBFC11
FF000003.7F823B28
...
000003FD PADE WB 5 U WRRR 00000000.00004000 8KB 0000FE7F.FFFBFFFE
FF000003.7FFFC020
000003FE PADE WB 5 U WRRR 00000000.00078000 8KB 0000FE7F.FFFBFFFD
FF000003.7FFFA020
000003FF PADE WB 2 K w--- 00000000.0717C000 8KB 0000FE7F.FFFA17FC
FF000003.42FF8000

```

This example shows the detailed contents of all the VHPT entries for CPU 0 that have a valid tag.

4.80. SHOW WORKING_SET_LIST

Displays the system working set list without changing the current process context. You can specify `SHOW WORKING_SET_LIST` or `SHOW WSL`. The two commands are equivalent.

Format

```
SHOW WORKING_SET_LIST [/ALL (d) | /ENTRY=n | /GPT
| /LOCKED | /MODIFIED | /SYSTEM]
```

```
SHOW WSL [/ALL (d) | /ENTRY=n | /GPT
| /LOCKED | /MODIFIED | /SYSTEM]
```

Parameters

None.

Qualifiers

`/ALL`

Displays all working set list entries. This is the default.

/ENTRY=*n*

Displays a specific working set entry, where *n* is the working set list index (WSLX) of the entry of interest.

/GPT

Displays working set list entries only for global page table pages.

/LOCKED

Displays working set list entries only for pageable system pages that are locked in the system working set.

/MODIFIED

Displays working set list entries only for pageable system pages that are marked modified.

/SYSTEM

Displays working set list entries only for pageable system pages.

Description

The SHOW WORKING_SET_LIST command displays the contents of requested entries in the system working set list. The SHOW WORKING_SET_LIST command is equivalent to the SHOW PROCESS/SYSTEM/WORKING_SET_LIST command, but the SDA current process context returns to the prior process upon completion. See the SHOW PROCESS command and Table 4.17 for more information.

4.81. SHOW WSL

See SHOW WORKING_SET_LIST.

4.82. SPAWN

Creates a subprocess of the process currently running SDA, copying the context of the current process to the subprocess and, optionally, executing a specified command within the subprocess.

Format

```
SPAWN [/qualifier[,...]] [command]
```

Parameter

command

Name of the command that you want the subprocess to execute.

Qualifiers

/INPUT=*filespec*

Specifies an input file containing one or more command strings to be executed by the spawned subprocess. If you specify a command string with an input file, the command string is processed before the commands in the input file. When processing is complete, the subprocess is terminated.

/NOLOGICAL_NAMES

Specifies that the logical names of the parent process are not to be copied to the subprocess. The default behavior is that the logical names of the parent process are copied to the subprocess.

/NOSYMBOLS

Specifies that the DCL global and local symbols of the parent process are not to be passed to the subprocess. The default behavior is that these symbols are passed to the subprocess.

/NOTIFY

Specifies that a message is to be broadcast to SYSS\$OUTPUT when the subprocess either completes processing or aborts. The default behavior is that such a message is not sent to SYSS\$OUTPUT.

/NOWAIT

Specifies that the system is not to wait until the subprocess is completed before allowing more commands to be entered. This qualifier allows you to input new SDA commands while the spawned subprocess is running. If you specify /NOWAIT, use /OUTPUT to direct the output of the subprocess to a file to prevent more than one process from simultaneously using your terminal.

The default behavior is that the system waits until the subprocess is completed before allowing more SDA commands to be entered.

/OUTPUT=*filespec*

Specifies an output file to which the results of the SPAWN operation are written. To prevent output from the spawned subprocess from being displayed while you are specifying new commands, specify an output other than SYSS\$OUTPUT whenever you specify /NOWAIT. If you omit the /OUTPUT qualifier, output is written to the current SYSS\$OUTPUT device.

/PROCESS=*process-name*

Specifies the name of the subprocess to be created. The default name of the subprocess is *USERNAME_n*, where *USERNAME* is the user name of the parent process. The variable *n* represents the subprocess number.

Examples

```
1. SDA> SPAWN
   $ MAIL
     .
     .
     .
   $ DIR
     .
     .
     .
   $ LO
     Process SYSTEM_1 logged out at 5-JAN-1993 15:42:23.59
SDA>
```

This example uses the SPAWN command to create a subprocess that issues DCL commands to invoke the Mail utility. The subprocess then lists the contents of a directory before logging out to return to the parent process executing SDA.

4.83. UNDEFINE

Removes the specified symbol from SDA's symbol table.

Format

```
UNDEFINE symbol
```

Parameter

symbol

The name of the symbol to be deleted from SDA's symbol table. A symbol name is required. Symbols that include lowercase letters must be enclosed in quotation marks.

Qualifiers

None.

4.84. VALIDATE PFN_LIST

Validates that the page counts on lists are correct.

Format

```
VALIDATE PFN_LIST {/ALL (d) | [/BAD | /FREE | /MODIFIED | /PRIVATE | /UNTESTED | /
```

Parameters

None.

Qualifiers

/ALL

Validates all the PFN lists: bad, free, modified, untested, zeroed free pages, and private pages.

/BAD

Validates the bad page list.

/FREE

Validates the free page list.

/MODIFIED

Validates the modified page list.

/PRIVATE

Validates all private page lists.

/UNTESTED

Validates the untested page list that was set up for deferred memory testing.

/ZERO

Validates the zeroed free page list.

Description

The `VALIDATE PFN_LIST` command validates the specified PFN list by counting the number of entries in the list and comparing that to the running count of entries for each list maintained by the system.

Examples

1.

```
SDA> VALIDATE PFN_LIST
Free page list validated: 1433 pages
      (excluding zeroed free page list with expected size 103 pages)
Zeroed free page list validated: 103 pages
Modified page list validated: 55 pages
Bad page list validated: 0 pages
Untested page list validated: 0 pages
Private page list at 81486340 validated: 2 pages
```

This example shows the default behavior of `VALIDATE PFN_LIST`, checking all lists.

2.

```
SDA> VALIDATE PFN_LIST/FREE
Free page list validated: 1433 pages
      (excluding zeroed free page list with expected size 103 pages)
```

This example shows the validation of only the free list.

4.85. VALIDATE POOL

Checks all free pool packets for `POOLCHECK`-style corruption, using the same algorithm as the system pool allocation routines when generating a `POOLCHECK` bugcheck and system dump.

Format

```
VALIDATE POOL { /ALL (d) | /BAP | /NONPAGED | /PAGED } [ /HEADER | /MAXIMUM_E
```

Parameters

None.

Qualifiers

/ALL

Checks free packets for all pool types (nonpaged pool, paged pool, and bus addressable pool). This is the default.

/BAP

Checks free packets in bus addressable pool.

/HEADER

Displays only the first 16 bytes of any corrupted free packets found.

/MAXIMUM_BYTES[=*n*]

Displays only the first *n* bytes of any corrupted free packets found. If you specify /MAXIMUM_BYTES without a value, the default is 64 bytes.

/NONPAGED

Checks free packets in nonpaged pool.

/PAGED

Checks free packets in paged pool.

/SUMMARY

Displays only a summary of corrupted pool packets found.

Description

The VALIDATE POOL command displays information about corrupted free pool packets. It is useful only if pool checking has been enabled using either the POOLCHECK or the SYSTEM_CHECK system parameters. (For information on these system parameters, refer to the *VSI OpenVMS System Management Utilities Reference Manual* or to the Sys_Parameters online help topic.)

Examples

- SDA> VALIDATE POOL
Non-Paged Dynamic Storage Pool: no free packet corruption detected
Paged Dynamic Storage Pool: no free packet corruption detected

This example shows the default behavior of VALIDATE POOL, checking all dynamic storage pools.

- SDA> VALIDATE POOL/NONPAGED/HEADER

Corrupt packets in Non-Paged Dynamic Storage Pool

Packet type/subtype	Start	Length	Header contents
[Free] (poolcheck error)	81E34EC0	00049140	64646464 64646464 00049140 00000000@...ddddddd

Non -Paged Dynamic Storage Pool: 1 corrupted free packet found

This example shows the validation of nonpaged pool only, and displays the header of the corrupted block found.

4.86. VALIDATE PROCESS

Performs validation of process data structures. Currently, the only validation available is to check free process pool packets for POOLCHECK-style corruption, using the same algorithm as the system pool allocation routines when generating a POOLCHECK bugcheck and system dump.

Format

```
VALIDATE PROCESS/POOL [= {P0 | P1 | IMGACT | ALL (d)} ] [/ADDRESS=pcb-address  
[/HEADER | /MAXIMUM_BYTES[=n] | /SUMMARY]
```

Parameters

ALL

Indicates that all processes in the system are to be validated.

process name

Name of the process to be validated. The process name can contain up to 15 uppercase letters, numerals, underscore (_), dollar sign (\$), colon (:), and some other printable characters. If it contains any other characters (including lowercase letters), you might need to enclose the process name in quotation marks (" ").

Qualifiers

/ADDRESS = *pcb address*

Specifies the process control block (PCB) address of the process to be validated.

/HEADER

Displays only the first 16 bytes of any corrupted free packets found.

/ID = *nn*/INDEX = *nn*

Specifies the process to be validated by its index into the system's list of software process control blocks (PCBs), or by its process identification. You can supply the following values for *nn*:

- The process index itself.
- A process identification (PID) or extended PID longword, from which SDA extracts the correct index. The PID or extended PID of any thread of a process with multiple kernel threads can be specified. Any thread-specific data displayed by further commands is for the given thread.

To obtain these values for any given process, issue the SDA command SHOW SUMMARY/THREADS. The /ID=*nn* and /INDEX=*nn* qualifiers can be used interchangeably.

/MAXIMUM_BYTES[=*n*]

Displays only the first *n* bytes of any corrupted free packets found. If you specify /MAXIMUM_BYTES without a value, the default is 64 bytes.

/NEXT

Causes SDA to locate the next process in the process list and validate that process. If there are no further processes in the process list, SDA returns an error.

/POOL [= {P0 | P1 | IMGACT | ALL (d)}]

(Required) Causes process pool validation to be performed. Use of a keyword on the /POOL qualifier allows the user to specify which process pool is to be validated (P0, P1, Image Activator Pool, or ALL). Default: ALL

/SUMMARY

Displays only a summary of the corrupted pool packets found.

/SYSTEM

This qualifier is provided for compatibility with SET PROCESS/SYSTEM and SHOW PROCESS/SYSTEM. There is no pool associated with the system process that can be validated. SDA sets its current process context to the system process and outputs the text:

```
Options ignored for System process: POOL
```

Description

The VALIDATE PROCESS command validates the process indicated by one of the following: *process-name*, the process specified in the /ID or /INDEX qualifier, the next process in the system's process list, the system process, or all processes. The VALIDATE PROCESS command performs an implicit SET PROCESS command under certain uses of its qualifiers and parameters, as noted in Section 2.5. By default, the VALIDATE PROCESS command validates the SDA current process, as defined in Section 2.5.

Currently, the only validation available is to check free pool packets for POOLCHECK-style corruption. The command is useful only if pool checking has been enabled using either the POOLCHECK or the SYSTEM_CHECK system parameters. (For information on these system parameters, refer to the *VSI OpenVMS System Management Utilities Reference Manual* or to the Sys_Parameters online help topic.)

If a process is specified using *process-name*, /ADDRESS, /ID, /INDEX, /NEXT, or /SYSTEM, that process becomes the SDA current process for future commands.

Examples

```
SDA> VALIDATE PROCESS JOB_CONTROL/POOL/HEADER
Process index: 000C   Name: JOB_CONTROL       Extended PID: 0000020C
-----
Corrupt packets in P1 Dynamic Storage Pool
-----
Packet type/subtype      Start      Length      Header contents
-----
[Free]                   (poolcheck error)  7FEB6000 0006E000  00600003 027702A0 0006E000 00000000  .....w....
P1 Dynamic Storage Pool: 1 corrupted free packet found
Image Activator Dynamic Storage Pool: no free packet corruption detected
```

This example shows the default behavior of VALIDATE PROCESS/POOL, checking all process storage pools, and displaying only the header of the corrupted block found.

4.87. VALIDATE QUEUE

Validates the integrity of the specified queue by checking the pointers in the queue.

Format

```
VALIDATE QUEUE [address]
```

[/BACKLINK | /LIST | /PHYSICAL
| /QUADWORD | /SELF_RELATIVE | /SINGLY_LINKED]

Parameter

address

Address of an element in a queue.

If you specify the period (.) as the **address**, SDA uses the last evaluated expression as the queue element's address.

If you do not specify an **address**, the VALIDATE QUEUE command determines the address from the last issued VALIDATE QUEUE command in the current SDA session.

If you do not specify an **address**, and no queue has previously been specified, SDA displays the following error message:

```
%SDA-E-NOQUEUE, no queue has been specified for validation
```

Qualifiers

/BACKLINK

Allows doubly linked lists to be validated from the tail of the queue. If the queue is found to be broken when validated from the head of the queue, you can use /BACKLINK to narrow the list of corrupted entries.

/LIST

Displays the address of each element in the queue.

/PHYSICAL

Allows validation of queues whose header and links are physical addresses.

/QUADWORD

Allows the validate operation to occur on queues with linked lists of quadword addresses.

/SELF_RELATIVE

Specifies that the selected queue is a self-relative queue.

/SINGLY_LINKED

Allows validation of queues that have no backward pointers.

Description

The VALIDATE QUEUE command uses the forward and, optionally, backward pointers in each element of the queue to make sure that all such pointers are valid and that the integrity of the queue is intact. If the queue is intact, SDA displays the following message:

Queue is complete, total of n elements in the queue

In these messages, *n* represents the number of entries the VALIDATE QUEUE command has found in the queue.

If SDA discovers an error in the queue, it displays one of the following error messages:

```
Error in forward queue linkage at address nnnnnnnn after tracing x elements
Error comparing backward link to previous structure address (nnnnnnnn)
Error occurred in queue element at address oooooooo after tracing pppp
elements
```

These messages can appear frequently when you use the VALIDATE QUEUE command within an SDA session that is analyzing a running system. In a running system, the composition of a queue can change while the command is tracing its links, thus producing an error message.

If there are no entries in the queue, SDA displays this message:

```
The queue is empty
```

Examples

1. SDA> VALIDATE QUEUE/SELF_RELATIVE IOC\$GQ_POSTIQ
Queue is complete, total of 159 elements in the queue

This example validates the self-relative queue IOC\$GQ_POSTIQ. The validation is successful and the system determines that there are 159 IRPs in the list.

2. SDA> VALIDATE QUEUE/QUADWORD FFFFFFFF80D0E6C0/LIST

Entry	Address	Flink	Blink
Header	FFFFFFFF80D0E6C0	FFFFFFFF80D03780	
	FFFFFFFF80D0E800		
1.	FFFFFFFF80D0E790	FFFFFFFF80D0E7C0	
	FFFFFFFF80D0E6C0		
2.	FFFFFFFF80D0E800	FFFFFFFF80D0E6C0	
	FFFFFFFF80D0E7C0		

Queue is complete, total of 3 elements in the queue

This example shows the validation of quadword elements in a list.

3. SDA> VALIDATE QUEUE/SINGLY_LINKED EXE\$GGL_NONPAGED+4
Queue is zero-terminated, total of 95 elements in the queue

This example shows the validation of singly linked elements in the queue. The forward link of the final element is zero instead of being a pointer back to the queue header.

4.88. VALIDATE SHM_CPP

Validates all the shared memory common property partitions (CPPs) and the counts and ranges of attached PFNs; optionally, it can validate the contents of the database for each PFN.

Format

```
VALIDATE SHM_CPP [/qualifiers]
```

Parameters

None.

Qualifiers

/ADDRESS=*n*

Validates the counts and ranges for a single shared memory CPP given the address of the SHM_CPP structure.

/ALL

Validates all the shared memory CPPs. This is the default.

/IDENT=*n*

Validates the counts and ranges for a single shared memory CPP.

/PFN

Validates the PFN database contents for each attached PFN. The default is all lists (free, bad, untested) plus the PFN database pages and the complete range of PFNs in the CPP.

You can limit which lists are validated by specifying one or more keywords from the following table. If you specify multiple keywords, enclose them in parentheses and separate keywords with a comma.

ALL_FRAGMENTS	Validates the complete range of PFNs in the CPP.
BAD	Validates only the bad page list.
FREE	Validates only the free page list.
PFNDB	Validates the PFNs containing the PFN database.
UNTESTED	Validates only the untested page list.

If you specify the /PFN without /ALL, /IDENT, or /ADDRESS, the system validates the PFN lists from the last shared memory CPP.

Examples

```
SDA> VALIDATE SHM_CPP
Not validating SHM_CPP 0000 at FFFFFFFF.7F2BA140, VALID flag clear

Not validating SHM_CPP 0001 at FFFFFFFF.7F2BA380, VALID flag clear

Not validating SHM_CPP 0002 at FFFFFFFF.7F2BA5C0, VALID flag clear

Validating SHM_CPP 0003 at FFFFFFFF.7F2BA800 ...

    Validating counts and ranges in the free page list ...
    ... o.k.

    Not validating the bad page list, list is empty
```

```
Not validating the untested page list, list is empty
```

```
Not validating SHM_CPP 0004 at FFFFFFFF.7F2BAA40, VALID flag clear
```

```
Not validating SHM_CPP 0005 at FFFFFFFF.7F2BAC80, VALID flag clear
```

```
Not validating SHM_CPP 0006 at FFFFFFFF.7F2BAEC0, VALID flag clear
```

This example shows the default output for the `VALIDATE SHM_CPP` command.

4.89. VALIDATE TQEIDX

Validates all the data structures associated with timer queue entry index (TQEIDX) structures.

Format

```
VALIDATE TQEIDX
```

Parameters

None.

Qualifiers

None.

Description

TQEs are linked together with index blocks that point to TQEs or to another level of index block. `VALIDATE TQEIDX` checks that all the index blocks are correctly linked together.

Examples

```
SDA> VALIDATE TQEIDX
Validating time index buckets...
... o.k.
Validating ID index buckets...
... o.k.
Validating 1st time...
... o.k.
Validating counts...
... o.k.
```

This example shows the output from a successful `VALIDATE TQEIDX` command.

4.90. WAIT

Causes SDA to wait for the specified length of time.

Format

```
WAIT [wait-time]
```


Parameter

wait-time

The wait time is given as a delta time: [[hh:]mm:]ss[.t[h]]. If omitted, the default wait time is one second.

Qualifiers

None.

Description

The WAIT command can be used in command procedures such as scripts collecting performance data. See Chapter 8 for a sample procedure.

Examples

```
SDA> WAIT 00:00:15
```

SDA waits 15 seconds before accepting the next command.

Chapter 5. SDA CLUE Extension

The SDA CLUE command invokes the Crash Log Utility Extractor, which captures specific crash dump information and, upon system reboot, preserves it in a file with the following naming scheme:

```
CLUE$nodename_ddmmyy_hhmm.LIS
```

You enter CLUE extension commands at the SDA prompt. For example:

```
SDA> CLUE CONFIG
```

You can get full help on CLUE by entering `HELP CLUE` at the `SDA>` prompt.

5.1. Overview of SDA CLUE Extension

SDA CLUE (Crash Log Utility Extractor) commands automate the analysis of crash dumps and maintain a history of all fatal bugchecks on either a standalone or cluster system. You can use SDA CLUE commands in conjunction with SDA to collect and decode additional dump file information not readily accessible through standard SDA commands. SDA CLUE extension commands can summarize information provided by certain standard SDA commands and provide additional detail for some SDA commands. For example, SDA CLUE extension commands can quickly provide detailed extended QIO processor (XQP) summaries. You can also use SDA CLUE commands interactively on a running system to help identify performance problems.

You can use all CLUE commands when analyzing crash dumps; the only CLUE commands that are not allowed when analyzing a running system are `CLUE CRASH`, `CLUE ERRLOG`, `CLUE HISTORY`, and `CLUE STACK`.

When you reboot the system after a system failure, you automatically invoke SDA by default. To facilitate better crash dump analysis, SDA CLUE commands automatically capture and archive summary dump file information in a CLUE listing file.

A startup command procedure initiates commands that do the following:

- Invoke SDA
- Issue an SDA `CLUE HISTORY` command
- Create a listing file called `CLUE$nodename_ddmmyy_hhmm.LIS`

The `CLUE HISTORY` command adds a one-line summary entry to a history file and saves the following output from SDA CLUE commands in the listing file:

- Crash dump summary information
- System configuration
- Stack decoder
- Page and swap files
- Memory management statistics
- Process DCL recall buffer

- Active XQP processes
- XQP cache header

The contents of this CLUE list file can help you analyze a system failure. If these files accumulate more space than the threshold allows (default is 5000 blocks), the oldest files are deleted until the threshold limit is reached. You can also customize this threshold using the CLUE\$MAX_BLOCKS logical name.

For additional information on the contents of the CLUE listing file, see the reference section on CLUE HISTORY.

It is important to remember that CLUE\$nodename_ddmmy_hhmm.LIS contains only an overview of the crash dump and does not always contain enough information to determine the cause of the crash. The dump itself should always be saved using the procedures described in Section 2.2.2 and Section 2.2.4.

To inhibit the running of CLUE at system startup, define the logical CLUE\$INHIBIT in the SYLOGICALS.COM file as /SYS TRUE.

5.2. Displaying Data with CLUE

To invoke a CLUE command, enter the command at the SDA prompt. For example:

```
SDA> CLUE CONFIG
```

5.3. Using CLUE with DOSD

DOSD (Dump Off System Disk) allows you to write the system dump file to a device other than the system disk. For SDA CLUE to be able to correctly find the dump file to be analyzed after a system crash, you need to perform the following steps:

1. Modify the command procedure SY\$MANAGER:SYCONFIG.COM to add the system logical name CLUE\$DOSD_DEVICE to point to the device where the dump file resides. You need to supply only the physical or logical device name without a file specification.
2. Modify the command procedure SY\$MANAGER:SYCONFIG.COM to mount systemwide the device where the dump file resides. Otherwise, SDA CLUE cannot access and analyze the dump file.

In the following example, the dump file has been placed on device \$3\$DUA25, which has the label DMP\$DEV. You need to add the following commands to SY\$MANAGER:SYCONFIG.COM:

```
$ MOUNT/SYSTEM/NOASSIST $3$DUA25: DMP$DEV DMP$DEV
$ DEFINE/SYSTEM CLUE$DOSD_DEVICE DMP$DEV
```

5.4. SDA CLUE Extension Commands

The following pages describe the SDA CLUE extension commands.

5.4.1. CLUE CALL_FRAME (Alpha Only)

Displays key information, such as the PC of the caller, from the active call frames at the time of the crash.

Format

```
CLUE CALL_FRAME [/CPU [cpu-id|ALL]
| /PROCESS [/ADDRESS=n | INDEX=n
| /IDENTIFICATION=n | process-name | ALL]]
```

Parameters

ALL

When used with /CPU, it requests information about all CPUs in the system. When used with /PROCESS, it requests information about all processes that exist in the system.

cpu-id

When used with /CPU, it gives the number of the CPU for which information is to be displayed. Use of the **cpu-id** parameter causes the CLUE CALL_FRAME command to perform an implicit SET CPU command, making the indicated CPU the current CPU for subsequent SDA commands.

process-name

When used with /PROCESS, it gives the name of the process for which information is to be displayed. Use of the **process-name** parameter, the /ADDRESS qualifier, the /INDEX qualifier, or the /IDENTIFICATION qualifier causes the CLUE CALL_FRAME command to perform an implicit SET PROCESS command, making the indicated process the current process for subsequent SDA commands. You can determine the names of the processes in the system by issuing a SHOW SUMMARY command.

The **process-name** can contain up to 15 letters and numerals, including the underscore (_) and dollar sign (\$). If it contains any other characters, you must enclose the **process-name** in quotation marks (" ").

Qualifiers

/ADDRESS=*n*

Specifies the PCB address of the desired process when used with CLUE CALL_FRAME/PROCESS.

/CPU [*cpu-id*|ALL]

Indicates that the call frame for a CPU is required. Specify the CPU by its number or use ALL to indicate all CPUs.

/IDENTIFICATION=*n*

Specifies the identification of the desired process when used with CLUE CALL_FRAME/PROCESS.

/INDEX=*n*

Specifies the index of the desired process when used with CLUE CALL_FRAME/PROCESS.

/PROCESS [process-name|ALL]

Indicates that the call frame for a process is required. The process should be specified with either one of the qualifiers /ADDRESS, /IDENTIFICATION, or /INDEX, or by its name, or by using ALL to indicate all processes.

Description

The CLUE CALL_FRAME command displays call chain information for a process or a CPU. The process context calls work on both the running system and dump file; the CPU context calls only on dump files.

If neither /CPU nor /PROCESS is specified, the parameter (CPU-id or process-name) is ignored and the call frame for the SDA current process is displayed.

Examples

1. SDA> CLUE CALL/PROCESS IPCACP

```
Call Chain: Process index: 000B Process name: IPCACP PCB: 8136EF00
-----
Procedure Frame Procedure Entry Return Address
-----
-----
7FFA1CA0 Null 800C8C90 SCH$WAIT_PROC_C
7FFA1D00 Stack 800D9250 SYS$HIBER_C 0003045C
IPCACP+0003045C
7FFA1D50 Stack 00030050 IPCACP+00030050 800D11C8 EXE
$CMKRNLC+000D8
7FFA1E60 Null 800B6120 EXE$BLDPKTSWPR_C
7FFA1E78 Null 800B6120 EXE$BLDPKTSWPR_C
7FFA1EC0 Null 80248120 NSA$CHECK_PRIVILEGE_C
7FFA1F00 Null 80084640 EXE$CMODEXECX_C
7FFA1F70 Stack 800D10F0 EXE$CMKRNLC 80084CC8 EXE
$CMODKRNLC+00198
7B01FAB0 Stack 00030010 IPCACP+00030010 83EA3454 SYS
$IMGSTAC+00154
7B01FB10 Stack 83EA3300 SYS$IMGSTAC 83D99CC4 EXE
$PROC_IMGACT_C+00384
7B01FBA0 Stack 83D99BA0 EXE$PROC_IMGACT_C+00260 83D99B9C EXE
$PROC_IMGACT_C+0025C
```

In this example, the CLUE CALL_FRAME command displays the call frame from the process IPCACP.

2. SDA> CLUE CALL/CPU ALL

```
Call Chain: Process index: 0000 Process name: NULL PCB: 827377C0
(CPU 0)
-----
Procedure Frame Procedure Entry Return Address
-----
-----
8F629D28 Null 80205E00 SYS$SCS+05E00
8F629D68 Null 8020A850 SCS$REC_MSGREC_C
8F629D98 Null 914A5340 SYS$PBDRIVER+07340
8F629DB8 Null 914A4FD0 SYS$PBDRIVER+06FD0
8F629DE0 Stack 914AACF0 SYS$PBDRIVER+0CCF0 914AE5CC SYS
$PBDRIVER+105CC
```

```

8F629E50 Stack 914AE418 SYS$PBDRIVER+10418 800503B0
EXE_STD$QUEUE_FORK_C+00350
8F629F88 Null 800E95F4 SCH$WAIT_ANY_MODE_C
8F629FD0 Stack 800D0F80 SCH$IDLE_C 800E92D0 SCH
$INTERRUPT+00BB0
Call Chain: Process index: 0000 Process name: NULL PCB: 827377C0
(CPU 2)
-----
Procedure Frame Procedure Entry Return Address
-----
90FCBF88 Null 800E95F4 SCH$WAIT_ANY_MODE_C
90FCBFC8 Null 800E95F4 SCH$WAIT_ANY_MODE_C
90FCBFD0 Stack 800D0F80 SCH$IDLE_C 800E92D0 SCH
$INTERRUPT+00BB0
Call Chain: Process index: 0000 Process name: NULL PCB: 827377C0
(CPU 6)
-----
Procedure Frame Procedure Entry Return Address
-----
90FCBF88 Null 800E95FA SCH$WAIT_ANY_MORE_c
90FD9F88 Null 800E95F4 SCH$WAIT_ANY_MODE_C
90FD9FD0 Stack 800D0F80 SCH$IDLE_C 800E92D0 SCH
$INTERRUPT+00BB0

```

In this example, CLUE/CPU ALL shows the call frame for all CPUs.

5.4.2. CLUE CLEANUP

Performs housekeeping operations to conserve disk space.

Format

CLUE CLEANUP

Parameters

None.

Qualifiers

None.

Description

CLUE CLEANUP performs housekeeping operations to conserve disk space. To avoid filling up the system disk with listing files generated by CLUE, CLUE CLEANUP is run during system startup to check the overall disk space used by all CLUE\$*.LIS files.

If the CLUE\$COLLECT:CLUE\$*.LIS files occupy more space than the logical CLUE\$MAX_BLOCKS allows, then the oldest files are deleted until the threshold is reached. If this logical name is not defined, a default value of 5,000 disk blocks is assumed. A value of zero disables housekeeping and no check on the disk space is performed.

Examples

1. SDA> CLUE CLEANUP

```
%CLUE-I-CLEANUP, housekeeping started...
%CLUE-I-MAXBLOCK, maximum blocks allowed 5000 blocks
%CLUE-I-STAT, total of 4 CLUE files, 192 blocks.
```

In this example, the CLUE CLEANUP command displays that the total number of blocks of disk space used by CLUE files does not exceed the maximum number of blocks allowed. No files are deleted.

5.4.3. CLUE CONFIG

Displays the system, memory, and device configurations.

Format

```
CLUE CONFIG
```

Parameters

None.

Qualifiers

/ADAPTER

Displays only the part of the system configuration that contains information about the adapters and devices on the system.

/CPU

Displays only the part of the system configuration that contains information about the CPUs.

/MEMORY

Displays only the part of the system configuration that contains information about the layout of physical memory.

Description

CLUE CONFIG displays the system, memory, and device configurations. If no qualifier is specified, the entire system configuration is displayed (memory, CPUs, adapters, and devices), plus additional system information.

5.4.4. CLUE CRASH

Displays a crash dump summary.

Format

```
CLUE CRASH
```

Parameters

None.

Qualifiers

None.

Description

CLUE CRASH displays a crash dump summary, which includes the following items:

- Bugcheck type
- Current process and image
- Failing PC and PS
- Executive image section name and offset
- General registers
- Failing instructions
- Exception frame, signal and mechanism arrays (if available)
- CPU state information (spinlock related bugchecks only)

Examples

```
SDA> CLUE CRASH
Crash Time:          30-AUG-1996 13:13:46.83
Bugcheck Type:      SSRVEXCEPT, Unexpected system service exception
Node:               SWPCTX (Standalone)
CPU Type:           DEC 3000 Model 400
VMS Version:        X6AF-FT2
Current Process:    SYSTEM
Current Image:      $31$DKB0:[SYS0.] [SYSMGR]X.EXE;1
Failing PC:         00000000.00030078      SYS$K_VERSION_01+00078
Failing PS:         00000000.00000003
Module:             X
Offset:             00030078

Boot Time:          30-AUG-1996 09:06:22.00
System Uptime:      0 04:07:24.83
Crash/Primary CPU: 00/00
System/CPU Type:    0402
Saved Processes:    18
Pagesize:          8 KByte (8192 bytes)
Physical Memory:    64 MByte (8192 PFNs, contiguous memory)
Dumpfile Pagelets: 98861 blocks
Dump Flags:         olddump, writecomp, errlogcomp, dump_style
Dump Type:          raw, selective
EXE$GL_FLAGS:      poolpging, init, bugdump
Paging Files:      1 Pagefile and 1 Swapfile installed

Stack Pointers:
KSP = 00000000.7FFA1C98   ESP = 00000000.7FFA6000   SSP = 00000000.7FFAC100
USP = 00000000.7AFFBAD0

General Registers:
R0 = 00000000.00000000   R1 = 00000000.7FFA1EB8   R2 = FFFFFFFF.80D0E6C0
R3 = FFFFFFFF.80C63460   R4 = FFFFFFFF.80D12740   R5 = 00000000.000000C8
R6 = 00000000.00030038   R7 = 00000000.7FFA1FC0   R8 = 00000000.7FFAC208
R9 = 00000000.7FFAC410   R10 = 00000000.7FFAD238  R11 = 00000000.7FFCE3E0
R12 = 00000000.00000000  R13 = FFFFFFFF.80C6EB60  R14 = 00000000.00000000
R15 = 00000000.009A79FD  R16 = 00000000.000003C4  R17 = 00000000.7FFA1D40
```

```

R18 = FFFFFFFF.80C05C38   R19 = 00000000.00000000   R20 = 00000000.7FFA1F50
R21 = 00000000.00000000   R22 = 00000000.00000001   R23 = 00000000.7FFF03C8
R24 = 00000000.7FFF0040   AI  = 00000000.00000003   RA  = FFFFFFFF.82A21080
PV  = FFFFFFFF.829CF010   R28 = FFFFFFFF.8004B6DC   FP  = 00000000.7FFA1CA0
PC  = FFFFFFFF.82A210B4   PS  = 18000000.00000000

```

Exception Frame:

```

R2  = 00000000.00000003   R3  = FFFFFFFF.80C63460   R4  = FFFFFFFF.80D12740
R5  = 00000000.000000C8   R6  = 00000000.00030038   R7  = 00000000.7FFA1FC0
PC  = 00000000.00030078   PS  = 00000000.00000003

```

Signal Array:

```

Arg Count    = 00000005
Condition    = 0000000C
Argument #2  = 00010000
Argument #3  = 00000000
Argument #4  = 00030078
Argument #5  = 00000003

```

64-bit Signal Array:

```

Arg Count    = 00000005
Condition    = 00000000.0000000C
Argument #2  = 00000000.00010000
Argument #3  = 00000000.00000000
Argument #4  = 00000000.00030078
Argument #5  = 00000000.00000003

```

Mechanism Array:

```

Arguments    = 0000002C   Establisher FP = 00000000.7AFFBAD0
Flags        = 00000000   Exception FP  = 00000000.7FFA1F00
Depth       = FFFFFFFD   Signal Array  = 00000000.7FFA1EB8
Handler Data = 00000000.00000000   Signal64 Array = 00000000.7FFA1ED0
R0  = 00000000.00020000   R1  = 00000000.00000000   R16 = 00000000.00020004
R17 = 00000000.00010050   R18 = FFFFFFFF.FFFFFFFF   R19 = 00000000.00000000
R20 = 00000000.7FFA1F50   R21 = 00000000.00000000   R22 = 00000000.00010050
R23 = 00000000.00000000   R24 = 00000000.00010051   R25 = 00000000.00000000
R26 = FFFFFFFF.8010ACA4   R27 = 00000000.00010050   R28 = 00000000.00000000

```

System Registers:

```

Page Table Base Register (PTBR)          00000000.00001136
Processor Base Register (PRBR)          FFFFFFFF.80D0E000
Privileged Context Block Base (PCBB)    00000000.003FE080
System Control Block Base (SCBB)        00000000.000001DC
Software Interrupt Summary Register (SISR) 00000000.00000000
Address Space Number (ASN)              00000000.0000002F
AST Summary / AST Enable (ASTSR_ASTEN)  00000000.0000000F
Floating-Point Enable (FEN)             00000000.00000000
Interrupt Priority Level (IPL)           00000000.00000000
Machine Check Error Summary (MCES)      00000000.00000000
Virtual Page Table Base Register (VPTB)  FFFFFFFC.00000000

```

Failing Instruction:

```

SYS$K_VERSION_01+00078:      LDL          R28, (R28)

```

Instruction Stream (last 20 instructions):

```

SYS$K_VERSION_01+00028:      LDQ          R16, #X0030 (R13)
SYS$K_VERSION_01+0002C:      LDQ          R27, #X0048 (R13)
SYS$K_VERSION_01+00030:      LDA          R17, (R28)
SYS$K_VERSION_01+00034:      JSR          R26, (R26)
SYS$K_VERSION_01+00038:      LDQ          R26, #X0038 (R13)
SYS$K_VERSION_01+0003C:      BIS          R31, SP, SP
SYS$K_VERSION_01+00040:      BIS          R31, R26, R0
SYS$K_VERSION_01+00044:      BIS          R31, FP, SP
SYS$K_VERSION_01+00048:      LDQ          R28, #X0008 (SP)
SYS$K_VERSION_01+0004C:      LDQ          R13, #X0010 (SP)
SYS$K_VERSION_01+00050:      LDQ          FP, #X0018 (SP)

```

SYS\$K_VERSION_01+00054:	LDA	SP, #X0020 (SP)
SYS\$K_VERSION_01+00058:	RET	R31, (R28)
SYS\$K_VERSION_01+0005C:	BIS	R31, R31, R31
SYS\$K_VERSION_01+00060:	LDA	SP, #XFFE0 (SP)
SYS\$K_VERSION_01+00064:	STQ	FP, #X0018 (SP)
SYS\$K_VERSION_01+00068:	STQ	R27, (SP)
SYS\$K_VERSION_01+0006C:	BIS	R31, SP, FP
SYS\$K_VERSION_01+00070:	STQ	R26, #X0010 (SP)
SYS\$K_VERSION_01+00074:	LDA	R28, (R31)
SYS\$K_VERSION_01+00078:	LDL	R28, (R28)
SYS\$K_VERSION_01+0007C:	BEQ	R28, #X000007
SYS\$K_VERSION_01+00080:	LDQ	R26, #XFFE8 (R27)
SYS\$K_VERSION_01+00084:	BIS	R31, R26, R0
SYS\$K_VERSION_01+00088:	BIS	R31, FP, SP

5.4.5. CLUE ERRLOG

Extracts the error log buffers from the dump file and places them into the binary file called CLUE\$ERRLOG.SYS.

Format

CLUE ERRLOG [/OLD]

Parameters

None.

Qualifier

/OLD

Dumps the errorlog buffers into a file using the old errorlog format. The default action, if /OLD is not specified, is to dump the errorlog buffers in the common event header format.

Description

CLUE ERRLOG extracts the error log buffers from the dump file and places them into the binary file called CLUE\$ERRLOG.SYS.

These buffers contain messages not yet written to the error log file at the time of the failure. When you analyze a failure on the same system on which it occurred, you can run the Error Log utility on the actual error log file to see these error log messages. When analyzing a failure from another system, use the CLUE ERRLOG command to create a file containing the failing system's error log messages just prior to the failure. System failures are often triggered by hardware problems, so determining what, if any, hardware errors occurred prior to the failure can help you troubleshoot a failure.

You can define the logical CLUE\$ERRLOG to any file specification if you want error log information written to a file other than CLUE\$ERRLOG.SYS.

Note

You need at least DECevent V2.9 to analyze the new common event header (CEH) format file. The old format file can be analyzed by ANALYZE/ERROR or any version of DECevent.

Examples

```
SDA> CLUE ERRLOG
```

Sequence	Date	Time
-----	-----	-----
128	11-MAY-1994	00:39:31.30
129	11-MAY-1994	00:39:32.12
130	11-MAY-1994	00:39:44.83
131	11-MAY-1994	00:44:38.97 * Crash Entry

In addition to writing the error log buffers into CLUE\$ERRLOG.SYS, the CLUE ERRLOG command displays the sequence, date, and time of each error log buffer extracted from the dump file.

5.4.6. CLUE FRU

Outputs the Field Replacement Unit (FRU) table to a file for display by DECEvent.

Format

```
CLUE FRU
```

Parameters

None.

Qualifiers

None.

Description

The FRU command extracts the FRU table into an output file (CLUE\$FRU.SYS), which can then be displayed by DECEvent. This command works on the running system, as well as on dump files.

5.4.7. CLUE HISTORY

Updates history file and generates crash dump summary output.

Format

```
CLUE HISTORY [/qualifier]
```

Parameters

None.

Qualifier

```
/OVERDRIVE
```

Allows execution of this command even if the dump file has already been analyzed (DMP \$V_OLDDUMP bit set).

Description

This command updates the history file pointed to by the logical name `CLUE$HISTORY` with a one-line entry and the major crash dump summary information. If `CLUE$HISTORY` is not defined, a file `CLUE$HISTORY.DAT` in your default directory will be created.

In addition, a listing file with summary information about the system failure is created in the directory pointed to by `CLUE$COLLECT`. The file name is of the form `CLUE$node_ddmmyy_hhmm.LIS` where the timestamp (*hhmm*) corresponds to the system failure time and not the time when the file was created.

The listing file contains summary information collected from the following SDA commands:

- `CLUE CRASH`
- `CLUE CONFIG`
- `CLUE MEMORY/FILES`
- `CLUE MEMORY/STATISTIC`
- `CLUE PROCESS/RECALL`
- `CLUE XQP/ACTIVE`

Refer to the reference section for each of these commands to see examples of the displayed information.

The logical name `CLUE$FLAG` controls how much information is written to the listing file.

- Bit 0---Include crash dump summary
- Bit 1---Include system configuration
- Bit 2---Include stack decoding information
- Bit 3---Include page and swap file usage
- Bit 4---Include memory management statistics
- Bit 5---Include process DCL recall buffer
- Bit 6---Include active XQP process information
- Bit 7---Include XQP cache header

If this logical name is undefined, all bits are set by default internally and all information is written to the listing file. If the value is zero, no listing file is generated. The value has to be supplied in hexadecimal form (for example, `DEFINE CLUE$FLAG 81` will include the crash dump summary and the XQP cache header information).

If the logical name `CLUE$SITE_PROC` points to a valid and existing file, it will be executed as the final step of the `CLUE HISTORY` command (for example, automatic saving of the dump file during system startup). If used, this file should contain only valid SDA commands.

Refer to Section 2.2.4 for more information on site-specific command files.

5.4.8. CLUE MCHK

This command is obsolete.

Format

CLUE MCHK

Parameters

None.

Qualifiers

None.

Description

The CLUE MCMK command has been withdrawn. Issuing the command produces the following output, explaining the correct way to obtain MACHINECHECK information from a crash dump.

Please use the following commands in order to extract the errorlog buffers from the dumpfile header and analyze the machine check entry:

```
$ analyze/crash sys$system:sysdump.dmp
SDA> clue errlog
SDA> exit
$ diagnose clue$errlog
```

5.4.9. CLUE MEMORY

Displays memory- and pool-related information.

Format

CLUE MEMORY [/qualifier[,...]]

Parameters

None.

Qualifiers

/FILES

Displays information about page and swap file usage.

/FREE

Validates and displays dynamic nonpaged free packet list queue. (See also /FULL.)

/FULL

Ignored except when used with /FREE or /GH. When used with /FREE, the first 16 bytes of each entry on the free packet list is displayed. When used with /GH, a list of the images that use each granularity hint region is displayed.

/GH

Displays information about the granularity hint regions. (See also /FULL.)

/LAYOUT

Decodes and displays much of the system virtual address space layout.

/LOOKASIDE

Validates the lookaside list queue heads and counts the elements for each list.

/STATISTIC

Displays systemwide performance data such as page fault, I/O, pool, lock manager, MSCP, and file system cache.

Description

The CLUE MEMORY command displays memory- and pool-related information.

Examples

1. SDA> CLUE MEMORY/FILES
Paging File Usage (blocks):

```

-----
Swapfile (Index 1)                               Device           DKA0:
  PFL Address      FFFFFFFF.81531340      UCB Address
  FFFFFFFF.814AAF00
  Free Blocks              44288      Bitmap
  FFFFFFFF.815313E0
  Total Size (blocks)      44288      Flags
  inited,swap_file
  Total Write Count              0      Total Read Count
  0
  Smallest Chunk (pages)      2768      Largest Chunk (pages)
  2768
  Chunks GEQ 64 Pages              1      Chunks LT 64 Pages
  0

Pagefile (Index 254)                             Device           DKA0:
  PFL Address      FFFFFFFF.8152E440      UCB Address
  FFFFFFFF.814AAF00
  Free Blocks              1056768      Bitmap
  FFFFFFFF.6FB16008
  Total Size (blocks)      1056768      Flags
  inited
  Total Write Count              0      Total Read Count
  0
  Smallest Chunk (pages)      66048      Largest Chunk (pages)
  66048
  Chunks GEQ 64 Pages              1      Chunks LT 64 Pages
  0

Summary:  1 Pagefile and 1 Swapfile installed

Total Size of all Swap Files:              44288 blocks
Total Size of all Paging Files:            1056768 blocks
Total Committed Paging File Usage:        344576 blocks

```

This example shows the display produced by the CLUE MEMORY/FILES command.

```
2. SDA> CLUE MEMORY/FREE/FULL
Non-Paged Dynamic Storage Pool - Variable Free Packet Queue:
-----
CLASSDR FFFFFFFF.80D157C0 : 64646464 64646464 00000040 80D164C0
ÀdÑ.@...dddddddd
CLASSDR FFFFFFFF.80D164C0 : 64646464 64646464 00000080 80D17200
.rÑ.....dddddddd
CLASSDR FFFFFFFF.80D17200 : 64646464 64646464 00000080 80D21AC0
À.Ò.....dddddddd
CLASSDR FFFFFFFF.80D21AC0 : 64646464 64646464 00000080 80D228C0
À(Ò.....dddddddd
VCC FFFFFFFF.80D228C0 : 801CA5E8 026F0040 00000040 80D23E40
@>Ò.@...@.o.è¥..
CLASSDR FFFFFFFF.80D23E40 : 64646464 64646464 00000040 80D24040
@@Ò.@...dddddddd
CLASSDR FFFFFFFF.80D24040 : 64646464 64646464 00000040 80D26FC0
ÀoÒ.@...dddddddd
CLASSDR FFFFFFFF.80D26FC0 : 64646464 64646464 00000080 80D274C0
ÀtÒ.....dddddddd
CLASSDR FFFFFFFF.80D274C0 : 64646464 64646464 00000040 80D2E200
.âÒ.@...dddddddd
CLASSDR FFFFFFFF.80D2E200 : 64646464 64646464 00000080 80D2E440
@äÒ.....dddddddd
CLASSDR FFFFFFFF.80D2E440 : 64646464 64646464 00000040 80D2F000
.Ò.@...dddddddd
CLASSDR FFFFFFFF.80D2F000 : 64646464 64646464 00000080 80D2F400
.ôÒ.....dddddddd
.
.
.
CLASSDR FFFFFFFF.80E91D40 : 64646464 64646464 00000500 80E983C0
À.é.....dddddddd
CLASSDR FFFFFFFF.80E983C0 : 64646464 64646464 00031C40 00000000
....@...dddddddd
Free Packet Queue, Status: Valid, 174 elements
Largest free chunk: 00031C40 (hex) 203840 (dec) bytes
Total free dynamic space: 0003D740 (hex) 251712 (dec) bytes
```

The CLUE MEMORY/FREE/FULL command validates and displays dynamic nonpaged free packet list queue.

```
3. SDA> CLUE MEMORY/GH/FULL
Granularity Hint Regions - Huge Pages:
-----

Execlet Code Region
Pages/Slices
Base/End VA FFFFFFFF.80000000 FFFFFFFF.80356000 Current Size
427/ 427
Base/End PA 00000000.00400000 00000000.00756000 Free
/ 0
Total Size 00000000.00356000 3.3 MB In Use
/ 427
Bitmap VA/Size FFFFFFFF.80D17CC0 00000000.00000040 Initial Size
512/ 512
```



```

Slice Size      00000000.00002000          Released
85/      85
Next free Slice 00000000.000001AB

```

Image Length	Base	End
SYS\$PUBLIC_VECTORS 00001A00	FFFFFFFF.80000000	FFFFFFFF.80001A00
SYS\$BASE_IMAGE 0000B400	FFFFFFFF.80002000	FFFFFFFF.8000D400
SYS\$CNBTDRIVER 00001000	FFFFFFFF.8000E000	FFFFFFFF.8000F000
SYS\$NISCA_BTDRIVER 0000FA00	FFFFFFFF.80010000	FFFFFFFF.8001FA00
SYS\$ESBTDRIVER 00002400	FFFFFFFF.80020000	FFFFFFFF.80022400
SYS\$OPDRIVER 00003C00	FFFFFFFF.80024000	FFFFFFFF.80027C00
SYSTEM_DEBUG 00028200	FFFFFFFF.80028000	FFFFFFFF.80050200
SYSTEM_PRIMITIVES 00037000	FFFFFFFF.80052000	FFFFFFFF.80089000
SYSTEM_SYNCHRONIZATION 0000B400	FFFFFFFF.8008A000	FFFFFFFF.80095400
ERRORLOG 00003200	FFFFFFFF.80096000	FFFFFFFF.80099200
SYS\$CPU_ROUTINES_0402 00009A00	FFFFFFFF.8009A000	FFFFFFFF.800A3A00
EXCEPTION_MON 00018800	FFFFFFFF.800A4000	FFFFFFFF.800BC800
IO_ROUTINES_MON 00024000	FFFFFFFF.800BE000	FFFFFFFF.800E2000
SYSDEVICE 00003C00	FFFFFFFF.800E2000	FFFFFFFF.800E5C00
PROCESS_MANAGEMENT_MON 00025000	FFFFFFFF.800E6000	FFFFFFFF.8010B000
SYS\$VM 0005B200	FFFFFFFF.8010C000	FFFFFFFF.80167200
SHELL8K 00001200	FFFFFFFF.80168000	FFFFFFFF.80169200
LOCKING 00011E00	FFFFFFFF.8016A000	FFFFFFFF.8017BE00
MESSAGE_ROUTINES 00006A00	FFFFFFFF.8017C000	FFFFFFFF.80182A00
LOGICAL_NAMES 00002C00	FFFFFFFF.80184000	FFFFFFFF.80186C00
F11BXQP 00008400	FFFFFFFF.80188000	FFFFFFFF.80190400
SYSLICENSE 00000400	FFFFFFFF.80192000	FFFFFFFF.80192400
IMAGE_MANAGEMENT 00003A00	FFFFFFFF.80194000	FFFFFFFF.80197A00
SECURITY 00008E00	FFFFFFFF.80198000	FFFFFFFF.801A0E00
SYSGETSYI 00001A00	FFFFFFFF.801A2000	FFFFFFFF.801A3A00
SYS\$TRANSACTION_SERVICES 00021000	FFFFFFFF.801A4000	FFFFFFFF.801C5000

SYS\$UTC_SERVICES	FFFFFFFF.801C6000	FFFFFFFF.801C7000
00001000		
SYS\$VCC_MON	FFFFFFFF.801C8000	FFFFFFFF.801D4E00
0000CE00		
SYS\$IPC_SERVICES	FFFFFFFF.801D6000	FFFFFFFF.80214A00
0003EA00		
SYS\$DR_DYN	FFFFFFFF.80216000	FFFFFFFF.80219200
00003200		
SYS\$MME_SERVICES	FFFFFFFF.8021A000	FFFFFFFF.8021B000
00001000		
SYS\$TTDRIVER	FFFFFFFF.8021C000	FFFFFFFF.8022FE00
00013E00		
SYS\$PKCDRIVER	FFFFFFFF.80230000	FFFFFFFF.80240400
00010400		
SYS\$DKDRIVER	FFFFFFFF.80242000	FFFFFFFF.80251600
0000F600		
RMS	FFFFFFFF.80252000	FFFFFFFF.802C5E00
00073E00		
SYS\$GXADRIVER	FFFFFFFF.802C6000	FFFFFFFF.802CE000
00008000		
SYS\$ECDRIVER	FFFFFFFF.802CE000	FFFFFFFF.802D1000
00003000		
SYS\$LAN	FFFFFFFF.802D2000	FFFFFFFF.802D8E00
00006E00		
SYS\$LAN_CSMACD	FFFFFFFF.802DA000	FFFFFFFF.802E6600
0000C600		
SYS\$MKDRIVER	FFFFFFFF.802E8000	FFFFFFFF.802F1C00
00009C00		
SYS\$YRDRIVER	FFFFFFFF.802F2000	FFFFFFFF.802F9600
00007600		
SYS\$SODRIVER	FFFFFFFF.802FA000	FFFFFFFF.802FF000
00005000		
SYS\$INDRIVER	FFFFFFFF.80300000	FFFFFFFF.8030EA00
0000EA00		
NETDRIVER	FFFFFFFF.80310000	FFFFFFFF.80310200
00000200		
NETDRIVER	FFFFFFFF.80312000	FFFFFFFF.80329E00
00017E00		
SYS\$IMDRIVER	FFFFFFFF.8032A000	FFFFFFFF.8032EA00
00004A00		
SYS\$IKDRIVER	FFFFFFFF.80330000	FFFFFFFF.8033AC00
0000AC00		
NDDRIVER	FFFFFFFF.8033C000	FFFFFFFF.8033F800
00003800		
SYS\$WSDRIVER	FFFFFFFF.80340000	FFFFFFFF.80341600
00001600		
SYS\$CTDRIVER	FFFFFFFF.80342000	FFFFFFFF.8034D200
0000B200		
SYS\$RTTDRIVER	FFFFFFFF.8034E000	FFFFFFFF.80351800
00003800		
SYS\$FTDRIVER	FFFFFFFF.80352000	FFFFFFFF.80354200
00002200		

Execlet Data Region

Pages/Slices

Base/End VA FFFFFFFF.80C00000 FFFFFFFF.80CC0000 Current Size
96/ 1536

```

Base/End PA      00000000.00800000 00000000.008C0000 Free
/      11
Total Size      00000000.000C0000          0.7 MB In Use
/      1525
Bitmap VA/Size  FFFFFFFF.80D17D00 00000000.00000100 Initial Size
128/ 2048
Slice Size      00000000.00000200          Released
32/ 512
Next free Slice 00000000.000005F5

```

Image Length	Base	End
SYS\$PUBLIC_VECTORS 00005000	FFFFFFFF.80C00000	FFFFFFFF.80C05000
SYS\$BASE_IMAGE 00020E00	FFFFFFFF.80C05000	FFFFFFFF.80C25E00
SYS\$CNBTDRIVER 00000400	FFFFFFFF.80C25E00	FFFFFFFF.80C26200
SYS\$NISCA_BTDRIVER 00003200	FFFFFFFF.80C26200	FFFFFFFF.80C29400
SYS\$ESBTDRIVER 00000400	FFFFFFFF.80C29400	FFFFFFFF.80C29800
SYS\$OPDRIVER 00000A00	FFFFFFFF.80C29800	FFFFFFFF.80C2A200
SYSTEM_DEBUG 00024200	FFFFFFFF.80C2A200	FFFFFFFF.80C4E400
SYSTEM_PRIMITIVES 00009E00	FFFFFFFF.80C4E400	FFFFFFFF.80C58200
SYSTEM_SYNCHRONIZATION 00001E00	FFFFFFFF.80C58200	FFFFFFFF.80C5A000
ERRORLOG 00000600	FFFFFFFF.80C5A000	FFFFFFFF.80C5A600
SYS\$CPU_ROUTINES_0402 00002400	FFFFFFFF.80C5A600	FFFFFFFF.80C5CA00
EXCEPTION_MON 00008200	FFFFFFFF.80C5CA00	FFFFFFFF.80C64C00
IO_ROUTINES_MON 00005E00	FFFFFFFF.80C64C00	FFFFFFFF.80C6AA00
SYSDEVICE 00000C00	FFFFFFFF.80C6AA00	FFFFFFFF.80C6B600
PROCESS_MANAGEMENT_MON 00007000	FFFFFFFF.80C6B600	FFFFFFFF.80C72600
SYS\$VM 00006A00	FFFFFFFF.80C72600	FFFFFFFF.80C79000
SHELL8K 00001000	FFFFFFFF.80C79000	FFFFFFFF.80C7A000
LOCKING 00001A00	FFFFFFFF.80C7A000	FFFFFFFF.80C7BA00
MESSAGE_ROUTINES 00001600	FFFFFFFF.80C7BA00	FFFFFFFF.80C7D000
LOGICAL_NAMES 00001200	FFFFFFFF.80C7D000	FFFFFFFF.80C7E200
F11BXQP 00001800	FFFFFFFF.80C7E200	FFFFFFFF.80C7FA00
SYSLICENSE 00000400	FFFFFFFF.80C7FA00	FFFFFFFF.80C7FE00
IMAGE_MANAGEMENT 00000800	FFFFFFFF.80C7FE00	FFFFFFFF.80C80600

SECURITY	FFFFFFFF.80C80600	FFFFFFFF.80C83000
00002A00		
SYSGETSYI	FFFFFFFF.80C83000	FFFFFFFF.80C83200
00000200		
SYS\$TRANSACTION_SERVICES	FFFFFFFF.80C83200	FFFFFFFF.80C89E00
00006C00		
SYS\$UTC_SERVICES	FFFFFFFF.80C89E00	FFFFFFFF.80C8A200
00000400		
SYS\$VCC_MON	FFFFFFFF.80C8A200	FFFFFFFF.80C8BC00
00001A00		
SYS\$IPC_SERVICES	FFFFFFFF.80C8BC00	FFFFFFFF.80C91000
00005400		
SYSLDR_DYN	FFFFFFFF.80C91000	FFFFFFFF.80C92200
00001200		
SYS\$MME_SERVICES	FFFFFFFF.80C92200	FFFFFFFF.80C92600
00000400		
SYS\$TTDRIVER	FFFFFFFF.80C92600	FFFFFFFF.80C94C00
00002600		
SYS\$PKCDRIVER	FFFFFFFF.80C94C00	FFFFFFFF.80C96A00
00001E00		
SYS\$DKDRIVER	FFFFFFFF.80C96A00	FFFFFFFF.80C99800
00002E00		
RMS	FFFFFFFF.80C99800	FFFFFFFF.80CAAC00
00011400		
RECOVERY_UNIT_SERVICES	FFFFFFFF.80CAAC00	FFFFFFFF.80CAB000
00000400		
SYS\$GXADRIVER	FFFFFFFF.80CAB000	FFFFFFFF.80CAF000
00004000		
SYS\$ECDRIVER	FFFFFFFF.80CAF000	FFFFFFFF.80CAFC00
00000C00		
SYS\$LAN	FFFFFFFF.80CAFC00	FFFFFFFF.80CB0800
00000C00		
SYS\$LAN_CSMACD	FFFFFFFF.80CB0800	FFFFFFFF.80CB1800
00001000		
SYS\$MKDRIVER	FFFFFFFF.80CB1800	FFFFFFFF.80CB3000
00001800		
SYS\$YRDRIVER	FFFFFFFF.80CB3000	FFFFFFFF.80CB3C00
00000C00		
SYS\$SODRIVER	FFFFFFFF.80CB3C00	FFFFFFFF.80CB4E00
00001200		
SYS\$INDRIVER	FFFFFFFF.80CB4E00	FFFFFFFF.80CB5E00
00001000		
NETDRIVER	FFFFFFFF.80CB5E00	FFFFFFFF.80CB8800
00002A00		
SYS\$IMDRIVER	FFFFFFFF.80CB8800	FFFFFFFF.80CB9400
00000C00		
SYS\$IKDRIVER	FFFFFFFF.80CB9400	FFFFFFFF.80CBAA00
00001600		
NDDRIVER	FFFFFFFF.80CBAA00	FFFFFFFF.80CBB400
00000A00		
SYS\$WSDRIVER	FFFFFFFF.80CBB400	FFFFFFFF.80CBC000
00000800		
SYS\$CTDRIVER	FFFFFFFF.80CBC000	FFFFFFFF.80CBD800
00001C00		
SYS\$RTTDRIVER	FFFFFFFF.80CBD800	FFFFFFFF.80CBE200
00000A00		
SYS\$FTDRIVER	FFFFFFFF.80CBE200	FFFFFFFF.80CBEA00
00000800		

```

    11 free Slices                FFFFFFFF.80CBEA00  FFFFFFFF.80CC0000
00001600

```

S0/S1 Executive Data Region

Pages/Slices

```

    Base/End VA      FFFFFFFF.80D00000  FFFFFFFF.80ECA000  Current Size
229/  229
    Base/End PA      00000000.00900000  00000000.00ACA000  Free
/      0
    Total Size       00000000.001CA000                1.7 MB  In Use
/      229
    Bitmap VA/Size   FFFFFFFF.80D17E00  00000000.00000020  Initial Size
229/  229
    Slice Size       00000000.00002000                Released
0/      0
    Next free Slice  00000000.00000007

```

Item	Base	End
System Header	FFFFFFFF.80D00000	FFFFFFFF.80D0A000
Error Log Allocation Buffers	FFFFFFFF.80D0A000	FFFFFFFF.80D0C000
Nonpaged Pool (initial size)	FFFFFFFF.80D0E000	FFFFFFFF.80ECA000

Resident Image Code Region

Pages/Slices

```

    Base/End VA      FFFFFFFF.80400000  FFFFFFFF.80C00000  Current Size
1024/ 1024
    Base/End PA      00000000.00C00000  00000000.01400000  Free
/      223
    Total Size       00000000.00800000                8.0 MB  In Use
/      801
    Bitmap VA/Size   FFFFFFFF.80D17E20  00000000.00000080  Initial Size
1024/ 1024
    Slice Size       00000000.00002000                Released
0/      0
    Next free Slice  00000000.00000321

```

Image	Base	End
LIBRTL	FFFFFFFF.80400000	FFFFFFFF.8049EA00
LIBOTS	FFFFFFFF.804A0000	FFFFFFFF.804AEC00
CMA\$TIS_SHR	FFFFFFFF.804B0000	FFFFFFFF.804B2600
DPML\$SHR	FFFFFFFF.804B4000	FFFFFFFF.8050B600
DECC\$SHR	FFFFFFFF.8050C000	FFFFFFFF.80657000
SECURESHRP	FFFFFFFF.80658000	FFFFFFFF.80676000
SECURESHR	FFFFFFFF.80676000	FFFFFFFF.8068C000
SECURESHR	FFFFFFFF.8068C000	FFFFFFFF.8068C200

```

LBRSHR                FFFFFFFF.8068E000  FFFFFFFF.806A3E00
00015E00
DECW$TRANSPORT_COMMON FFFFFFFF.806A4000  FFFFFFFF.806B0C00
0000CC00
CDE$UNIX_ROUTINES    FFFFFFFF.806B2000  FFFFFFFF.806C1E00
0000FE00
DECW$XLIBSHR         FFFFFFFF.806C2000  FFFFFFFF.80781C00
000BFC00
DECW$XTLIBSHRR5      FFFFFFFF.80782000  FFFFFFFF.807C7600
00045600
DECW$XMLIBSHR12      FFFFFFFF.807C8000  FFFFFFFF.8096AE00
001A2E00
DECW$MRMLIBSHR12     FFFFFFFF.8096C000  FFFFFFFF.80994200
00028200
DECW$DXMLIBSHR12     FFFFFFFF.80996000  FFFFFFFF.80A40400
000AA400
223 free Slices      FFFFFFFF.80A42000  FFFFFFFF.80C00000
001BE000

```

S2 Executive Data Region

Pages/Slices

```

Base/End VA          FFFFFFFE.00000000  FFFFFFFE.00050000  Current Size
40/      8
Base/End PA          00000000.00350000  00000000.003A0000  Free
/        0
Total Size           00000000.00050000                0.3 MB  In Use
/        8
Bitmap VA/Size       FFFFFFFF.80D17EA0  00000000.00000008  Initial Size
40/      8
Slice Size           00000000.0000A000                Released
0/        0
Next free Slice      00000000.00000008

```

```

Item                Base                End
Length
PFN Database        FFFFFFFE.00000000  FFFFFFFE.00050000
00050000

```

The CLUE MEMORY/GH/FULL command displays data structures that describe granularity hint regions and huge pages.

4. SDA> CLUE MEMORY/LAYOUT
System Virtual Address Space Layout:

```

-----
Item                Base                End
Length
System Virtual Base Address  FFFFFFFE.00000000
PFN Database        FFFFFFFE.00000000  FFFFFFFE.00280000
00280000
Permanent Mapping of System L1PT  FFFFFFFE.00280000  FFFFFFFE.00282000
00002000
Global Page Table (GPT)        FFFFFFFE.00282000  FFFFFFFE.0089CD38
0061AD38
Resource Hash Table  FFFFFFFF.6FC1A000  FFFFFFFF.6FC22000
00008000
Lock ID Table        FFFFFFFF.6FC22000  FFFFFFFF.70000000
003DE000

```

Execlet Code Region 00800000	FFFFFFFF.80000000	FFFFFFFF.80800000
Resident Image Code Region 00800000	FFFFFFFF.80800000	FFFFFFFF.81000000
System Header 0000E000	FFFFFFFF.81400000	FFFFFFFF.8140E000
Error Log Allocation Buffers 00006000	FFFFFFFF.8140E000	FFFFFFFF.81414000
Nonpaged Pool (initial size) 003B4000	FFFFFFFF.81414000	FFFFFFFF.817C8000
Nonpaged Pool Expansion Area 00E9C000	FFFFFFFF.817C8000	FFFFFFFF.82664000
Execlet Data Region 00400000	FFFFFFFF.81000000	FFFFFFFF.81400000
Fork Buffers Secondary to Primary 00002000	FFFFFFFF.8268C000	FFFFFFFF.8268E000
Erase Pattern Buffer Page 00002000	FFFFFFFF.8268E000	FFFFFFFF.82690000
363 Balance Slots, 33 pages each 05D96000	FFFFFFFF.826A0000	FFFFFFFF.88436000
Paged Pool 003AE000	FFFFFFFF.88436000	FFFFFFFF.887E4000
System Control Block (SCB) 00008000	FFFFFFFF.887E4000	FFFFFFFF.887EC000
Restart Parameter Block (HWRPB) 00000B48	FFFFFFFF.88832000	FFFFFFFF.88832B48
Erase Pattern Page Table Page 00002000	FFFFFFFF.82690000	FFFFFFFF.82692000
Posix Cloning Parent Page Mapping 00002000	FFFFFFFF.88B1E000	FFFFFFFF.88B20000
Posix Cloning Child Page Mapping 00002000	FFFFFFFF.88B20000	FFFFFFFF.88B22000
Swapper Process Kernel Stack 00004000	FFFFFFFF.88B56000	FFFFFFFF.88B5A000
Swapper Map 00022000	FFFFFFFF.88B60000	FFFFFFFF.88B82000
Idle Loop's Mapping of Zero Pages 00002000	FFFFFFFF.88C5E000	FFFFFFFF.88C60000
PrimCPU Machine Check Logout Area 00000400	FFFFFFFF.88C60400	FFFFFFFF.88C60800
PrimCPU Sys Context Kernel Stack 00004000	FFFFFFFF.88C58000	FFFFFFFF.88C5C000
Tape Mount Verification Buffer 00004000	FFFFFFFF.88C62000	FFFFFFFF.88C66000
Mount Verification Buffer 00002000	FFFFFFFF.88C66000	FFFFFFFF.88C68000
Demand Zero Optimization Page 00002000	FFFFFFFF.88E68000	FFFFFFFF.88E6A000
Executive Mode Data Page 00002000	FFFFFFFF.88E6A000	FFFFFFFF.88E6C000
System Space Expansion Region 73DF0000	FFFFFFFF.8C000000	FFFFFFFF.FFDF0000
System Page Table Window 00200000	FFFFFFFF.FFDF0000	FFFFFFFF.FFFF0000
N/A Space 00010000	FFFFFFFF.FFFF0000	FFFFFFFF.FFFFFFFF

The CLUE MEMORY/LAYOUT command decodes and displays the system virtual address space layout.

```

5. SDA> CLUE MEMORY/LOOKASIDE
Non-Paged Dynamic Storage Pool - Lookaside List Queue Information:
-----
Listhead Addr: FFFFFFFF.80C50400   Size:   64   Status: Valid, 11
elements
Listhead Addr: FFFFFFFF.80C50408   Size:  128   Status: Valid, 1 element
Listhead Addr: FFFFFFFF.80C50410   Size:  192   Status: Valid, 29
elements
Listhead Addr: FFFFFFFF.80C50418   Size:  256   Status: Valid, 3
elements
Listhead Addr: FFFFFFFF.80C50420   Size:  320   Status: Valid, 7
elements
Listhead Addr: FFFFFFFF.80C50428   Size:  384   Status: Valid, 1 element
Listhead Addr: FFFFFFFF.80C50430   Size:  448   Status: Valid, 1 element
Listhead Addr: FFFFFFFF.80C50438   Size:  512   Status: Valid, 1 element
Listhead Addr: FFFFFFFF.80C50440   Size:  576   Status: Valid, 6
elements
Listhead Addr: FFFFFFFF.80C50448   Size:  640   Status: Valid, 1 element
Listhead Addr: FFFFFFFF.80C50450   Size:  704   Status: Valid, 5
elements
Listhead Addr: FFFFFFFF.80C50458   Size:  768   Status: Valid, 1 element
Listhead Addr: FFFFFFFF.80C50460   Size:  832   Status: Valid, empty
Listhead Addr: FFFFFFFF.80C50468   Size:  896   Status: Valid, 1 element
Listhead Addr: FFFFFFFF.80C50470   Size:  960   Status: Valid, 1 element
Listhead Addr: FFFFFFFF.80C50478   Size: 1024   Status: Valid, 6
elements
Listhead Addr: FFFFFFFF.80C50480   Size: 1088   Status: Valid, 1 element
Listhead Addr: FFFFFFFF.80C50488   Size: 1152   Status: Valid, 1 element
Listhead Addr: FFFFFFFF.80C50490   Size: 1216   Status: Valid, 1 element
Listhead Addr: FFFFFFFF.80C50498   Size: 1280   Status: Valid, 2
elements
Listhead Addr: FFFFFFFF.80C504A0   Size: 1344   Status: Valid, 2
elements
Listhead Addr: FFFFFFFF.80C504A8   Size: 1408   Status: Valid, 1 element
Listhead Addr: FFFFFFFF.80C504B0   Size: 1472   Status: Valid, 1 element
Listhead Addr: FFFFFFFF.80C504B8   Size: 1536   Status: Valid, 1 element
Listhead Addr: FFFFFFFF.80C504C0   Size: 1600   Status: Valid, 1 element
Listhead Addr: FFFFFFFF.80C504C8   Size: 1664   Status: Valid, 1 element
Listhead Addr: FFFFFFFF.80C504D0   Size: 1728   Status: Valid, 1 element
Listhead Addr: FFFFFFFF.80C504D8   Size: 1792   Status: Valid, 1 element
Listhead Addr: FFFFFFFF.80C504E0   Size: 1856   Status: Valid, empty
Listhead Addr: FFFFFFFF.80C504E8   Size: 1920   Status: Valid, empty
Listhead Addr: FFFFFFFF.80C504F0   Size: 1984   Status: Valid, 1 element
Listhead Addr: FFFFFFFF.80C504F8   Size: 2048   Status: Valid, 1 element
Listhead Addr: FFFFFFFF.80C50500   Size: 2112   Status: Valid, 1 element
Listhead Addr: FFFFFFFF.80C50508   Size: 2176   Status: Valid, 15
elements
Listhead Addr: FFFFFFFF.80C50510   Size: 2240   Status: Valid, empty
Listhead Addr: FFFFFFFF.80C50518   Size: 2304   Status: Valid, 1 element
.
.
.

Total free space: 00016440 (hex)    91200 (dec) bytes

```


The CLUE MEMORY/LOOKASIDE command summarizes the state of nonpageable lookaside lists. For each list, an indication of whether the queue is well formed is given. If a queue is not well formed or is invalid, messages indicating what is wrong with the queue are displayed. This command is analogous to the SDA command VALIDATE QUEUE.

These messages can also appear frequently when you use the VALIDATE QUEUE command within an SDA session that is analyzing a running system. In a running system, the composition of a queue can change while the command is tracing its links, thus producing an error message.

```
6. SDA> CLUE MEMORY/STATISTIC
Memory Management Statistics:
-----
Pagefaults:
Total Page Faults          1060897
    32
Total Page Reads           393414
    0
I/O's to read Pages       163341
    0
Modified Pages Written     121
    55596
I/O's to write Mod Pages   19
    0
Demand Zero Faults        281519
Global Valid Faults       378701
Modified Faults           236189
    0
Read Faults                0
    0
Execute Faults            28647
    10229
    0

Direct I/O                 591365
    653
Buffered I/O              589652
    654
Split I/O                  213
    12193
Hits                       83523
    12196
Logical Name Transl       1805476
    46
Dead Page Table Scans     0
    0

Non-Paged Pool:
Successful Expansions
Unsuccessful Expansions
Failed Pages Accumulator
Total Alloc Requests
Failed Alloc Requests

Paged Pool:
Total Failures
Failed Pages Accumulator
Total Alloc Requests
Failed Alloc Requests

Cur Mapped Gbl Sections
Max Mapped Gbl Sections
Cur Mapped Gbl Pages
Max Mapped Gbl Pages
Maximum Processes
Sched Zero Pages Created

Distributed Lock Manager:
    Local      Incoming
Outgoing
$ENQ New Lock Requests    674059      0
    0
$ENQ Conversion Requests  497982      0
    0
$DEQ Dequeue Requests    671626      0
    0
```

Blocking ASTs	26	0	
0			
Directory Functions		0	
0			
Deadlock Messages		0	
0			
\$ENQ Requests that Wait	822	Deadlock Searches Performed	
0			
\$ENQ Requests not Queued	3	Deadlocks Found	
0			
MSCP Statistics:		Total IOs	
0			
Count of VC Failures	0	Split IOs	
0			
Count of Hosts Served	0	IOs that had to Wait (Buf)	
0			
Count of Disks Served	10	Requests in MemWait Queue	
0			
MSCP_BUFFER (SYSGEN)	128	Max Req ever in MemWait	
0			
MSCP_CREDITS (SYSGEN)	8		
File System Cache:	Current SYSGEN Param	Hits	Misses
Hitrate			
File Header Cache	(ACP_HDRCACHE = 726)	196207	1214
99.3%			
Storage Bitmap Cache	(ACP_MAPCACHE = 181)	38	9
80.8%			
Directory Data Cache	(ACP_DIRCACHE = 726)	153415	199
99.8%			
Directory LRU	(ACP_DINDXCACHE= 181)	138543	106
99.9%			
FID Cache	(ACP_FIDCACHE = 64)	119	6
95.2%			
Extent Cache	(ACP_EXTCACHE = 64)	229	9
96.2%			
Quota Cache	(ACP_QUOCACHE = 365)	0	0
0.0%			
Volume Synch Locks	958	Window Turns	
1464			
Volume Synch Locks Wait	0	Currently Open Files	
630			
Dir/File Synch Locks	432071	Total Count of OPENS	
52903			
Dir/file Synch Locks Wait	746	Total Count of ERASE QIOs	
186			
Access Locks	151648		
Free Space Cache Wait	12608		
Global Pagefile Quota	785957	GBLPAGFIL (SYSGEN) Limit	
786688			

The CLUE MEMORY/STATISTIC command displays systemwide performance data such as page fault, I/O, pool, lock manager, MSCP, and file system cache statistics.

5.4.10. CLUE PROCESS

Displays process-related information from the current process context.

Format

```
CLUE PROCESS [/qualifier[,...]]
```

Parameters

None.

Qualifiers

/ALL

Ignored except when specified with /BUFFER. Displays the buffer objects for all processes (that is, all existing buffer objects).

/BUFFER

Displays the buffer objects for the current process or for all processes if /ALL is specified.

/LAYOUT

Displays the process P1 virtual address space layout.

/LOGICAL

Displays the process logical names and equivalence names, if they can be accessed.

/RECALL

Displays the DCL recall buffer, if it can be accessed.

Description

The CLUE PROCESS command displays process-related information from the current process context. Much of this information is in pageable address space and thus may not be present in a dump file.

Examples

```
1. SDA> CLUE PROCESS/LOGICAL
   Process Logical Names:
   -----
   "SYS$OUTPUT" = "_CLAWS$LTA5004:"
   "SYS$OUTPUT" = "_CLAWS$LTA5004:"
   "SYS$DISK" = "WORK1:"
   "BACKUP_FILE" = "_$65$DUA6"
   "SYS$PUTMSG" = "...À...À..."
   "SYS$COMMAND" = "_CLAWS$LTA5004:"
   "TAPE_LOGICAL_NAME" = "_$1$MUA3:"
   "TT" = "LTA5004:"
   "SYS$INPUT" = "_$65$DUA6:"
   "SYS$INPUT" = "_CLAWS$LTA5004:"
   "SYS$ERROR" = "21C00303.LOG"
   "SYS$ERROR" = "_CLAWS$LTA5004:"
```

```
"ERROR_FILE" = "_$65$DUA6"
```

The CLUE PROCESS/LOGICAL command displays logical names for each running process.

```
2. SDA> CLUE PROCESS/RECALL
Process DCL Recall Buffer:
-----
Index  Command
  1    ana/sys
  2    @login
  3    mc sysman io auto /log
  4    show device d
  5    sea <.x>*.lis clue$
  6    tpu <.x>*0914.lis
  7    sh log *hsj*
  8    xd <.x>.lis
  9    mc ess$ladcp show serv
 10    tpu clue_cmd.cld
 11    ana/sys
```

The CLUE PROCESS/RECALL command displays a listing of the DCL commands that have been executed most recently.

5.4.11. CLUE REGISTER

Displays the active register set for the crash CPU. The CLUE REGISTER command is valid only when analyzing crash dumps.

Format

```
CLUE REGISTER [/CPU [cpu-id|ALL]
|/PROCESS [/ADDRESS=n|INDEX=n
|/IDENTIFICATION=n|process-name|ALL]]
```

Parameters

ALL

When used with /CPU, it requests information about all CPUs in the system. When used with /PROCESS, it requests information about all processes that exist in the system.

cpu-id

When used with /CPU, it gives the number of the CPU for which information is to be displayed. Use of the cpu-id parameter causes the CLUE REGISTER command to perform an implicit SET CPU command, making the indicated CPU the current CPU for subsequent SDA commands.

process-name

When used with /PROCESS, it gives the name of the process for which information is to be displayed. Use of the **process-name** parameter, the /ADDRESS qualifier, the /INDEX qualifier, or the /IDENTIFICATION qualifier causes the CLUE REGISTER command to perform an implicit SET PROCESS command, making the indicated process the current process for subsequent SDA commands. You can determine the names of the processes in the system by issuing a SHOW SUMMARY command.

The **process-name** can contain up to 15 letters and numerals, including the underscore (_) and dollar sign (\$). If it contains any other characters, you must enclose the **process-name** in quotation marks (" ").

Qualifiers

/ADDRESS=*n*

Specifies the PCB address of the desired process when used with CLUE REGISTER/PROCESS.

/CPU [*cpu-id*|ALL]

Indicates that the registers for a CPU are required. Specify the CPU by its number or use ALL to indicate all CPUs.

/IDENTIFICATION=*n*

Specifies the identification of the desired process when used with CLUE REGISTER/PROCESS.

/INDEX=*n*

Specifies the index of the desired process when used with CLUE REGISTER/PROCESS.

/PROCESS [*process-name*|ALL]

Indicates that the registers for a process are required. The process should be specified with either one of the qualifiers /ADDRESS, /IDENTIFICATION, or /INDEX, or by its name, or by using ALL to indicate all processes.

Description

The CLUE REGISTER command displays the active register set of the crash CPU. It also identifies any known data structures, symbolizes any system virtual addresses, interprets the processor status (PS), and attempts to interpret R0 as a condition code.

If neither /CPU nor /PROCESS is specified, the parameter (*cpu-id* or *process-name*) is ignored and the registers for the SDA current process are displayed.

Examples

```
SDA> CLUE REGISTER
Current Registers:   Process index: 0042   Process name: BATCH_3   PCB:
817660C0   (CPU 1)
-----
R0  = 00000000.00000000
R1  = FFFFFFFF.814A2C80   MP_CPU   (CPU Id 1)
R2  = 00000000.00000000
R3  = 00000000.23D6BBEE
R4  = 00000000.00000064
R5  = FFFFFFFF.831F8000   PHD
R6  = 00000000.12F75475
R7  = 00000000.010C7A70
R8  = 00000000.00000001
R9  = 00000000.00000000
R10 = 00000000.00000000
R11 = FFFFFFFF.814A2C80   MP_CPU   (CPU Id 1)
R12 = FFFFFFFF.810AA5E0   SYSTEM_SYNCHRONIZATION+293E0
R13 = FFFFFFFF.810AC408   SMP$TIMEOUT
```

```

R14 = FFFFFFFF.810AED00 SMP$GL_SCHED
R15 = 00000000.7FFA1DD8
R16 = 00000000.0000078C
R17 = 00000000.00000000
R18 = FFFFFFFF.810356C0 SYS$CPU_ROUTINES_2208+1D6C0
R19 = FFFFFFFF.81006000 EXE$GR_SYSTEM_DATA_CELLS
R20 = FFFFFFFF.80120F00 SCH$QEND_C+00080
R21 = 00000000.00000000
R22 = FFFFFFFF.00000000
R23 = 00000000.00000000
R24 = 00000000.00000000
AI = FFFFFFFF.81006000 EXE$GR_SYSTEM_DATA_CELLS
RA = 00000000.00000000
PV = 00000000.00000000
R28 = FFFFFFFF.810194A0 EXE$GL_TIME_CONTROL
FP = 00000000.7FFA1F90
PC = FFFFFFFF.800863A8 SMP$TIMEOUT_C+00068
PS = 18000000.00000804 Kernel Mode, IPL 8, Interrupt

```

5.4.12. CLUE SCSI

Displays information related to SCSI and Fibre Channel.

Format

```
CLUE SCSI { /CONNECTION=n | /PORT=n | /REQUEST=n | /SUMMARY }
```

Qualifiers

/CONNECTION=*scdt-address*

Displays information about SCSI connections and decodes the SCSI connection descriptor data structure identified by the SCDT address.

/PORT=*spdt-address*

Displays all or a specific port descriptor identified by its SPDT address.

/REQUEST=*scdrp-address*

Displays information about SCSI requests and decodes the SCSI class driver request packet identified by the SCDRP address.

/SUMMARY

Displays a summary of all SCSI and FC ports and devices and their type and revisions.

Description

The CLUE SCSI command displays information about SCSI and Fibre Channel.

Examples

1. SDA> CLUE SCSI/SUMMARY
SCSI Summary Configuration:

```

-----
SPDT      Port  STDT   SCSI-Id  SCDT   SCSI-Lun  Device      UCB
Type     Rev

```



```

UCB Address          8519B4C0      Device
00000000.00000000 ()
Busarray Address    8518A180      Port Host SCSI Id
0
Port Flags
mapping_reg,dir_dma,luns,cmdq,port_autosense,smart_port
Port Device Status  online
Port Dev Status at DIPL  stdt_scdt
Target inited Bus Resets      0      Number of Events
0
Retry Attempts        0      Curr I/Os on all Ports
0
Stray Interrupts      0      Curr I/Os on all Devices
0
Unexpected Interrupts  0      Total Outstanding I/Os
0
Reselections          0
CRAB Address          8515DD00      Port Wait Queue      empty
Port CRAM Address     00000000      Nonpg Pool FKB Que  empty
Port IDB Address      85151340      Bus Reset Waiters   empty

```

This example shows a report for the PORT with SPDT address 851BED80.

```

3. SDA> CLUE SCSI/CONNECTION=85512840
SCSI Connection Descriptor (SCDT):
-----
SCDT Connection Descriptor  85512840      Device
DGA10
STDT Target Descriptor     851BBE00      Type
MSA1000 VOLUME
SPDT Port Descriptor       851BED80      Revision          4.48
Port UCB Address           8519B4C0      Target SCSI Id
1
Device UCB Address         85512CC0      Device SCSI Lun
512
Connection State           open
Capability Mask            scsi_2,cmdq
Connection Flags           ena_discon
Queue Flags                -
DIPL Queue Flags          -
Total Outstanding I/Os     0      Number of Commands sent
0
Outstanding Port I/Os      0      Number of Messages sent
0
Outstanding Device I/Os    0      Number of Bytes sent
0
Arbitration Failures       0      Parity Errors
0
Selection Failures         0      Missing Phase Errors
0
Count of Controller Errors  0      Bad Phase Errors
0
Count of Bus Errors        0      Count of Retries
0

```

This report includes information about SCSI connections and decodes the SCSI connection descriptor data structure identified by the SCDT address 85512840.

5.4.13. CLUE SG

Displays the scatter-gather map.

Format

CLUE SG [/CRAB=address]

Parameters

None.

Qualifiers

/CRAB=address

Displays the ringbuffer for the specified Counted Resource Allocation Block (CRAB). The default action is to display the ringbuffer for all CRABs.

Description

CLUE SG decodes and displays the scatter/gather ringbuffer entries.

Examples

```
1. SDA> CLUE SG/CRAB=81224740
Scatter/Gather Ringbuffer for CRAB 81224740:
-----
XAct  CRCTX      Item_Num  Item_Cnt  DMA_Addr  Status  Callers_PC                                     Count  Buf_Addr
-----
ALLO  81272780  00000020  00000004  00000000  00000001  847DDA94 SYS$EWDRIIVER+01A94  00000018  81240AE0
ALLO  81272700  0000001C  00000004  00000000  00000001  847DDA94 SYS$EWDRIIVER+01A94  00000017  81240AC0
ALLO  81272680  00000018  00000004  00000000  00000001  847DDA94 SYS$EWDRIIVER+01A94  00000016  81240AA0
ALLO  81272600  00000014  00000004  00000000  00000001  847DDA94 SYS$EWDRIIVER+01A94  00000015  81240A80
ALLO  81272580  00000010  00000004  00000000  00000001  847DDA94 SYS$EWDRIIVER+01A94  00000014  81240A60
ALLO  81272500  0000000C  00000004  00000000  00000001  847DDA94 SYS$EWDRIIVER+01A94  00000013  81240A40
ALLO  81272480  00000008  00000004  00000000  00000001  847DDA94 SYS$EWDRIIVER+01A94  00000012  81240A20
ALLO  81272400  00000004  00000004  00000000  00000001  847DDA94 SYS$EWDRIIVER+01A94  00000011  81240A00
ALLO  81272380  00000000  00000004  00000000  00000001  847DDA94 SYS$EWDRIIVER+01A94  00000010  812409E0
DEAL  841DBEA0  00000000  0000000C  C0000000  00000001  803B5124 SYS$PKQDRIVER+0B124  0000000F  812409C0
ALLO  841DBEA0  00000000  0000000C  00000000  00000001  803B4FB8 SYS$PKQDRIVER+0AFB8  0000000E  812409A0
DEAL  841DBEA0  00000000  00000012  C0000000  00000001  803B5124 SYS$PKQDRIVER+0B124  0000000D  81240980
ALLO  841DBEA0  00000000  00000012  00000000  00000001  803B4FB8 SYS$PKQDRIVER+0AFB8  0000000C  81240960
DEAL  841DBEA0  00000000  0000000C  C0000000  00000001  803B5124 SYS$PKQDRIVER+0B124  0000000B  81240940
ALLO  841DBEA0  00000000  0000000C  00000000  00000001  803B4FB8 SYS$PKQDRIVER+0AFB8  0000000A  81240920
DEAL  841DBEA0  00000000  00000012  C0000000  00000001  803B5124 SYS$PKQDRIVER+0B124  00000009  81240900
ALLO  841DBEA0  00000000  00000012  00000000  00000001  803B4FB8 SYS$PKQDRIVER+0AFB8  00000008  812408E0
DEAL  841DBEA0  00000000  00000012  C0000000  00000001  803B5124 SYS$PKQDRIVER+0B124  00000007  812408C0
ALLO  841DBEA0  00000000  00000012  00000000  00000001  803B4FB8 SYS$PKQDRIVER+0AFB8  00000006  812408A0
DEAL  841DBEA0  00000000  00000012  C0000000  00000001  803B5124 SYS$PKQDRIVER+0B124  00000005  81240880
ALLO  841DBEA0  00000000  00000012  00000000  00000001  803B4FB8 SYS$PKQDRIVER+0AFB8  00000004  81240860
DEAL  841DBEA0  00000000  00000012  C0000000  00000001  803B5124 SYS$PKQDRIVER+0B124  00000003  81240840
ALLO  841DBEA0  00000000  00000012  00000000  00000001  803B4FB8 SYS$PKQDRIVER+0AFB8  00000002  81240820
DEAL  841DBEA0  00000000  0000000C  C001E000  00000001  803B5124 SYS$PKQDRIVER+0B124  00000001  81240800
ALLO  841DBEA0  00000000  0000000C  00000000  00000001  803B4FB8 SYS$PKQDRIVER+0AFB8  00000000  812407E0
```

In this example, the scatter-gather ring buffer for the CRAB at address 81224740 is displayed.

```
2. SDA> CLUE SG/CRAB=8120D600
Scatter/Gather Ringbuffer for CRAB 8120D600:
-----
XAct  CRCTX      Item_Num  Item_Cnt  DMA_Addr  Status  Callers_PC                                     Count  Buf_Addr
-----
ALLO  8128A380  0001C000  00004000  00000000  00000001  8480E990 SYS$MCDRIIVER+02990  00000000  8121C760
```

In this example, the scatter-gather ring buffer for the CRAB address 8120D600 is displayed.

5.4.14. CLUE STACK

On Alpha, CLUE STACK identifies and displays the current stack. On Integrity servers, CLUE STACK only identifies the current stack without displaying it. Use the SDA command SHOW STACK on both Alpha and Integrity servers to display and decode the whole stack for the more common bugcheck types.

Format

CLUE STACK

Parameters

None.

Qualifiers

None.

Description

The CLUE STACK command identifies and displays the current stack together with the upper and lower stack limits. In case of a FATALEXCPT, INVEXCEPTN, SSRVEXCEPT, UNXSIGNAL, or PGFIPLHI bugcheck, CLUE STACK tries to decode the whole stack.

Examples

```
SDA> CLUE STACK
```

```
Stack Decoder:
```

```
-----
```

```
Normal Process Kernel Stack:
```

Stack Pointer	00000000.7FFA1C98
Stack Limits (low)	00000000.7FFA0000
(high)	00000000.7FFA2000

```
SSRVEXCEPT Stack:
```

```
-----
```

```
Stack Pointer SP => 00000000.7FFA1C98
```

```
Information saved by Bugcheck:
```

a(Signal Array)	00000000.7FFA1C98	00000000.00000000
-----------------	-------------------	-------------------

```
EXE$EXCPTN[E] Temporary Storage:
```

```
EXE$EXCPTN[E] Stack Frame:
```

PV	00000000.7FFA1CA0	FFFFFFFF.829CF010	EXE\$EXCPTN
Entry Point		FFFFFFFF.82A21000	EXE\$EXCPTN_C
return PC	00000000.7FFA1CA8	FFFFFFFF.82A2059C	SYS
\$CALL_HANDL_C+0002C			
saved R2	00000000.7FFA1CB0	00000000.00000000	
saved FP	00000000.7FFA1CB8	00000000.7FFA1CD0	

```
SYSCALL_HANDL Temporary Storage:
```

	00000000.7FFA1CC0	FFFFFFFF.829CEDA8	SYSCALL_HANDL
	00000000.7FFA1CC8	00000000.00000000	

```
SYSCALL_HANDL Stack Frame:
```

PV	00000000.7FFA1CD0	FFFFFFFF.829CEDA8	SYSCALL_HANDL
Entry Point		FFFFFFFF.82A20570	SYS
\$CALL_HANDL_C			
	00000000.7FFA1CD8	00000000.00000000	
return PC	00000000.7FFA1CE0	FFFFFFFF.82A1E930	CHF_REI+000DC
saved FP	00000000.7FFA1CE8	00000000.7FFA1F40	

```
Fixed Exception Context Area:
```

Linkage Pointer	00000000.7FFA1CF0	FFFFFFFF.80C63780	
EXCEPTION_MON_NPRW+06D80			
a(Signal Array)	00000000.7FFA1CF8	00000000.7FFA1EB8	
a(Mechanism Array)	00000000.7FFA1D00	00000000.7FFA1D40	
a(Exception Frame)	00000000.7FFA1D08	00000000.7FFA1F00	
Exception FP	00000000.7FFA1D10	00000000.7FFA1F40	
Unwind SP	00000000.7FFA1D18	00000000.00000000	
Reinvokable FP	00000000.7FFA1D20	00000000.00000000	
Unwind Target	00000000.7FFA1D28	00000000.00020000	SYS
\$K_VERSION_04			
#Sig Args/Byte Cnt	00000000.7FFA1D30	00000005.00000250	BUG\$_NETRCVPKT
a(Msg)/Final Status	00000000.7FFA1D38	829CE050.000008F8	BUG
\$_SEQ_NUM_OVF			
Mechanism Array:			
Flags/Arguments	00000000.7FFA1D40	00000000.0000002C	
a(Establisher FP)	00000000.7FFA1D48	00000000.7AFFBAD0	
reserved/Depth	00000000.7FFA1D50	FFFFFFFF.FFFFFFFD	
a(Handler Data)	00000000.7FFA1D58	00000000.00000000	
a(Exception Frame)	00000000.7FFA1D60	00000000.7FFA1F00	
a(Signal Array)	00000000.7FFA1D68	00000000.7FFA1EB8	
saved R0	00000000.7FFA1D70	00000000.00020000	SYS
\$K_VERSION_04			
saved R1	00000000.7FFA1D78	00000000.00000000	
saved R16	00000000.7FFA1D80	00000000.00020004	UCB
\$M_NI_PRM_MLT+00004			
saved R17	00000000.7FFA1D88	00000000.00010050	SYS
\$K_VERSION_16+00010			
saved R18	00000000.7FFA1D90	FFFFFFFF.FFFFFFFF	
saved R19	00000000.7FFA1D98	00000000.00000000	
saved R20	00000000.7FFA1DA0	00000000.7FFA1F50	
saved R21	00000000.7FFA1DA8	00000000.00000000	
saved R22	00000000.7FFA1DB0	00000000.00010050	SYS
\$K_VERSION_16+00010			
saved R23	00000000.7FFA1DB8	00000000.00000000	
saved R24	00000000.7FFA1DC0	00000000.00010051	SYS
\$K_VERSION_16+00011			
saved R25	00000000.7FFA1DC8	00000000.00000000	
saved R26	00000000.7FFA1DD0	FFFFFFFF.8010ACA4	AMAC
\$EMUL_CALL_NATIVE_C+000A4			
saved R27	00000000.7FFA1DD8	00000000.00010050	SYS
\$K_VERSION_16+00010			
saved R28	00000000.7FFA1DE0	00000000.00000000	
FP Regs not valid	[.....]		
a(Signal64 Array)	00000000.7FFA1EA0	00000000.7FFA1ED0	
SP Align = 10(hex)	[.....]		
Signal Array:			
Arguments	00000000.7FFA1EB8	00000005	
Condition	00000000.7FFA1EBC	0000000C	
Argument #2	00000000.7FFA1EC0	00010000	LDRIMG
\$M_NPAGED_LOAD			
Argument #3	00000000.7FFA1EC4	00000000	
Argument #4	00000000.7FFA1EC8	00030078	SYS
\$K_VERSION_01+00078			
Argument #5	00000000.7FFA1ECC	00000003	
64-bit Signal Array:			

```

Arguments          00000000.7FFA1ED0  00002604.00000005
Condition          00000000.7FFA1ED8  00000000.0000000C
Argument #2       00000000.7FFA1EE0  00000000.00010000  LDRIMG
$M_NPAGED_LOAD
Argument #3       00000000.7FFA1EE8  00000000.00000000
Argument #4       00000000.7FFA1EF0  00000000.00030078  SYS
$K_VERSION_01+00078
Argument #5       00000000.7FFA1EF8  00000000.00000003

Interrupt/Exception Frame:
saved R2          00000000.7FFA1F00  00000000.00000003
saved R3          00000000.7FFA1F08  FFFFFFFF.80C63460
EXCEPTION_MON_NPRW+06A60
saved R4          00000000.7FFA1F10  FFFFFFFF.80D12740  PCB
saved R5          00000000.7FFA1F18  00000000.0000000C8
saved R6          00000000.7FFA1F20  00000000.00030038  SYS
$K_VERSION_01+00038
saved R7          00000000.7FFA1F28  00000000.7FFA1FC0
saved PC          00000000.7FFA1F30  00000000.00030078  SYS
$K_VERSION_01+00078
saved PS          00000000.7FFA1F38  00000000.00000003  IPL INT CURR
PREV
SP Align = 00(hex) [.....]          00 0 Kern
User

Stack Frame:
PV               00000000.7FFA1F40  00000000.00010050  SYS
$K_VERSION_16+00010
Entry Point      00000000.00030060  SYS
$K_VERSION_01+00060
00000000.7FFA1F48  00000000.00010000  LDRIMG
$M_NPAGED_LOAD
return PC        00000000.7FFA1F50  FFFFFFFF.8010ACA4  AMAC
$EMUL_CALL_NATIVE_C+000A4
saved FP         00000000.7FFA1F58  00000000.7FFA1F70

Stack (not decoded):
00000000.7FFA1F60  00000000.00000001
00000000.7FFA1F68  FFFFFFFF.800EE81C  RM_STD
$DIRCACHE_BLKAST_C+005AC

Stack Frame:
PV               00000000.7FFA1F70  FFFFFFFF.80C6EBA0  EXE$CMKRNL
Entry Point      FFFFFFFF.800EE6C0  EXE$CMKRNL_C
00000000.7FFA1F78  00000000.829CEDE8  EXE$SIGTORET
00000000.7FFA1F80  00010050.00000002
00000000.7FFA1F88  00000000.00020000  SYS
$K_VERSION_04
00000000.7FFA1F90  00000000.00030000  SYS
$K_VERSION_01
return PC        00000000.7FFA1F98  FFFFFFFF.800A4D64
__RELEASE_LDBL_EXEC_SERVICE+00284
saved R2         00000000.7FFA1FA0  00000000.00000003
saved R4         00000000.7FFA1FA8  FFFFFFFF.80D12740  PCB
saved R13        00000000.7FFA1FB0  00000000.00010000  LDRIMG
$M_NPAGED_LOAD
saved FP         00000000.7FFA1FB8  00000000.7AFFBAD0

```

```

Interrupt/Exception Frame:
saved R2          00000000.7FFA1FC0  00000000.7FFCF880  MMG$IMGHDRBUF
+00080
saved R3          00000000.7FFA1FC8  00000000.7B0E9851
saved R4          00000000.7FFA1FD0  00000000.7FFCF818  MMG$IMGHDRBUF
+00018
saved R5          00000000.7FFA1FD8  00000000.7FFCF938  MMG$IMGHDRBUF
+00138
saved R6          00000000.7FFA1FE0  00000000.7FFAC9F0
saved R7          00000000.7FFA1FE8  00000000.7FFAC9F0
saved PC          00000000.7FFA1FF0  FFFFFFFF.80000140  SYS$CLREF_C
saved PS          00000000.7FFA1FF8  00000000.0000001B  IPL INT CURR
PREV
SP Align = 00(hex)  [.....]          00 0 User
User

```

CLUE STACK identifies and displays the current stack and its upper and lower limit. It then decodes the current stack if it is one of the more common bugcheck types. In this case, CLUE STACK tries to decode the entire INVEXCEPTN stack.

5.4.15. CLUE SYSTEM

Displays the contents of the shared logical name tables in the system.

Format

CLUE SYSTEM /LOGICAL

Parameters

None.

Qualifiers

/LOGICAL

Displays all the shared logical names.

Description

The CLUE SYSTEM/LOGICAL command displays the contents of the shared logical name tables in the system.

Examples

```

SDA> CLUE SYSTEM/LOGICAL
Shareable Logical Names:
-----
"XMICONBMSEARCHPATH" = "CDE$HOME_DEFAULTS:[ICONS]%B%M.BM"
"MTHRRTL_TV" = "MTHRRTL_D53_TV"
"SMGSHR_TV" = "SMGSHR"
"DECW$DEFAULT_KEYBOARD_MAP" = "NORTH_AMERICAN_LK401AA"
"CONVSHR_TV" = "CONVSHR"
"XDPS$INCLUDE" = "SYS$SYSROOT:[XDPS$INCLUDE]"
"DECW$SYSTEM_DEFAULTS" = "SYS$SYSROOT:[DECW$DEFAULTS.USER]"
"SYS$PS_FONT_METRICS" = "SYS$SYSROOT:[SYSFONT.PS_FONT_METRICS.USER]"
"SYS$TIMEZONE_NAME" = "???"

```

```

"STARTUP$STARTUP_VMS" = "SYS$STARTUP:VMS$VMS.DAT"
"PASMSG" = "PAS$MSG"
"UCX$HOST" = "SYS$COMMON:[SYSEXE]UCX$HOST.DAT;1"
"SYS$SYLOGIN" = "SYS$MANAGER:SYLOGIN"
"DNS$SYSTEM" = "DNS$SYSTEM_TABLE"
"IPC$ACP_ERRMBX" = "d.Ú."
"CDE$DETACHED_LOGICALS" = "DECW$DISPLAY,LANG"
"DECW$SERVER_SCREEN" = "GXA0"
"DNS$_COTOAD_MBX" = "ä<â."
"DNS$LOGICAL" = "DNS$SYSTEM"
"OSIT$MAILBOX" = "äAë."
"XNL$SHR_TV" = "XNL$SHR_TV_SUPPORT.EXE"
"MOM$SYSTEM" = "SYS$SYSROOT:[MOM$SYSTEM]"
"MOP$LOAD" = "SYS$SYSROOT:<MOM$SYSTEM>"
.
.
.

```

5.4.16. CLUE VCC

Displays virtual I/O cache-related information. If extended file cache (XFC) is enabled, the CLUE VCC command is disabled.

Format

```
CLUE VCC [/qualifier[,...]]
```

Parameters

None.

Qualifiers

/CACHE

Decodes and displays the cache lines that are used to correlate the file virtual block numbers (VBNs) with the memory used for caching. Note that the cache itself is not dumped in a selective dump. Use of this qualifier with a selective dump produces the following message:

```
%CLUE-I-VCCNOCAC, Cache space not dumped because DUMPSTYLE is selective
```

/LIMBO

Walks through the limbo queue (LRU order) and displays information for the cached file header control blocks (FCBs).

/STATISTIC

Displays statistical and performance information related to the virtual I/O cache.

/VOLUME

Decodes and displays the cache volume control blocks (CVCB).

Examples

1. SDA> CLUE VCC/STATISTIC

Virtual I/O Cache Statistics:

```

-----
Cache State          pak,on,img,data,enabled
Cache Flags          on,protocol_only
Cache Data Area      80855200
Total Size (pages)   400      Total Size (MBytes)
    3.1 MB
Free Size (pages)    0      Free Size (MBytes)
    0.0 MB
Read I/O Count       34243   Read I/O Bypassing Cache
    3149
Read Hit Count        15910   Read Hit Rate
    46.4%
Write I/O Count       4040   Write I/O Bypassing Cache
    856
IOpost PID Action Rtns 40829   IOpost Physical I/O Count
    28
IOpost Virtual I/O Count 0      IOpost Logical I/O Count
    7
Read I/O past File HWM 124    Cache Id Mismatches
    44
Count of Cache Block Hits 170    Files Retained
    100
Cache Line LRU       82B11220 82B11620   Oldest Cache Line Time
    00001B6E
Limbo LRU Queue      80A97E3C 80A98B3C   Oldest Limbo Queue Time
    00001B6F
Cache VCB Queue      8094DE80 809AA000   System Uptime (seconds)
    00001BB0
    
```

2. SDA> CLUE VCC/VOLUME

Virtual I/O Cache - Cache VCB Queue:

```

-----
CacheVCB RealVCB   LockID      IRP Queue      CID  LKSB Ocnt State
-----
-----
8094DE80 80A7E440 020007B2 8094DEBC 8094DEBC 0000 0001 0002 on
809F3FC0 809F97C0 0100022D 809F3FFC 809F3FFC 0000 0001 0002 on
809D0240 809F7A40 01000227 809D027C 809D027C 0000 0001 0002 on
80978B80 809F6C00 01000221 80978BBC 80978BBC 0000 0001 0002 on
809AA000 809A9780 01000005 809AA83C 809AA03C 0007 0001 0002 on
    
```

3. SDA> CLUE VCC/LIMBO

Virtual I/O Cache - Limbo Queue:

```

-----
CFCB      CVCB      FCB      CFCB      IOerrors      FID (hex)
-----
-Status-
-----
80A97DC0 809AA000 80A45100 00000200 00000000 (076B,0001,00)
80A4E440 809AA000 809CD040 00000200 00000000 (0767,0001,00)
80A63640 809AA000 809FAE80 00000200 00000000 (0138,0001,00)
80AA2540 80978B80 80A48140 00000200 00000000 (0AA5,0014,00)
80A45600 809AA000 80A3AC00 00000200 00000000 (0C50,0001,00)
80A085C0 809AA000 809FA140 00000200 00000000 (0C51,0001,00)
80A69800 809AA000 809FBA00 00000200 00000000 (0C52,0001,00)
80951000 809AA000 80A3F140 00000200 00000000 (0C53,0001,00)
80A3E580 809AA000 80A11A40 00000200 00000000 (0C54,0001,00)
80A67F80 809AA000 80978F00 00000200 00000000 (0C55,0001,00)
809D30C0 809AA000 809F4CC0 00000200 00000000 (0C56,0001,00)
    
```

```

809D4B80 809AA000 8093E540 00000200 00000000 (0C57,0001,00)
[.....]
80A81600 809AA000 8094B2C0 00000200 00000000 (0C5D,0001,00)
80AA3FC0 809AA000 80A2DEC0 00000200 00000000 (07EA,000A,00)
80A98AC0 809AA000 8093C640 00000200 00000000 (0C63,0001,00)

```

4. SDA> CLUE VCC/CACHE

Virtual I/O Cache - Cache Lines:

```

-----
CL      VA      CVCB     CFCB     FCB      CFCB     IOerrors  FID
(hex)
-----
----- -Status- -----
-----
82B11200 82880000 809D0240 809D7000 80A01100 00000200 00000000
(006E,0003,00)
82B15740 82AAA000 809AA000 80A07A00 80A24240 00000000 00000000
(0765,0001,00)
82B14EC0 82A66000 809AA000 80A45600 80A3AC00 00000200 00000000
(0C50,0001,00)
82B12640 82922000 809D0240 809D7000 80A01100 00000200 00000000
(006E,0003,00)
82B123C0 8290E000 809AA000 80A45600 80A3AC00 00000200 00000000
(0C50,0001,00)
82B13380 8298C000 809D0240 809D7000 80A01100 00000200 00000000
(006E,0003,00)
82B15A40 82AC2000 809AA000 80A45600 80A3AC00 00000200 00000000
(0C50,0001,00)
82B15F40 82AEA000 809D0240 809D7000 80A01100 00000200 00000000
(006E,0003,00)
82B12AC0 82946000 809D0240 809D7000 80A01100 00000200 00000000
(006E,0003,00)
82B12900 82938000 809D0240 809D7000 80A01100 00000200 00000000
(006E,0003,00)
82B10280 82804000 809AA000 80A45600 80A3AC00 00000200 00000000
(0C50,0001,00)
82B122C0 82906000 809AA000 80A1AC00 80A48000 00000000 00000000
(0164,0001,00)
82B14700 82A28000 809AA000 809FFEC0 809F8DC0 00000004 00000000
(07B8,0001,00)
82B11400 82890000 809AA000 80A113C0 80A11840 00000000 00000000
(00AF,0001,00)
[.....]
82B11380 8288C000 809AA000 809DA0C0 809C99C0 00002000 00000000
(00AB,0001,00)
82B130C0 82976000 809AA000 809DA0C0 809C99C0 00002000 00000000
(00AB,0001,00)
82B11600 828A0000 809AA000 809DA0C0 809C99C0 00002000 00000000
(00AB,0001,00)

```

5.4.17. CLUE XQP

Displays XQP-related information.

Format

CLUE XQP [/qualifier[,...]]

Parameters

None.

Qualifiers

/ACTIVE

Displays all active XQP processes. (See also /FULL.)

/AQB

Displays any current I/O request packets (IRPs) waiting at the interlocked queue.

/BFRD=index

Displays the buffer descriptor (BFRD) referenced by the index specified. The index is identical to the hash value.

/BFRL=index

Displays the buffer lock block descriptor (BFRL) referenced by the index specified. The index is identical to the hash value.

/BUFFER=(n,m)

Displays the BFRDs for a given pool. Specify either 0, 1, 2 or 3, or a combination of these in the parameter list. (See also /FULL.)

/CACHE_HEADER

Displays the block buffer cache header.

/FCB=address

Displays all file header control blocks (FCBs) with a nonzero DIRINDEX for a given volume. If no address is specified, the current volume of the current process is used. (See also /FULL.)

The address specified can also be either a valid volume control block (VCB), unit control block (UCB), or window control block (WCB) address.

/FILE=address

Decodes and displays file header (FCB), window (WCB), and cache information for a given file. The file can be identified by either its FCB or WCB address.

/FULL

Ignored except when used with certain other qualifiers. When used with /ACTIVE, CLUE displays additional data on the XQP's caller (for Alpha only). When used with /BUFFER or /VALIDATE, CLUE displays additional data on each buffer descriptor. When used with /FCB, CLUE displays all FCBs, including any that are unused.

/GLOBAL

Displays the global XQP area for a given process.

/LBN_HASH=lbn

Calculates and displays the hash value for a given logical block number (LBN).

/LIMBO

Searches through the limbo queue and displays FCB information from available, but unused file headers.

/LOCK=lockbasis

Displays all file system serialization, arbitration, and cache locks found for the specified lockbasis.

/THREAD=n

Displays the XQP thread area for a given process. The specified thread number is checked for validity. If no thread number is specified, the current thread is displayed. If no current thread, but only one single thread is in use, then that thread is displayed. If more than one thread exists or an invalid thread number is specified, then a list of currently used threads is displayed.

/VALIDATE=(n,m)

Performs certain validation checks on the block buffer cache to detect corruption. Specify 1, 2, 3, 4, or a combination of these in the parameter list. If an inconsistency is found, a minimal error message is displayed. (See also /FULL.)

Description

The CLUE XQP command displays XQP information. XQP is part of the I/O subsystem.

Examples

1. SDA> CLUE XQP/CACHE_HEADER

Block Buffer Cache Header:

```
-----
Cache_Header  8437DF90    BFRcnt      000005D2    FreeBFRL
 843916A0
Bufbase       8439B400    BFRDbase    8437E080    BFRLbase
 8438F7E0
Bufsize       000BA400    LBNhashtbl  84398390    BFRLhashtbl
 84399BC8
Realsize      000D78A0    LBNhashcnt  0000060E    BFRLhashcnt
 0000060E

Pool          #0          #1          #2          #3
Pool_LRU      8437E5C0    84385F40    84387E90    8438EEB0
              8437F400    84385D60    8438AC80    8438EE20
Pool_WAITQ    8437DFE0    8437DFE8    8437DFF0    8437DFF8
              8437DFE0    8437DFE8    8437DFF0    8437DFF8
Waitcnt       00000000    00000000    00000000    00000000
Poolavail     00000094    00000252    00000251    00000094
Poolcnt       00000095    00000254    00000254    00000095

AmbigQFL      00000000    Process_Hits 00000000    Cache_Serial
 00000000
AmbigQBL      00000000    Valid_Hits   00000000    Cache_Stalls
 00000000
```

Disk_Reads	00000000	Invalid_Hits	00000000	Buffer_Stalls
	00000000			
Disk_Writes	00000000	Misses	00000000	

The SDA command `CLUE XQP/CACHE_HEADER` displays the block buffer cache header.

2. SDA> `CLUE XQP/VALIDATE=(1,4)`
Searching BFRD Array for possible Corruption...
Searching Lock Basis Hashtable for possible Corruption...

In this example, executing the `CLUE XQP/VALIDATE=(1,4)` command indicated that no corruption was detected in either the BFRD Array or the Lock Basis Hashtable.

Chapter 6. SDA FLT Extension

The Alignment Fault Utility (FLT) finds alignment faults and records them in a ring buffer, which can be sized when starting alignment fault tracing. The summary screen displays the results sorted by the program counter (PC) that has incurred the most alignment faults. The detailed trace output also shows the process identification (PID) of the process that caused the alignment fault, with the virtual address that triggered the fault.

Output can be directed to a file using the SDA SET OUTPUT command.

FLT can be started and stopped as required without the need for a system reboot.

6.1. FLT Commands

The table below summarizes the commands for the FLT utility.

Table 6.1. Commands for the Alignment Fault Utility

Commands	Description
FLT LOAD	Loads the FLT\$DEBUG execlt.
FLT UNLOAD	Unloads the FLT\$DEBUG execlt.
FLT START TRACE	Starts alignment fault tracing.
FLT	Lists the FLT commands.
FLT STOP TRACE	Stops tracing.
FLT SHOW TRACE	Displays detailed information about the trace.

The end of this chapter has an example of how you might use these FLT commands.

6.1.1. FLT

When entered with no keywords, lists the FLT commands.

Format

FLT

Parameters

None.

Qualifiers

None.

6.1.2. FLT LOAD

Loads the FLT\$DEBUG execlt. Do this before starting alignment fault tracing.

Format

FLT LOAD

Parameters

None.

Qualifiers

None.

6.1.3. FLT SHOW TRACE

Displays detail about the trace.

Format

```
FLT SHOW TRACE [/SUMMARY [/RATES (d) | /TOTALS]]
```

Parameters

None.

Qualifiers

/RATES

When used with /SUMMARY, the alignment fault rate per second for each PC during the collection interval is displayed. This is the default.

/SUMMARY

Displays the results sorted by the program counter (PC) that has incurred the most alignment faults.

/TOTALS

When used with /SUMMARY, the total number of alignment faults for each PC during the collection interval is displayed.

6.1.4. FLT START TRACE

Starts alignment fault tracing. By default, all PCs are traced.

Format

```
START TRACE [/BUFFER=pages] [/BEGIN=pc_range_low]  
[/CALLER] [/END=pc_range_high]  
[/INDEX=pid] [MODE=(mode,...)]
```

Parameters

None.

Qualifiers

/BUFFER=pages

The number of pages to size the trace buffer. The default is 128 pages or 1MB.

/BEGIN=pc_range_low

Start of range of PCs to trace.

/CALLER

For each alignment fault, in addition to recording the PC that incurred the fault, FLT also records the PCs of the caller, the callers caller, and so on, for up to 10 call frames.

/END=pc_range_high

End of range of PCs to trace.

/INDEX=pid

Only trace alignment faults for the specified process. You can specify the process index itself, or the process identification or extended process identification, from which the process index is extracted.

/MODE=(mode,...)

Only trace alignment faults that occur in the specified modes. Allowed modes are KERNEL, EXEC, SUPER and USER. If you specify only one mode, you can omit the parentheses.

6.1.5. FLT STOP TRACE

Stops tracing.

Format

FLT STOP TRACE

Parameters

None.

Qualifiers

None.

6.1.6.

Unloads the FLT\$DEBUG execlt.

Format

FLT UNLOAD

Parameters

None.

Qualifiers

None.

Example

```
SDA> flt load
SDA> flt start trace
.
.
.
SDA> flt show trace /summary
```

Fault Trace Information: (at 12-OCT-2004 16:09:29.43, trace time 00:00:55.145335)

Exception PC	Count	Exception PC	Module	Offset
FFFFFFFF.86214790	973	RDMSHRP72+0019E790	RDMSHRP72	0019E790
FFFFFFFF.86214791	871	RDMSHRP72+0019E791	RDMSHRP72	0019E791
FFFFFFFF.8620B261	700	RDMSHRP72+00195261	RDMSHRP72	00195261
FFFFFFFF.8620B260	700	RDMSHRP72+00195260	RDMSHRP72	00195260
FFFFFFFF.841C3451	208	LIBRTL+00195451	LIBRTL	00195451
FFFFFFFF.818E43E0	193	NET\$TRANSPORT_NSP+303E0	NET\$TRANSPORT_NSP	000303E0
FFFFFFFF.818E4400	193	NET\$TRANSPORT_NSP+30400	NET\$TRANSPORT_NSP	00030400
FFFFFFFF.818E4430	193	NET\$TRANSPORT_NSP+30430	NET\$TRANSPORT_NSP	00030430
FFFFFFFF.818E4450	193	NET\$TRANSPORT_NSP+30450	NET\$TRANSPORT_NSP	00030450
FFFFFFFF.818E44B1	193	NET\$TRANSPORT_NSP+304B1	NET\$TRANSPORT_NSP	000304B1
FFFFFFFF.818E44D0	193	NET\$TRANSPORT_NSP+304D0	NET\$TRANSPORT_NSP	000304D0
FFFFFFFF.818E6720	186	NET\$TRANSPORT_NSP+32720	NET\$TRANSPORT_NSP	00032720
FFFFFFFF.818E64C0	179	NET\$TRANSPORT_NSP+324C0	NET\$TRANSPORT_NSP	000324C0
FFFFFFFF.818E6520	179	NET\$TRANSPORT_NSP+32520	NET\$TRANSPORT_NSP	00032520
FFFFFFFF.86DE9480	166	RDMSHRP72+00D73480	RDMSHRP72	00D73480
FFFFFFFF.807814A1	162	EXE\$SETOPR_C+00841	MESSAGE_ROUTINES	0001D7A1
FFFFFFFF.86DE8C90	146	RDMSHRP72+00D72C90	RDMSHRP72	00D72C90
FFFFFFFF.86DE8EC0	146	RDMSHRP72+00D72EC0	RDMSHRP72	00D72EC0
FFFFFFFF.8701C340	146	RDMSHRP72+00FA6340	RDMSHRP72	00FA6340
FFFFFFFF.862026E1	100	RDMSHRP72+0018C6E1	RDMSHRP72	0018C6E1
FFFFFFFF.86202580	100	RDMSHRP72+0018C580	RDMSHRP72	0018C580
FFFFFFFF.862025B0	100	RDMSHRP72+0018C5B0	RDMSHRP72	0018C5B0
FFFFFFFF.8701B900	83	RDMSHRP72+00FA5900	RDMSHRP72	00FA5900
00000000.000EE990	37			
00000000.000EEA51	37			
00000000.000EE8D1	37			
FFFFFFFF.807359C1	28	LOCKING+253C1	LOCKING	000253C1
FFFFFFFF.807359F1	28	LOCKING+253F1	LOCKING	000253F1
FFFFFFFF.80732EE0	27	LCK\$PILL_RSB_CACHE_C+008F0	LOCKING	000228E0
FFFFFFFF.86DE8690	18	RDMSHRP72+00D72690	RDMSHRP72	00D72690
FFFFFFFF.80B388A0	15	SECURITY+461A0	SECURITY	000461A0
FFFFFFFF.80B213F0	13	NSA\$SIZE_NSAB_C+00840	SECURITY	0002ECF0
FFFFFFFF.86DFE9E0	12	RDMSHRP72+00D889E0	RDMSHRP72	00D889E0
[.....]				

```
SDA> flt show trace
```

Unaligned Data Fault Trace Information:

Timestamp	CPU	Unaligned VA	Exception PC	Access	EPID	Trace Buffer
12-OCT 16:09:56.439499	02	00000000.014A4F8A	86214791 RDMSHRP72+0019E791	Exec	39C004DC	FFFFFFFF.74921610
12-OCT 16:09:56.439493	02	00000000.023DFFD4	86214790 RDMSHRP72+0019E790	Exec	39C004DC	FFFFFFFF.749215E8
12-OCT 16:09:56.439486	02	00000000.014A4F42	86214790 RDMSHRP72+0019E790	Exec	39C004DC	FFFFFFFF.749215C0
12-OCT 16:09:56.439480	02	00000000.014A4F8A	86214790 RDMSHRP72+0019E790	Exec	39C004DC	FFFFFFFF.74921598
12-OCT 16:09:56.439254	02	00000000.0154F1DC	807814A1 EXE\$SETOPR_C+00841	Exec	39C004DC	FFFFFFFF.74921570
12-OCT 16:09:56.431606	02	00000000.014A4F5A	86214791 RDMSHRP72+0019E791	Exec	39C004DC	FFFFFFFF.74921548
12-OCT 16:09:56.431601	02	00000000.022DEE44	86214790 RDMSHRP72+0019E790	Exec	39C004DC	FFFFFFFF.74921520
12-OCT 16:09:56.431594	02	00000000.014A4F42	86214790 RDMSHRP72+0019E790	Exec	39C004DC	FFFFFFFF.749214F8
12-OCT 16:09:56.431588	02	00000000.014A4F5A	86214790 RDMSHRP72+0019E790	Exec	39C004DC	FFFFFFFF.749214D0
12-OCT 16:09:56.430255	02	00000000.0155BDDC	807814A1 EXE\$SETOPR_C+00841	Exec	39C004DC	FFFFFFFF.749214A8
12-OCT 16:09:56.426878	02	00000000.014A4F72	86214791 RDMSHRP72+0019E791	Exec	39C004DC	FFFFFFFF.74921480
12-OCT 16:09:56.426872	02	00000000.02394ED4	86214790 RDMSHRP72+0019E790	Exec	39C004DC	FFFFFFFF.74921458
12-OCT 16:09:56.426865	02	00000000.014A4F42	86214790 RDMSHRP72+0019E790	Exec	39C004DC	FFFFFFFF.74921430
12-OCT 16:09:56.426859	02	00000000.014A4F72	86214790 RDMSHRP72+0019E790	Exec	39C004DC	FFFFFFFF.74921408
12-OCT 16:09:56.426583	02	00000000.0154A97C	807814A1 EXE\$SETOPR_C+00841	Exec	39C004DC	FFFFFFFF.749213E0
12-OCT 16:09:56.421244	02	00000000.014A4F52	86214791 RDMSHRP72+0019E791	Exec	39C004DC	FFFFFFFF.749213B8
12-OCT 16:09:56.421238	02	00000000.02296824	86214790 RDMSHRP72+0019E790	Exec	39C004DC	FFFFFFFF.74921390
12-OCT 16:09:56.421232	02	00000000.014A4F42	86214790 RDMSHRP72+0019E790	Exec	39C004DC	FFFFFFFF.74921368
12-OCT 16:09:56.421226	02	00000000.014A4F52	86214790 RDMSHRP72+0019E790	Exec	39C004DC	FFFFFFFF.74921340
12-OCT 16:09:56.420916	02	00000000.0156405C	807814A1 EXE\$SETOPR_C+00841	Exec	39C004DC	FFFFFFFF.74921318
12-OCT 16:09:56.413932	02	00000000.014A4F52	86214791 RDMSHRP72+0019E791	Exec	39C004DC	FFFFFFFF.749212F0
12-OCT 16:09:56.413926	02	00000000.023C10D4	86214790 RDMSHRP72+0019E790	Exec	39C004DC	FFFFFFFF.749212C8
12-OCT 16:09:56.413918	02	00000000.014A4F42	86214790 RDMSHRP72+0019E790	Exec	39C004DC	FFFFFFFF.749212A0
12-OCT 16:09:56.413913	02	00000000.014A4F52	86214790 RDMSHRP72+0019E790	Exec	39C004DC	FFFFFFFF.74921278
12-OCT 16:09:56.413645	02	00000000.01564E9C	807814A1 EXE\$SETOPR_C+00841	Exec	39C004DC	FFFFFFFF.74921250
12-OCT 16:09:56.403972	02	00000000.014A4F52	86214791 RDMSHRP72+0019E791	Exec	39C004DC	FFFFFFFF.74921228
12-OCT 16:09:56.403966	02	00000000.023036C4	86214790 RDMSHRP72+0019E790	Exec	39C004DC	FFFFFFFF.74921200
12-OCT 16:09:56.403960	02	00000000.014A4F42	86214790 RDMSHRP72+0019E790	Exec	39C004DC	FFFFFFFF.749211D8
12-OCT 16:09:56.403954	02	00000000.014A4F52	86214790 RDMSHRP72+0019E790	Exec	39C004DC	FFFFFFFF.749211B0
12-OCT 16:09:56.403689	02	00000000.0155E47C	807814A1 EXE\$SETOPR_C+00841	Exec	39C004DC	FFFFFFFF.74921188
12-OCT 16:09:56.395575	02	00000000.014A4F8A	86214791 RDMSHRP72+0019E791	Exec	39C004DC	FFFFFFFF.74921160
12-OCT 16:09:56.395569	02	00000000.02448D24	86214790 RDMSHRP72+0019E790	Exec	39C004DC	FFFFFFFF.74921138
12-OCT 16:09:56.395562	02	00000000.014A4F42	86214790 RDMSHRP72+0019E790	Exec	39C004DC	FFFFFFFF.74921110

[.....]

Chapter 7. SDA OCLA Extension (Alpha Only)

The Alpha EV7 On-Chip Logic Analyzer (OCLA) utility collects Program Counter (PC) traces in a portion of the Alpha EV7 cache. This data enables the user to tell which instructions each Alpha EV7 CPU on the system has executed.

7.1. Overview of OCLA

OCLA enables the user to tell which instructions each Alpha EV7 CPU has executed by setting aside one seventh of the Alpha EV7 cache as acquisition memory which stores the virtual addresses of instructions executed by the Alpha EV7 CPU. The acquisition memory in the cache can later be analyzed with an SDA extension.

The acquisition of instructions can be enabled or disabled while the system is running, thereby allowing the acquisition of instruction streams for a given period of time without the need to restart the system.

If the OCLA is enabled and started, and your system subsequently fails due to a crash, the current acquisition memory is automatically saved to the system dump file. The instructions executed by each CPU prior to the system failure can then be analyzed with SDA. Upon restart of the system, the acquisition memory in the EV7 is still there and can be copied into system memory using the OCLA ENABLE and OCLA DUMP commands.

If the STOP/CPU command is issued on a CPU for which OCLA has been enabled, OCLA is automatically disabled if the CPU is allowed to leave the active set. When a CPU is started with the START/CPU command, OCLA is not automatically enabled; rather, it must be enabled using SDA.

Table 7.1 summarizes the SDA commands and qualifiers for the OCLA utility.

7.2. SDA OCLA Commands

Table 7.1. SDA Commands for the OCLA Utility

Commands	Description
OCLA ENABLE	Enables the OCLA. The command reserves one seventh of the EV7 cache as acquisition memory for instructions.
OCLA DISABLE	Disables the OCLA and returns the cache set to the Alpha EV7 CPU.
OCLA DUMP	Copies the acquisition memory in the Alpha EV7 cache to a region in system space for later analysis by SDA.
OCLA HELP	Provides online help about OCLA commands.
OCLA LOAD	Loads the OCLA\$PCTRACE executable. This must be done prior to enabling any OCLA.
OCLA SET REGISTER/RESET	Resets OCLA registers to the default values.
OCLA SHOW REGISTER	Displays detailed information about the OCLA registers.

Commands	Description
OCLA SHOW STATUS	Displays the status of an OCLA.
OCLA SHOW TRACE	Decodes the acquired compressed instruction stream and displays it.
OCLA START	Starts the acquisition of instructions into the acquisition memory.
OCLA STOP	Stops the acquisition of instructions.
OCLA UNLOAD	Unloads the OCLA\$PCTRACE execlset and returns the acquisition buffers to the system.

7.2.1. OCLA DISABLE

Disables the OCLA and returns the cache set to the Alpha EV7 CPU.

Format

```
OCLA DISABLE [/CPU=n]
```

Parameters

None.

Qualifier

/CPU=n

Specifies the CPU on which OCLA should be disabled. If this qualifier is omitted, OCLA is disabled on every CPU in the system.

7.2.2. OCLA DUMP

Copies the acquisition memory in the Alpha EV7 cache to a region in system space for later analysis by SDA. When a system fails, data collected in the EV7 cache is automatically saved in the system dump file for each enabled CPU. (See the OCLA SHOW TRACE command for more information.)

Format

```
OCLA DUMP [/CPU=n]
```

Parameters

None.

Qualifier

/CPU=n

Specifies the CPU for which to dump the acquisition memory. If this qualifier is omitted, the acquisition memory is dumped for all CPUs.

7.2.3. OCLA ENABLE

Enables the OCLA. Reserves one-seventh of the EV7 cache as acquisition memory for instructions.

Format

```
OCLA ENABLE [/CPU=n] [/RESET]
```

Parameters

None.

Qualifiers

/CPU=*n*

Specifies the CPU on which to enable OCLA. If this qualifier is omitted, OCLA is enabled on every CPU in the system.

/RESET

Initializes the OCLA to default values.

Under certain circumstances, the OCLA might not be initialized properly when the system is powered on. For more information, see the OCLA SHOW REGISTER command.

If you wish to reset only certain registers to default values, use the OCLA SET REGISTER/RESET command.

7.2.4. OCLA HELP

Provides online help on OCLA commands.

Format

```
OCLA HELP
```

Parameters

None.

Qualifiers

None.

7.2.5. OCLA LOAD

Loads the OCLA\$PCTRACE execlt. This must be done before enabling any OCLA.

Format

```
OCLA LOAD
```

Parameters

None.

Qualifiers

None.

7.2.6. OCLA SET REGISTER

Resets a specified OCLA register to its default value. The /RESET qualifier is required for this operation.

Format

OCLA SET REGISTER /RESET keyword

Parameter

keyword

Specifies which OCLA register to reset to its default value. The valid keywords are as follows:

MISC	OCLA 1 miscellaneous register
OCLA1_CTL	OCLA 1 control register
PC_CTL	OCLA 1 PC control register
SMASK	OCLA 1 select mask register
SMATCH	OCLA 1 select match register
TMASK	OCLA 1 trigger mask register
TMATCH	OCLA 1 trigger match register

Note

You cannot reset all registers using a single command if OCLA has already been enabled. You must first disable OCLA using the OCLA DISABLE command. You can then reset all the registers by performing an OCLA ENABLE/RESET command.

Qualifier

/RESET

This qualifier is required to reset the specified register to its default value.

7.2.7. OCLA SHOW REGISTER

Displays detailed information about OCLA registers.

Format

OCLA SHOW REGISTER [/CPU=n]

Parameter

None.

Qualifier

/CPU=n

Specifies the CPU for which to display registers. If this qualifier is omitted, registers are displayed for all CPUs.

Example

```

SDA> SHOW REGISTER/CPU=7
OCLA EV7 CPU Registers for CPU: 07
-----
ZBOX control register for CPU 07: 00000000ffffffff
CBOX control register for CPU 07: 078000001024a807
OCLA 1 MISC register for CPU 07: 0000000000000000

OCLA 1 TMATCH: 40000002ffffffff
OCLA 1 SMATCH: 0000000000000000
OCLA 1 PC_TMATCH: 0000000000000000
OCLA 1 PC_SMATCH: 0000000000000000

OCLA 1 TMASK: 4000000000000000
OCLA 1 SMASK: 0000000000000000
OCLA 1 PC_TMASK: 0000000000000000
OCLA 1 PC_SMASK: 0000000000000000

OCLA 1 control register for CPU 07: 8000210000000000
Enab Run  RDRST ITRIG IFULL TAG_EN TS_EN PDAT_EN SFILT TMODE IRQF IRQT
TIHANG
  1  0    0    0    0    0    0    0    0    00  00  0  0
  0
TAG_SRC EXT_SRC TS_FORCE EIO WRAP SREL  AMATCH  AADDR
  000    004    0  0    1  0    0000  0000

OCLA 1 PC Control register for CPU 07: 000000000000003f
STGSEL TRGSEL OUTSEL CDEPTH  CMASK CAMEN
  03    03    03    00    0000    0

```

This command displays all OCLA-related registers on the EV7 CPU. This particular CPU was enabled with the /RESET qualifier, so the values have default settings.

7.2.8. OCLA SHOW STATUS

Displays the status of an OCLA.

Format

OCLA SHOW STATUS [/CPU=n]

Parameters

None.

Qualifiers

/CPU=n

Specifies the CPU for which to show OCLA status. If this qualifier is omitted, status is displayed for all CPUs.

Example

```
SDA> OCLA SHOW STATUS
EV7 OCLA status
-----
CPU 00 is enabled, no entries, no dump done
CPU 01 is enabled, no entries, no dump done
CPU 02 is enabled, no entries, no dump done
CPU 03 is enabled, no entries, no dump done
CPU 04 is enabled, no entries, no dump done
CPU 05 is enabled, no entries, no dump done
CPU 06 is enabled, no entries, no dump done
CPU 07 is enabled, running, no entries, no dump done
```

7.2.9. OCLA SHOW TRACE

Decodes the acquired compressed instruction stream and displays it.

Format

```
OCLA SHOW TRACE [/CPU=n] [/LAST=n][/NOPAL][/REVERSE][/SUMMARY][/SYMBOLIZE]
```

Parameters

None.

Qualifiers

/CPU=n

Specifies the CPU for which to show data. If this qualifier is omitted, trace data is displayed for all CPUs.

/LAST=n

Displays the last n instructions. If this qualifier is omitted, trace data is displayed for all instructions.

/NOPAL

Do not include PAL code when displaying instructions.

/REVERSE

Displays the instructions in reverse order.

/SUMMARY

Displays the last 42 instructions.

/SYMBOLIZE

Attempts to symbolize each instruction.

Example

```
SDA> OCLA SHOW TRACE/CPU=7/SUMMARY/SYMBOLIZE
OCLA PC trace information for CPU 07
-----
CPU 07 has 16384 valid entries
42 PC values displayed
0000002c00030358 ,PAL Code
0000002c0003035c ,PAL Code
ffffffff81244c94 OCLA$DEBUG+00C94
ffffffff81244c98 OCLA$DEBUG+00C98
ffffffff81244c9c OCLA$DEBUG+00C9C
ffffffff81244ca0 OCLA$DEBUG+00CA0
ffffffff81244ca4 OCLA$DEBUG+00CA4
ffffffff81244ca8 OCLA$DEBUG+00CA8
ffffffff81244cac OCLA$DEBUG+00CAC
ffffffff81244cb0 OCLA$DEBUG+00CB0
ffffffff81244cd0 OCLA$DEBUG+00CD0
ffffffff81244cd4 OCLA$DEBUG+00CD4
ffffffff81244cd8 OCLA$DEBUG+00CD8
ffffffff81244cdc OCLA$DEBUG+00CDC
ffffffff81244ce0 OCLA$DEBUG+00CE0
...
```

This example shows a summary of the last PC instructions executed by CPU 7 and symbolizes the PC values.

In this example, lines of PAL code are identified by ",PAL Code".

7.2.10. OCLA START

Starts the acquisition of instructions into acquisition memory.

Format

```
OCLA START [/CPU=n]
```

Parameters

None.

Qualifiers

/CPU=n

The CPU on which to start instruction acquisition. If this qualifier is omitted, instruction acquisition is started on all CPUs.

7.2.11. OCLA STOP

Stops the acquisition of instructions.

Format

```
OCLA STOP [/CPU=n]
```

Parameters

None.

Qualifiers

/CPU=*n*

Specifies the CPU on which to stop acquisition. If this qualifier is omitted, acquisition is stopped on all CPUs.

7.2.12. OCLA UNLOAD

Unloads the OCLA\$PCTRACE execllet and returns the acquisition buffers to the system.

Format

```
OCLA UNLOAD
```

Parameters

None.

Qualifiers

None.

Examples

- SDA> OCLA DUMP
OCLA PC trace performed for 8 CPUs
SDA> OCLA SHOW TRACE/SUMMARY/SYMBOLIZE/CPU=0
OCLA PC trace information for CPU 00

CPU 00 has 16384 valid entries
The overhead per allocation is 1208
42 PC values displayed
ffffffff8012d3ac SCH\$CALC_CPU_LOAD_C+0030C
ffffffff8012d3b0 SCH\$CALC_CPU_LOAD_C+00310
ffffffff8012d3b4 SCH\$CALC_CPU_LOAD_C+00314
ffffffff8012d3b8 SCH\$CALC_CPU_LOAD_C+00318
ffffffff8012d3bc SCH\$CALC_CPU_LOAD_C+0031C
ffffffff8012d3c0 SCH\$CALC_CPU_LOAD_C+00320
ffffffff8012d4d8 SCH\$CALC_CPU_LOAD_C+00438
...

This series of commands demonstrates how you can use the OCLA SDA extension to interactively inspect a running system by reading the EV7 acquisition memory. The second command copies the EV7 acquisition cache memory into system memory and displays the collected values for CPU 0.

2. SDA> OCLA LOAD
OCLA\$PCTRACE load status = 00000001

SDA> OCLA ENABLE/RESET
OCLA PC tracing enabled for 8 CPUs

SDA> OCLA START
OCLA PC tracing started for 8 CPUs

The series of commands in this example demonstrates how to load the OCLA execlt, enable the OCLA SDA extensions on each CPU in the system, and start each OCLA. Once started, the EV7 OCLA extensions collect data for each PC instruction executed by the active CPUs in the system.

In the unlikely event of a system failure, PC values recorded by the OCLA extensions are stored in the system dump file and can later be retrieved by using the System Dump Analyzer (SDA).

3. SDA> OCLA STOP
OCLA PC tracing stopped for 8 CPUs

SDA> OCLA DISABLE
OCLA PC tracing disabled for 8 CPUs

SDA> OCLA UNLOAD
OCLA\$PCTRACE unload status = 00000001

This series of commands stops all running OCLA extensions, disables and frees up system memory associated with each OCLA, and unloads the OCLA execlt from system memory.

Chapter 8. SDA SPL Extension

This chapter presents an overview of the SDA Spinlock Tracing (SPL) Utility and describes the SDA Spinlock Tracing commands.

8.1. Overview of the SDA Spinlock Tracing Utility

To synchronize access to data structures, the OpenVMS operating system uses a set of static and dynamic spinlocks, such as IOLOCK8 and SCHED. The operating system acquires a spinlock to synchronize data, and at the end of the critical code path the spinlock is then released. If a CPU attempts to acquire a spinlock while another CPU is holding it, the CPU attempting to acquire the spinlock has to spin, waiting until the spinlock is released. Any lost CPU cycles within such a spinwait loop are charged as MPsynch time.

By using the MONITOR utility, you can monitor the time in process modes, for example, with the command `$ MONITOR MODES`. A high rate of MP synchronization indicates contention for spinlocks. However, until the implementation of the Spinlock Tracing utility, there was no way to tell which spinlock was heavily used, and who was acquiring and releasing the contended spinlocks. The Spinlock Tracing utility allows a characterization of spinlock usage. It can also collect performance data for a given spinlock on a per-CPU basis.

This tracing ability is built into the system synchronization execlt, which contains the spinlock code, and can be enabled or disabled while the system is running. There is no need to reboot the system to load a separate debug image. The images that provide spinlock tracing functionality are as follows:

```
SYSS$LOADABLE_IMAGES:SPL$DEBUG.EXE
```

```
SYSS$SHARE:SPL$SDA.EXE
```

The SDA> prompt provides the command interface. From this command interface, you can load and unload the spinlock debug execlt using `SPL LOAD` and `SPL UNLOAD`, and start, stop and display spinlock trace data. This allows you to collect spinlock data for a given period of time without system interruption. Once information is collected, the trace buffer can be deallocated and the execlt can be unloaded to free up system resources. The spinlock trace buffer is allocated from S2 space and pages are taken from the free page list.

Should the system crash while spinlock tracing is enabled, the trace buffer is dumped into the system dump file, and it can later be analyzed using the spinlock trace utility. This is very useful in tracking down CPUSPINWAIT bugcheck problems.

Note that by enabling spinlock tracing, there is a performance impact. The amount of the impact depends on the amount of spinlock usage.

8.2. How to Use the SDA Spinlock Tracing Utility

The following steps will enable you to collect spinlock statistics using the Spinlock Tracing Utility.

1. Load the Spinlock Tracing Utility execlt.

```
SDA> SPL LOAD
```

2. Allocate a trace buffer and start tracing.

```
SDA> SPL START TRACE
```

3. Wait a few seconds to allow some tracing to be done, then find out which spinlocks are incurring the most acquisitions and the most spinwaits.

```
SDA> SPL SHOW TRACE/SUMMARY
```

For example, you might see contention for the SCHED and IOLOCK8 spinlocks (a high acquisition count, with a significant proportion of the acquisitions being forced to wait).

4. Look to see if the spinlocks with a high proportion of spinwaits caused a significant delay in the acquisition of the spinlock. You must now collect more detailed statistics on a specific spinlock.

```
SDA> SPL START COLLECT/SPINLOCK=SCHED
```

This command accumulates additional data for the specified spinlock. As long as tracing is not stopped, collection will continue to accumulate spinlock-specific data from the trace buffer.

5. Display the additional data collected for the specified spinlock.

```
SDA> SPL SHOW COLLECT
```

This display includes the average hold time of the spinlock and the average spinwait time while acquiring the spinlock.

6. Repeat steps 4 and 5 for each spinlock that has contention. A START COLLECT cancels the previous collection.
7. Disable spinlock tracing when you have collected all the needed spinlock statistics and release all the memory used by the Spinlock Tracing utility with the following commands.

```
SDA> SPL STOP COLLECT  
SDA> SPL STOP TRACE  
SDA> SPL UNLOAD
```

8.3. Example Command Procedure for Collection of Spinlock Statistics

The following example shows a command procedure that can be used for gathering spinlock statistics:

```
$ analyze/system  
spl load  
spl start trace/buffer=1000  
wait 00:00:15  
spl stop trace  
read/executive/nolog  
set output spl_trace.lis  
spl analyze  
spl show trace/summary  
spl start collect/spin=sched  
wait 00:00:05
```

```
spl show collect
spl start collect/spin=iolock8
wait 00:00:05
spl show collect
spl start collect/spin=lckmgr
wait 00:00:05
spl show collect
spl start collect/spin=mmg
wait 00:00:05
spl show collect
spl start collect/spin=timer
wait 00:00:05
spl show collect
spl start collect/spin=mailbox
wait 00:00:05
spl show collect
spl start collect/spin=perfmon
wait 00:00:05
spl show collect
spl stop collect
spl unload
exit
$ exit
```

A more comprehensive procedure is provided as `SYSEXAMPLES:SPL.COM`.

8.4. SDA Spinlock Tracing Commands

The SPL commands are described below.

8.4.1. SPL

Invokes the Spinlock Tracing Utility.

When entered by itself with no command keyword, the SPL command lists the SPL command options.

```
SDA> SPL
```

8.4.2. SPL ANALYZE

Analyzes collected spinlock data and presents the most relevant data.

Format

```
SPL ANALYZE [/[NO]CPU_STATISTICS |/[NO]PLATFORM | //[NO]HOLD_TIMES=n/[NO]WAIT_
```

Parameters

None.

Qualifiers

`/CPU_STATISTICS` (default)

/NOCPU_STATISTICS

Displays per-CPU statistics.

/HOLD_TIMES=n**/NOHOLD_TIMES=n**

Displays occurrences of spinlocks held longer than n microseconds. The default is 1000 microseconds.

/PLATFORM (default)**/NOPLATFORM**

Displays system platform information.

/USAGE=(HOLD=n,SPIN=n, TOP_PCS=n)

Specifies thresholds for displaying information on a spinlock. If the percentage of time a spinlock is held exceeds the value of HOLD=n, where n is a value from 0 to 100, displays the information on the spinlock. The default is 10%. If the percentage of time a spinlock is spinning exceeds the value of SPIN=n, displays the information on the spinlock. The default is 10%. If either the HOLD or SPIN thresholds are exceeded, displays information on a spinlock. The TOP_PCS=n keyword displays the top n unique callers to lock a spinlock. The default is to display the top five unique callers.

By specifying either /USAGE=(HOLD=0) or /USAGE=(SPIN=0), SPL displays information on all spinlock usage from the trace buffer.

/WAIT_TIMES=n**/NOWAIT_TIMES=n**

Displays occurrences of spinlocks held longer than n microseconds. The default is 1000 microseconds.

Description

The SPL ANALYZE command analyzes collected spinlock data and displays the most relevant data.

The SPL ANALYZE command provides an overview of SPINLOCK usage on a system. Data are provided by CPU and by spinlock. When looking at a system with high MP_Synch time, this is a good command to start with. Stop spinlock tracing before using this command.

Example

```
SDA> SPL ANALYZE/HOLD=50/WAIT=50/USAGE=HOLD=5
```

```
Spinlock Analysis (1)
```

```
Platform
```

```
-----
```

```
Node: CLU21
```

```
Hardware: AlphaServer ES45 Model 2
```

```
Active CPUs: 4
```

```
Memory: 16.00 GB
```

```
CPU Frequency: 1.000 GHz
```


Trace Buffer: 1280 pages (10.00 MB)
 Trace Time: 0.48 seconds
 Trace Start: 15-OCT 10:51:53.427386

CPU statistics (2)

CPU ID	% Time in Fork Dispatcher	% Time Spinlocks Held	% Time MP_Synch	All Spinlocks Acquires/sec	All Spinlocks Waits/sec
00	0.1	16.2	1.1	82210.4	1434.7
01	0.1	15.8	1.2	79551.5	1548.3
02	0.0	16.4	1.2	85690.9	1511.1
03	1.7	17.7	1.1	86601.3	1451.2
Total	1.9	66.1	4.6	334054.1	5945.3

Spinlock Usage (3)

Spinlock	% Time Held	Acquires/sec	Average Hold	% Time Spinning	Waits/sec	Average Spin	Spin to Hold Ratio
FILSYS	15.6	33776.8	4609	2.6	2314.1	11379	0.2
LCKMGR	9.3	26198.6	3560	1.2	2208.8	5494	0.1
PCB\$00000426	7.2	49420.4	1451	0.0	35.1	6342	0.0
PCB\$00000428	7.1	49125.2	1437	0.0	14.5	7532	0.0

Spinlock (4)

Spinlock	Caller's PC	% Time Held	Acquires /sec	Average	Spinwaits /sec	Average Spinwait
FILSYS						
	8022CA44 SEARCH_FCB_C+00604	12.0	4021.3	29793	303.5	11985
	80222E10 SET_DIRINDX_C+00030	0.5	4194.7	1163	247.7	11477
	8021B06C START_REQUEST_C+0006C	0.4	2438.0	1607	384.0	15838
	8021B208 FINISH_REQUEST_C+00058	0.4	2440.1	1510	206.4	15862
	800FC508 IOC_STD\$MAPVBLK_C+000C8	0.3	2014.8	1713	402.5	9518
LCKMGR						
	801DEB14 EXE\$ENQ_C+00A44	3.5	12984.7	2657	988.8	5727
	801E3B94 EXE\$DEQ_C+00114	3.0	5943.2	5109	538.8	4849
	801E03BC LOCKING+023BC	2.6	5941.2	4315	392.2	5682
	801E5C84 LCK\$DEQLOCK_C+00F54	0.3	1323.2	2091	289.0	5642
PCB\$00000426						
	801782F8 SCH\$ASTDEL_C+00078	1.9	15525.9	1256	0.0	0
	80179AC4 SCH\$QAST_C+00094	1.7	8907.6	1935	0.0	0
	8017A780 SCH\$QUEUE_AST_CURRENT_C+00070	1.2	7859.0	1532	0.0	0
	80178FE0 SCH\$ASTDEL_K_C+00090	1.2	8895.3	1320	8.3	2346
	80179124 SCH\$ASTDEL_K_C+001D4	1.1	7780.5	1355	0.0	0
PCB\$00000428						
	801782F8 SCH\$ASTDEL_C+00078	2.0	15606.4	1308	0.0	0
	80179AC4 SCH\$QAST_C+00094	1.6	8810.6	1794	0.0	0
	80178FE0 SCH\$ASTDEL_K_C+00090	1.2	8810.6	1344	6.2	2589
	8017A780 SCH\$QUEUE_AST_CURRENT_C+00070	1.2	7904.4	1492	0.0	0
	80179124 SCH\$ASTDEL_K_C+001D4	1.0	7728.9	1340	0.0	0
	8017A780 SCH\$QUEUE_AST_CURRENT_C+00070	1.1	8655.8	1298	0.0	0
	80179124 SCH\$ASTDEL_K_C+001D4	1.1	8598.0	1225	0.0	0
	80178FE0 SCH\$ASTDEL_K_C+00090	1.1	9192.5	1144	2.1	2326

Long Spinlock Hold Times (> 50 microseconds) (5)

Timestamp	CPU	Spinlock Forklock	Calling PC Forking PC	EPID	Hold (us)
15-OCT 10:51:53.801244	00	81D6A200 81D6A200	8051B380 LAN\$COMPLETE_VCRP_CSMACD_C+00	00000000	64
15-OCT 10:51:53.538665	00	818BBE00 POOL	8004B334 EXE\$ALONPAGVAR_C+002F4	00000000	59
15-OCT 10:51:53.538331	03	81F75980 PCB\$00000429	8017A808 SCH\$QUEUE_AST_CURRENT_C+000F8	00000000	56
15-OCT 10:51:53.597448	03	818BBE00 POOL	8004B334 EXE\$ALONPAGVAR_C+002F4	00000000	52
15-OCT 10:51:53.670228	03	818BBE00 POOL	8004B334 EXE\$ALONPAGVAR_C+002F4	00000000	51

Long Spinlock Wait Times (> 50 microseconds) (6)

Timestamp	CPU	Spinlock Forklock	Calling PC Forking PC	EPID	Wait (us)
15-OCT 10:51:53.454082	03	818BCB00 FILSYS	800FC508 IOC_STD\$MAPVBLK_C+000C8	00000000	79
15-OCT 10:51:53.661343	02	818BCB00 FILSYS	8021B208 FINISH_REQUEST_C+00058	00000000	76
15-OCT 10:51:53.661256	00	818BCB00 FILSYS	8021EDD0 F11BXQP+08DD0	00000000	66
15-OCT 10:51:53.898618	00	818BCB00 FILSYS	8021B06C START_REQUEST_C+0006C	00000000	53

This example shows the output of the SPL ANALYZE command, which is divided into several sections:

1. Spinlock Analysis:

Shows information on the platform such as the hardware type, the number of CPUs and the speed of the CPUs.

2. CPU Statistics:

Shows spinlock information on a per CPU basis. The percentage of time the CPU owns spinlock is displayed along with a percentage of time the CPU was executing from the fork dispatcher. This information can be very useful in determining the amount of time a CPU is in use for processing I/O.

3. Spinlock Usage:

Shows information on the spinlock usage by the system. This data is sorted by the percentage of time the spinlocks are held. The average hold time displayed is in system cycles. The display also includes the percent of time that CPUs are waiting on this spinlock along with the average number of cycles a CPU needed to wait before it was able to acquire the spinlock.

4. Spinlock:

For each spinlock displayed in section 3, the top callers are displayed sorted by the number of acquires per second that occurred. In addition, the average hold and wait time for each caller is displayed in system cycles.

5. Long Spinlock Hold Times:

The section on Long Spinlock Hold Times shows occurrences of spinlocks whose hold time exceeded a threshold. In the above report, the threshold was specified as 50 microseconds. The EPID at the time of the acquire is also displayed. An EPID of 0 indicates that the spinlock acquire did not occur in process context.

6. Long Spinlock Wait Times:

The section on Long Spinlock Wait Times shows occurrences of spinlocks whose wait time exceeded a threshold. In the above report, the threshold was specified as 50 microseconds. The EPID at the time of the acquire is also displayed. An EPID of 0 indicates that the spinlock acquire did not occur in process context.

8.4.3. SPL LOAD

Loads the SPL\$DEBUG execlt. This must be done prior to starting spinlock tracing.

Format

SPL LOAD

Parameters

None.

Qualifiers

None.

Description

The SPL LOAD command loads the SPL\$DEBUG execlt, which contains the tracing routines.

Example

```
SDA> SPL LOAD
```

```
SPL$DEBUG load status = 00000001
```

8.4.4. SPL SHOW COLLECT

Displays the collected spinlock data.

Format

```
SPL SHOW COLLECT [ /RATES | /TOTALS ]
```

Parameters

None.

Qualifiers

/RATES

Reports activity as a rate per second and hold/spin time as a percentage of time. This is the default.

/TOTALS

Reports activity as a count and hold/spin time as cycles.

Description

The SPL SHOW COLLECT command displays the collected spinlock data. It displays first a summary on a per-CPU basis, followed by the callers of the specific spinlock. This second list is sorted by the top consumers of the spinlock (in percent of time held). These displays show average spinlock hold and spinlock wait time in system cycles.

Example

```
SDA> SPL SHOW COLLECT
```

```
Spinlock Trace Information for SCHED:
```

CPU ID	% Time Held	Acquires/sec	Average Hold	% Time Spinning	Waits/sec	Average Spin	Spin to Hold Ratio
08	4.6	1651.4	8296	0.3	298.2	2601	0.06
09	4.9	1941.8	7578	0.2	276.3	1841	0.03
10	4.0	1593.5	7454	0.1	225.4	1794	0.03
11	5.2	2185.6	7185	0.2	272.8	1924	0.03
12	5.4	2105.1	7702	0.2	271.3	2012	0.03
13	5.7	6131.5	2785	2.5	2288.8	3330	0.45
	29.7	15608.8	6833	3.5	3632.8	2250	0.12

```
Spinlock Trace Information for SCHED: ( 6-DEC-2001 09:01:52.26, 3.3 nsec, 300 MHz)
```

Caller's PC	% Time Held	Acquires /sec	Maximum	Minimum	Average	Spinwaits /sec	Average Spinwait	% Time Spin
80342384 LCK\$SND_CVTRQ_C+00344	17.1	5758.4	26384	3531	8912	65.7	3181	0.1
8012D53C SCH\$IDLE_C+0024C	5.3	2614.5	20897	1384	6134	1083.3	1524	0.5
80347BB0 LCK\$DEALLOC_LKB_C+00220	5.2	5880.6	7767	472	2641	2248.5	3332	2.5
80151F84 SCH\$INTERRUPT+00064	0.5	214.1	15564	1619	6895	35.3	6092	0.1
80343FB8 LCK\$SND_LOCKREQ_C+00148	0.4	137.8	24063	4716	9509	0.0	0	0.0
801375C0 SCH\$QEND_C+00080	0.3	228.9	12107	2474	4251	29.0	3315	0.0

8.4.5. SPL SHOW TRACE

Displays spinlock tracing information.

Format

```
SPL SHOW TRACE [ /[NO]ACQUIRE | /CPU=n  
| /[NO]FORKLOCK=forklock | /[NO]FRKDSPH  
| /[NO]FRKEND | /RATES | /[NO]RELEASE  
| /[NO]SPINLOCK=spinlock | /SUMMARY  
| /TOP=n | /TOTALS | /[NO]WAIT ]
```

Parameters

None.

Qualifiers

/ACQUIRE

/NOACQUIRE

The **/ACQUIRE** qualifier displays any spinlock acquisitions.

The **/NOACQUIRE** qualifier ignores any spinlock acquisitions.

/CPU=n

Specifies the display of information for a specific CPU only, for example, **/CPU=5** or **/CPU=PRIMARY**. By default, all trace entries for all CPUs are displayed.

/FORKLOCK=*forklock*

/NOFORKLOCK

The **/FORKLOCK=*forklock*** qualifier specifies the display of a specific forklock, for example, **/FORKLOCK=IOLOCK8** or **/FORKLOCK=IPL8**.

The **/NOFORKLOCK** qualifier specifies that no forklock trace information be displayed. By default, all fork trace entries are decoded and displayed.

/FRKDSPH

/NOFRKDSPH

The **/FRKDSPH** qualifier displays all invocations of fork routines within the fork dispatcher. This is the default.

The **/NOFRKDSPH** qualifier ignores all of the operations of the **/FRKDSPH** qualifier.

/FRKEND

/NOFRKEND

The /FRKEND qualifier displays all returns from fork routines within the fork dispatcher. This is the default.

The /NOFRKEND qualifier ignores all operations of the /FRKEND qualifier.

/RATES

Reports activity as a rate per second and hold/spin time as a percentage of time. This is the default.

/RELEASE**/NORELEASE**

The /RELEASE qualifier displays any spinlock releases.

The /NORELEASE qualifier ignores any spinlock releases.

/SPINLOCK=*spinlock***/NOSPINLOCK**

The /SPINLOCK=*n* qualifier specifies the display of a specific spinlock, for example, /SPINLOCK=LCKMGR or /SPINLOCK=SCHED.

/NOSPINLOCK specifies that no spinlock trace information be displayed. By default, all spinlock trace entries are decoded and displayed.

/SUMMARY

Steps through the entire trace buffer and displays a summary of all spinlock and forklock activity. It also displays the top ten callers.

/TOP=*n*

Displays a different number other than the top ten callers or fork PCs. By default, the top ten are displayed. This qualifier is useful only when you also specify /SUMMARY.

/TOTALS

Reports activity as a count and hold/spin time as cycles.

/WAIT**/NOWAIT**

The /WAIT qualifier displays any spinwait operations.

The /NOWAIT qualifier ignores any spinwait operations.

Description

The SPL SHOW TRACE command displays spinlock tracing information. The latest acquired or released spinlock is displayed first, and then the trace buffer is stepped backwards in time.

By default, all trace entries will be displayed, but you can use qualifiers to select only certain entries.

Since this is not a time critical activity and a table lookup has to be done anyway to translate the SPL address to a spinlock name, commands like `/SPINLOCK=(SCHED,IOLOCK8)` do work. `/SUMMARY` will step the entire trace buffer and display a summary of all spinlock activity, along with the top-ten callers' PCs. You can use `/TOP=n` to display a different number of the top ranked callers.

Examples

Spinlock Trace Information:

Timestamp	CPU	Spin/Forklock/IPL	Caller's/Fork PC	EPID	Operation	Trace Buffer	
1	2	3	4	5	6	7	
23-JAN 15:32:03.223052	05	810B2200	MMG	80175594	MMG_STD\$IOLOCK_BUF_C+00214	00000568 Release	FFFFFFFF.05F635E0
23-JAN 15:32:04.794732	0B	810B2900	FILSYS	800F4340	IOC_STD\$MAPVBLK_C+002A0	0000056E Restore	FFFFFFFF.05F635C0
23-JAN 15:32:05.307011	0D	810B2200	MMG	8017B154	SYS\$VM+17154	00000570 Release	FFFFFFFF.05F635A0
23-JAN 15:32:05.307497	09	810B2100	SCHED	80144770	PROCESS_MANAGEMENT+2A770	00000000 Release	FFFFFFFF.05F63580
23-JAN 15:32:05.306490	0E	810B2200	MMG	8017550C	MMG_STD\$IOLOCK_BUF_C+0018C	00000571 Acquire (spin)	FFFFFFFF.05F63560
23-JAN 15:32:05.307951	00	810B2200	MMG	80175D9C	MMG_STD\$IOUNLOCK_BUF_C+000	00000000 Acquire (spin)	FFFFFFFF.05F63540
23-JAN 15:32:05.818853	0E	810B2200	MMG	80175594	MMG_STD\$IOLOCK_BUF_C+00214	00000571 Release	FFFFFFFF.05F63520
23-JAN 15:32:05.819422	0C	810B2100	SCHED	8011F53C	SCH\$CALC_CPU_LOAD_C+0049C	00000000 Acquire (spin)	FFFFFFFF.05F63500
23-JAN 15:32:05.819374	0D	810B2100	SCHED	8014C0E8	EXE\$SYNCH_LOOP_C+00458	00000570 Acquire (spin)	FFFFFFFF.05F634E0
23-JAN 15:32:05.818851	0E	810B2200	MMG	8017550C	MMG_STD\$IOLOCK_BUF_C+0018C	00000571 Acquire	FFFFFFFF.05F634C0
23-JAN 15:32:05.820320	00	810B2100	SCHED	801473A0	SCH\$QAST_C+004F0	00000000 Acqnoipl	FFFFFFFF.05F634A0
23-JAN 15:32:05.819370	0D	810B2700	IOLOCK8	800FFB30	EXE_STD\$INSIOQ_C+002B0	00000570 Release	FFFFFFFF.05F63480
23-JAN 15:32:05.819415	0C	810B2100	SCHED	8011F370	SCH\$CALC_CPU_LOAD_C+002D0	00000000 Release	FFFFFFFF.05F63460
23-JAN 15:32:05.820316	00	8994FE00	???	80146F44	SCH\$QAST_C+00094	00000000 Acquire (nospin)	FFFFFFFF.05F63440
23-JAN 15:32:05.820314	00	810B2200	MMG	80175DC0	MMG_STD\$IOUNLOCK_BUF_C+000	00000000 Restore	FFFFFFFF.05F63420
23-JAN 15:32:05.820312	00	810B2200	MMG	80175D9C	MMG_STD\$IOUNLOCK_BUF_C+000	00000000 Acquire	FFFFFFFF.05F63400
23-JAN 15:32:05.819409	0C	810B2100	SCHED	8014C0E8	EXE\$SYNCH_LOOP_C+00458	0000056F Acquire	FFFFFFFF.05F63380

Callout	Meaning
1	Shows timestamps that are collected as system cycle counters (SCC) and then displayed with an accuracy down to microseconds. Each CPU is incrementing its own SCC as soon as it is started, so there is some difference between different CPUs' system cycle counters. The standard system time is incremented only every 10 Msec and as such is not exact enough. Adjusting the SCC to the specific CPU's system time and translating it into an accurate timestamp will thus sometimes display times out of order for different CPUs. However, for the same CPU ID, the timestamps are accurate.
2	Shows the physical CPU ID of the CPU logging the trace entry.
3	Shows the address of the spinlock fork. If it is a static one, its name is displayed; otherwise, it is marked as ???.
4	Shows the caller's PC address that acquired or released the spinlock, or the fork PC if the trace entry is a forklock. Symbolization is attempted, so a READ/EXECUTIVE might help to display a routine name, instead of simply a module and offset.
5	Shows the EPID, which is the external PID of the process generating the trace entry. If an interrupt or fork was responsible for the entry, then a zero EPID is displayed.
6	Shows the trace operation. For a spinlock, which was acquired without going through a spinwait,

Callout	Meaning
	there is a matching acquire/release pair of trace entries for the same CPU ID for a given spinlock. If a spinlock is held, it cannot be acquired immediately, so there is also a spinwait trace entry for this pair. The different variations of the acquire and release operations are distinguished, as are the same spinlocks if they are acquired recursively multiple times.
7	Shows the address of the trace buffer entry, in case there is a need to access the raw and undecoded trace data.

SDA> SPL SHOW TRACE/SUMMARY **8**

Spinlock Trace Information: (at 6-DEC-2001 09:01:47.02, trace time 00:00:01.415159)

Spinlock	Events /sec	Acquires /sec	Releases /sec	Acq Own /sec	Acq NoSpin /sec	Spinwaits /sec	% Spinwait
EMB	1.4	0.7	0.7	0.0	0.0	0.0	0.0
MEGA	1.4	0.7	0.7	0.0	0.0	0.0	0.0
HWCLK	2049.2	1024.6	1024.6	0.0	0.0	0.0	0.0
INVALIDATE	221.9	110.9	110.9	0.0	0.0	0.0	0.0
MAILBOX	4.2	2.1	2.1	0.0	0.0	0.0	0.0
SCHED	34851.2	15609.6	15608.8	0.0	0.0	3632.8	23.3
MMG	1776.5	781.5	888.2	12.7	94.0	0.0	0.0
TIMER	308.1	154.0	154.0	0.0	0.0	0.0	0.0
TX_SYNCH	57.9	29.0	29.0	0.0	0.0	0.0	0.0
IOLOCK8	33944.6	15285.9	15292.3	6.4	0.0	3360.0	22.0
LCKMGR	53421.6	17816.4	17843.2	0.0	28.3	17733.7	99.4
FILSYS	278.4	139.2	139.2	0.0	0.0	0.0	0.0
QUEUEAST	5.7	2.8	2.8	0.0	0.0	0.0	0.0
???	41312.0	20538.3	20655.6	0.0	117.3	0.7	0.0
	168234.1	71495.8	71752.4	19.1	239.5	24727.3	34.5

Spinlock Trace Information: **9**

Spinlock	Events /sec	Acquires or Releases/sec	Spins /sec	% Spin	Own /sec	Caller's PC	Module	Offset
.								
.								
.								
SCHED	8129.1	5880.6 Acq/s	2248.5	38.2	0.0	80347BB0 LCK\$DEALLOC_LKB_C+00220	SYSSCLUSTER	00027BB0
SCHED	6186.6	6186.6 Rel/s	0.0	0.0	0.0	80152668 SCH\$INTERRUPT+00748	PROCESS_MANAGEMENT	0002A668
SCHED	5880.6	5880.6 Rel/s	0.0	0.0	0.0	80347C24 LCK\$DEALLOC_LKB_C+00294	SYSSCLUSTER	00027C24
SCHED	5824.1	5758.4 Acq/s	65.7	1.1	0.0	80342384 LCK\$SND_CVTREQ_C+00344	SYSSCLUSTER	00022384
SCHED	3697.8	2614.5 Acq/s	1083.3	41.4	0.0	8012D53C SCH\$IDLE_C+0024C	PROCESS_MANAGEMENT	0000553C
SCHED	2614.5	2614.5 Rel/s	0.0	0.0	0.0	8012D370 SCH\$IDLE_C+00080	PROCESS_MANAGEMENT	00005370
SCHED	444.5	368.9 Acq/s	75.6	20.5	0.0	80157E10 SCH\$POSTEF_C+00050	PROCESS_MANAGEMENT	0002FE10
SCHED	368.9	368.9 Rel/s	0.0	0.0	0.0	80157A70 SCH\$POSTEF_SCHED_C+00140	PROCESS_MANAGEMENT	0002FA70
SCHED	258.6	229.7 Acq/s	29.0	12.6	0.0	801375C0 SCH\$QEND_C+00080	PROCESS_MANAGEMENT	0000F5C0
SCHED	249.4	214.1 Acq/s	35.3	16.5	0.0	80151F84 SCH\$INTERRUPT+00064	PROCESS_MANAGEMENT	00029F84
MMG	154.8	154.8 Acq/s	0.0	0.0	0.0	80186AA4 MMG\$PAGEFAULT_C+000A4	SYSSVM	00014AA4
MMG	106.7	106.7 Acq/s	0.0	0.0	0.0	8017E658 MMG_STD\$SET_GH_AND_FASTMAP_6	SYSSVM	0000C658
MMG	106.7	106.7 Rel/s	0.0	0.0	0.0	8017E68C MMG_STD\$SET_GH_AND_FASTMAP_6	SYSSVM	0000C68C
MMG	88.3	88.3 Rel/s	0.0	0.0	0.0	80187024 MMG\$PAGEFAULT_C+00624	SYSSVM	00015024
MMG	77.7	77.7 Rel/s	0.0	0.0	0.0	8019E904 MMG_STD\$SETPRTPAG_64_C+002C4	SYSSVM	0002C904
.								
.								
.								

Callout	Meaning
8	Shows the summary information by stepping through the whole trace buffer, and displaying a single line of information for each spinlock. If the percent of spin wait is very high, then a spinlock is a candidate for high contention.
9	For each spinlock in the summary display, the top ten callers' PCs are displayed along with the number of spinlock acquisitions and releases, as

Callout	Meaning
	well as spinwait counts and the number of multiple acquisitions of the same spinlock.

Forklock Trace Information: (at 6-DEC-2001 09:01:47.02, trace time 00:00:01.415159) 10

```

-----
Forklock      Total      CPU ID
Events/sec    8          9          10         11         12         13
-----
IPL 08        2523.4     0.0      0.0      0.0      0.0      0.0  2523.4
TIMER         49.5      49.5     0.0     0.0     0.0     0.0   0.0
IOLOCK8       686.1     684.0    0.7     0.7     0.0     0.7   0.0
LCKMGR        3069.6    168.2    0.0     0.0     0.0     0.0 2901.4
QUEUEAST       2.8       0.0      0.7     0.0     1.4     0.7   0.0
-----
Totals        6331.4    901.7    1.4     0.7     1.4     1.4 5424.8
-----

```

Forklock Trace Information:

```

-----
Forklock      Event/sec  % Time Held  Average  Minimum  Maximum  Fork PC
-----
IPL 08        2523.4    16.7         19911    5761     66873   803F1490  SYS$PCADRIVER+05490
-----
Totals        2523.4    16.7
-----
TIMER         49.5      0.6          35812    504      813332  80050050  EXE$SWTIMER_FORK_C
-----
Totals        49.5      0.6
-----
IOLOCK8       496.1     1.1          6732     491      24046   805C4840  SYS$EWDRIIVER+04840
IOLOCK8       190.1     0.5          7619     1224     28993   805EEEC8  EXEC.FORK_C+00080
-----
Totals        686.1     1.6
-----
LCKMGR        3069.6    18.7         18268    3933     64563   8032E5E0  CNX$RCV_MSG_LCKMGR_FRK_C
-----
Totals        3069.6    18.7
-----
QUEUEAST       2.8       0.0          24885    20589    32203   802E4370  XFCCOMMONFORKDISPATCH_C
-----
Totals        2.8       0.0
-----
Totals        6331.4    37.6
-----

```

Callout	Meaning
10	The forklock summary displays the number of fork operations on a specific CPU for each forklock. For each forklock, the top ten fork PC addresses are displayed, along with the minimum, maximum and average duration of the fork operation in system cycles. The percent of time spent in a given fork routine is displayed along with the percent of time for the forklock.

8.4.6. SPL START COLLECT

Starts to collect spinlock information a longer period of time than will fit into the trace buffer.

Format

```
SPL START COLLECT [/SPINLOCK=spinlock | /ADDRESS=n]
```

Parameters

None.

Qualifiers

/ADDRESS=*n*

Specifies the tracing of a specific spinlock by address.

/SPINLOCK=*spinlock*

Specifies the tracing of a specific spinlock, for example, /SPINLOCK=LCKMGR or /SPINLOCK=SCHED.

Description

The SPL START COLLECT command starts a collection of spinlock information for a longer period of time than will fit into the trace buffer. You need to enable spinlock tracing before a spinlock collection can be started. On a system with heavy activity, the trace buffer typically can only hold a relatively small time window of spinlock information. In order to collect spinlock information over a longer time period, a collection can be started. The collection tries to catch up with the running trace index and save the spinlock information into a balanced tree within the virtual address space of the process performing the spinlock collection. Either use the name of a static spinlock, or supply the address of a dynamic spinlock, for which information should be gathered.

The trace entries are kept in the trace buffer, which is allocated from S2 space, hence there is no disruption, if tracing is started from within SDA and then the user exits from SDA. However, for the longer period data collection, the information is kept in process-specific memory, thus a user needs to stay within SDA; otherwise the data collection is automatically terminated by SDA's image rundown. You can collect data for two or more spinlocks simultaneously, by using a separate process for each collection.

Example

1. SDA> SPL START COLLECT
Use /SPINLOCK=name or /ADDRESS=n to specify which spinlock info needs to be collected...

This example shows that you need to supply either a spinlock name of a static spinlock, or the address of a dynamic spinlock, if you want to collect information over a long period of time.

2. SDA> SPL START COLLECT/SPINLOCK=LCKMGR

This example shows the command line to start to collect information on the usage of the LCKMGR spinlock.

8.4.7. SPL START TRACE

Enables spinlock tracing.

Format

```
SPL START TRACE [ /[NO]ACQUIRE | /BUFFER=pages | /CPU=n
| /[NO]FORKLOCK=forklock | /[NO]FRKDSPTH
| /[NO]FRKEND | /[NO]RELEASE
```

| `/[NO]SPINLOCK=spinlock` | `/[NO]WAIT`]

Parameters

None.

Qualifiers

`/ACQUIRE`

`/NOACQUIRE`

The `/ACQUIRE` qualifier traces any spinlock acquisitions. This is the default.

The `/NOACQUIRE` qualifier ignores any spinlock acquisitions.

`/BUFFER=pages`

Specifies the size of the trace buffer (in page units). It defaults to 128 pages, which is equivalent to 1MB, if omitted.

`/CPU=n`

Specifies the tracing of a specific CPU only, for example, `/CPU=5` or `/CPU=PRIMARY`. By default, all CPUs are traced.

`/FORKLOCK=forklock`

`/NOFORKLOCK`

The `/FORKLOCK=forklock` qualifier specifies the tracing of a specific forklock, for example, `/FORKLOCK=IOLOCK8` or `/FORKLOCK=IPL8`.

The `/NOFORKLOCK` qualifier disables forklock tracing and does not collect any forklock data. By default, all forks are traced.

`/FRKDSPTH`

`/NOFRKDSPTH`

The `/FRKDSPTH` qualifier traces all invocations of fork routines within the fork dispatcher. This is the default.

The `/NOFRKDSPTH` qualifier ignores all of the `/FRKDSPTH` operations.

`/FRKEND`

`/NOFRKEND`

The `/FRKEND` qualifier traces all returns from fork routines within the fork dispatcher. This is the default.

The /NOFRKEND qualifier ignores all of the operations of the /FRKEND qualifier.

/RELEASE

/NORELEASE

The /RELEASE qualifier traces any spinlock releases. This is the default.

The /NORELEASE qualifier ignores any spinlock releases.

/SPINLOCK=*spinlock*

/NOSPINLOCK

The /SPINLOCK=*spinlock* qualifier specifies the tracing of a specific spinlock, for example, /SPINLOCK=LCKMGR or /SPINLOCK=SCHED.

The /NOSPINLOCK qualifier disables spinlock tracing and does not collect any spinlock data. By default, all spinlocks are traced.

/WAIT

/NOWAIT

The /WAIT qualifier traces any spinwait operations. This is the default.

The /NOWAIT qualifier ignores any spinwait operations.

Description

The SPL START TRACE command enables spinlock and fork tracing. By default all spinlocks and forklocks are traced and a 128 page (1MByte) trace buffer is allocated and used as a ring buffer.

Example

1. SDA> SPL START TRACE/BUFFER=1000
Tracing started... (Spinlock = 00000000, Forklock = 00000000)

This example shows how to enable a tracing for all spinlock and forklock operations into a 8 MByte trace buffer.

2. SDA> SPL START TRACE/CPU=PRIMARY/SPINLOCK=SCHED /NOFORKLOCK
Tracing started... (Spinlock = 810AF600, Forklock = 00000000)

This example shows how to trace only SCHED spinlock operations on the primary CPU.

3. SDA> SPL START TRACE /NOSPINLOCK /FORKLOCK=IPL8
Tracing started... (Spinlock = 00000000, Forklock = 863A4C00)

This example shows how to trace only fork operations to IPL8.

8.4.8. SPL STOP COLLECT

Stops the spinlock collection, but does not stop spinlock tracing.

Format

`SPL STOP COLLECT`

Parameters

None.

Qualifiers

None.

Description

The `SPL STOP COLLECT` command stops the data collection, but does not affect tracing. This allows the user to start another collection for a different spinlock during the same trace run.

Example

```
SDA> SPL STOP COLLECT
```

8.4.9. SPL STOP TRACE

Disables spinlock tracing, but it does not deallocate the trace buffer.

Format

`SPL STOP TRACE`

Parameters

None.

Qualifiers

None.

Description

The `SPL STOP TRACE` command stops tracing, but leaves the trace buffer allocated for further analysis.

Example

```
SDA> SPL STOP TRACE  
Tracing stopped...
```

8.4.10. SPL UNLOAD

Unloads the `SPL$DEBUG` execllet and performs cleanup. Tracing is automatically disabled and the trace buffer deallocated.

Format

`SPL UNLOAD`

Parameters

None.

Qualifiers

None.

Description

The SPL UNLOAD command disables the tracing or collection functionality with a delay to a state of quiescence. This ensures that all pending trace operations in progress have finished before the trace buffer is deallocated. Finally the SPL UNLOAD command unloads the SPL\$DEBUG execlt.

Example

```
SDA> SPL UNLOAD
SPL$DEBUG unload status = 00000001
```


Chapter 9. SDA XFC Extension

The SDA extension commands for Extended File Cache (XFC) enable you to display the following information in a convenient and readable format:

- Various XFC data structures
- Statistics that aid in tuning the extended file cache

You can also control the types of events that are recorded by XFC's tracing feature.

9.1. SDA XFC Commands

The following pages describe the SDA XFC extension commands.

You can enter XFC commands at the SDA prompt or you can access online help, as follows:

```
SDA> XFC HELP
```

9.1.1. XFC SET TRACE

Controls the types of events to be recorded by XFC's trace facility and initializes the trace structures (to eliminate events that have already been recorded).

Format

```
XFC SET TRACE [/SELECT=LEVEL:level] [/RESET]
```

Parameters

Qualifiers

/SELECT=LEVEL:level

Specifies the level of tracing in XFC on a live system. The possible values for *level* are as follows:

1	(Default) Traces only major, unusual events.
2	Traces file access, deaccess, truncate, read start and complete, and write start and complete operations. Results are displayed using the SHOW TRACE command. Setting this trace level has only a minor performance impact.
3	Performs more detailed tracing, which can be viewed using the SHOW TRACE/RAW command. Has some performance impact.
4	Performs very detailed tracing with a noticeable performance impact.

/RESET

Initializes the trace buffer to eliminate all events that have already been traced.

Description

Traceable events within the XFC facility are organized by level of importance, from level 1 for rare, unusual events only, through level 4, which is a very detailed trace of events within the I/O flow through XFC. The trace buffer can be reset to clear older trace points.

9.2. XFC SHOW CONTEXT

Displays the contents of an XFC context block (CTX).

Format

`XFC SHOW CONTEXT [address][/STALLING | /FULL | /BRIEF]`

Parameters

address

The address of the CTX. If no address is supplied, then all the context structures are displayed.

Qualifiers

/BRIEF

Displays a brief summary for each context; for example, the I/O type, start virtual block number (VBN), and length of I/O.

/FULL

Displays the complete context structure. This is the default.

/STALLING

Displays only contexts that are stalling; for example, those that have a stall reason code other than `estrNotStalling`.

Description

The SHOW CONTEXT command displays the contents of an active context block. The state of each active operation within XFC is maintained in a data structure called a context block.

Examples

1. `SDA> XFC SHOW CONTEXT/BRIEF`

List of All XFC Active Contexts (CTX)

Address	I/O Type	I/O phase	I/O Stall reason	Volume ID	File ID	Start VBN	Length	IRP
FFFFFFFF818C6250	eiotReadThrough	eiopFillContext	estrWindowTurn	FFFFFFFFD8311BD00	3156	382593	32	818F7780
FFFFFFFF81854D10	eiotReadThrough	eiopFillContext	estrWindowTurn	FFFFFFFFD8311BD00	3156	283873	32	81B26940
FFFFFFFF818787D0	eiotReadThrough	eiopFillContext	estrWindowTurn	FFFFFFFFD8311BD00	3156	351777	32	81265FC0
FFFFFFFF81849E50	eiotReadAround	eiopSegmentDone	estrDiskIO	FFFFFFFFD8311BD00	3156	289089	32	818F7540
FFFFFFFF818DC0D0	eiotReadAround	eiopSegmentDone	estrDiskIO	FFFFFFFFD8311BD00	3156	271809	32	817C1800
FFFFFFFF81854190	eiotClusterTrans	eiopClusterIdle	estrNotStalled	0000000000000000	0	0	0	00000000

This example shows the address of the context block, I/O type (the type of operation), I/O phase (what phase the operation is in), I/O stall (reason for its stalling), volume ID (address of the control

volume block), start VBN (starting VBN of the I/O), length of the I/O, and I/O request packet (the address of the IRP).

```

2. SDA> XFC SHOW CONTEXT FFFFFFFF8190D690
List of All XFC Active Contexts (CTX)
-----
Context (CTX) Address: FFFFFFFF8190D690
I/O Phase:             eiopFillContext
I/O Type:              eiotReadThrough
Operation started:    17-APR-2002 11:23:29.00
Stall Reason:         estrWindowTurn
Stall Extent:         0000000000000000
Stall Op (IRP):       FFFFFFFF81267A40
Saved AST Parameter:  0000000000000000
Restart Routine:      0000000000000000
Context state flags   00000000
  Cache Hit:          False
  HWM Checked:        False
  Fork Restarted      False
  AST Required (flush) False
  Buffer locked        False
  Stalled converting  False
  Fork Block in use   False
  Override resource checks False
  Restart cluster trans False
  Restart cluster flush False
  MV volumes skipped  False
  Depose pending      False
  Ignore CFB Quiesce  False
  Delete CFB          False
  Read-ahead hit      False
ECB Count:            0
Index:                00000000 (      0)
Start VBN:            000107C1 (   67521)
Length in Blocks:     00000020 (    32)
Next VBN:             000107C1 (   67521)
I/O Extent Count:     0
Disk I/O Length:      00000020 (    32)
Bytes Copied:         0
Bytes Zeroed:         0
Bytes Requested:      16384
Volume (CVB):         0000000000000000
Volume Id:            FFFFFFFFD8311BD00
File Id:              00000000000000C54
Cache File Block:    FFFFFFFFD82CEA2A0
Process (PCB):        FFFFFFFF818FA500

```

This example shows output of a full display of a context block for a read I/O.

9.3. XFC SHOW EXTENT

Displays the contents of an extent control block (ECB).

Format

XFC SHOW EXTENT address

Parameters

address

The address of the ECB.

Qualifiers

None.

Description

The SHOW EXTENT command displays the contents of an extent control block (ECB). The data in the cache is divided into groups of VBNs called extents. Each extent is maintained in a data structure called an extent control block.

Example

```
SDA> XFC SHOW EXTENT FFFFFFFFD82A58A20
Cache Extent Address:  FFFFFFFFD82A58A20
Type:                  Primary
Flink:                 FFFFFFFF7F880350
Blink:                 FFFFFFFF7F880350
Start VBN:             00000001 (          1)
Start LBN:             00BA711C ( 12218652)
Length in Blocks:     00000006 (          6)
Data State:           Clean
Pin:                  None
Buffer Address:       FFFFFFFFD82A58A20
Secondary ECB Queue: FFFFFFFFD82A58A60
    Flink:             FFFFFFFFD83199A20
    Blink:             FFFFFFFFD83199A20
Primary ECB:          0000000000000000
LRU Queue:            FFFFFFFFD82A58AAC
    Flink:             FFFFFFFFD82A5A26C
    Blink:             FFFFFFFFD82A5344C
Waiters Queue:       FFFFFFFFD82A58A50
    Flink:             FFFFFFFFD82A58A50
    Blink:             FFFFFFFFD82A58A50
Lock Id:              00000000
Parent CFB:           FFFFFFFFD82A61180
ECB delete pending   False
ECB on LRU queue     True
ECB depose pending   False
ECB read ahead       False
LRU priority:        1
```

This example shows the contents of an extent control block.

9.4. XFC SHOW FILE

Displays the contents of the cache file block (CFB).

Format

```
XFC SHOW FILE [address] [ /EXTENTS | /ID=file-id
```

`| /CVB=address | /OPEN | /CLOSED | /STATISTICS | /FULL
| /BRIEF]`

Parameters

address

The address of the CFB. The `/OPEN` and `/CLOSED` qualifiers, if present, are ignored. If no address is supplied, then all the CFBs are displayed.

Qualifiers

/BRIEF

Displays the following summary information for each cache file block (CFB): CFB address, cache volume block (CVB) address, access count, active I/O count, and file ID.

`/BRIEF` is incompatible with `/EXTENTS`, `/FULL`, and `/STATISTICS`.

If the file specification is available in `LIB$FID_TO_NAME()`, it is displayed; otherwise, the file ID is displayed.

Note

Because the volume is accessed through its logical name, if two volumes are mounted that have the same logical name (for example, one mounted `/SYSTEM` and one mounted privately, which results in the same logical name in two different access-mode logical name tables), the incorrect file specification might be displayed.

/CLOSED

Displays only CFBs whose access count is zero.

/CVB=address

Displays information only for files matching the given cache volume block address.

/DISPLAY_NAME (default)

/NODISPLAY_NAME

Controls whether the file specification is displayed.

/EXTENTS

Displays the cache extents held in cache for any displayed files. This shows the primary and secondary cache extents along with their data state, virtual block numbers (VBNs), and logical block numbers (LBNs). It also shows a summary of memory usage (pagelets used and pagelets valid) for any displayed files. The `/EXTENTS` qualifier is incompatible with the `/BRIEF` qualifier.

/FULL

Displays all fields for each cache file block. This is the default.

If the file specification is available in `LIB$FID_TO_NAME()`, it is displayed; otherwise, the file ID is displayed.

Note

Because the volume is accessed through its logical name, if two volumes are mounted that have the same logical name (for example, one mounted /SYSTEM and one mounted privately, which results in the same logical name in two different access-mode logical name tables), the incorrect file specification might be displayed.

/ID=file-id

Displays only information about any files matching the given file-identification (FID). The file identification (FID) is the hexadecimal file number component in a format file ID (file number, sequence number, relative volume number).

/OPEN

Displays only CFBs whose access count is greater than zero.

/STATISTICS

Displays more statistics about the specified file. The /STATISTICS qualifier is incompatible with the /BRIEF qualifier.

Description

The SHOW FILE command displays the contents of the XFC cache file block. The state of any file in the cache is maintained in a data structure called a cache file block (CFB). There is a CFB for every open file on a system and a CFB for each closed file that is still being cached.

Examples

1. SDA> XFC SHOW FILE/BRIEF

```
XFC Cache File Block brief listing
-----
CFB Address   CVB Address   Volume Name           File ID   Access  Write  Total  Read   Hit   Extent  Allocated
Count        Access       (423,4,0)             (899,4,0) 1      0      14    6    42.86% 13      13
(2098,4,0)     1      0      1      0    0.00%  1      1
(2336,4,0)     1      0     10    3   30.00%  4      4
(423,4,0)      1      0      2      0    0.00%  3      3
(904,4,0)      1      0      6      0    0.00%  3      3
(426,4,0)      1      0      2      0    0.00%  4      4
(2338,4,0)     1      0    141   101  71.63% 131    131
(427,4,0)      1      0      2      0    0.00%  4      4
.
.
.
```

This example shows the brief output from this command.

2. SDA> XFC SHOW FILE/STATISTICS FFFFFFFFD831A24C0

```
Full Cache File Block (CFB) Details
-----
CFB Address:      FFFFFFFFD831A24C0
CFB Address:      FFFFFFFFD831A24C0
Flink:           FFFFFFFFD831A22C0
Blink:           FFFFFFFFD831A2700
Access Count:    1
Write Access Count: 0
Volume (CVB):    FFFFFFFFD831FE080
Quiescing:       False
File (FCB):      FFFFFFFF81943D80
Volume Id:       FFFFFFFFD831FE080
```

```

File Id:                0000000000000383
External FID:           (899,4,0)
Predicted Next VBN:    000000FB (      251)
Active Caching Mode:   Write Through
Active I/O count:      0
Flush Fail Status:     00000000 (      0)
No Readahead Reasons: 0
Active Readaheds:     0
File Bad:              False
Caching disabled:      False
File deleted on close: False
File Quiescing:        False
File Depositing:       False
File Deleting:         False
File BlkASTInProg:     False
File IgnoreBlkAST      False
File Readahead EOF    False
PECBs Allocated:       13 (      13 pages)
PECBs Deallocated:     0
PECBs Deallocated:     0
SECBs Allocated:       3
SECBs Deallocated:     19
Lock Id:               0C00037F
  Granted Lock mode:   PRMode
  Conversion phase:    Illegal
Conversion phase count: 1
Hash Bucket Queue:    FFFFFFFD831A2520
  Flink:               FFFFFFFF7FF819B0
  Blink:               FFFFFFFF7FF819B0
PECB Queue:           FFFFFFFD831A2530
  Flink:               FFFFFFFD8311888C
  Blink:               FFFFFFFD831A072C
Stalled IOs Queue:   FFFFFFFD831A24F0
  Flink:               FFFFFFFD831A24F0
  Blink:               FFFFFFFD831A24F0
FAL transition Queue: FFFFFFFD831A2500
  Flink:               FFFFFFFD831A2500
  Blink:               FFFFFFFD831A2500
Contexts Waiting:     FFFFFFFD831A2510
  Flink:               FFFFFFFD831A2510
  Blink:               FFFFFFFD831A2510
BlkASTs Waiting:      FFFFFFFD831A2540
  Flink:               FFFFFFFD831A2540
  Blink:               FFFFFFFD831A2540
Deaccess Wait List:   FFFFFFFD831A2600
  Flink:               0000000000000000
Quiesce context:      0000000000000000
Up convert context:   0000000000000000
File IO Statistics - all in decimal
-----
Statistics Valid From: 19-APR-2002 07:10:32.77

Total QIOs to this file:      14
Read IOs to this file:        14
Write IOs to this file:        0
Write IOs to this file:        0
Read Hits:                     6
Hit Rate:                      42.86 %

```

```
Average Overall I/O response time to this file
  in milliseconds:                0.9525
Average Cache Hit I/O response time to this file
  in milliseconds:                0.0702
Average Disk I/O response time to this file
  in milliseconds:                1.6141
Accuracy of I/O resp time:                65 %
Read Ahead Count:                   0
Read Through Count:                 14
Write Through Count:                0
Read Around Count:                  0
Write Around Count:                 0
CFB FAL stalls:                     1
CFB Operation stalls:               0
FAL Blocking ASTs:                  0
Quiesce Depose:                     0
Quiesce depose Stalls:              0
```

(I/O size statistics not collected for this file)

Files found: 1

This example shows a collection of performance statistics for a file.

9.5. XFC SHOW HISTORY

Displays approximately three days of XFC activity in 10-minute intervals.

Format

```
XFC SHOW HISTORY
```

Parameters

None.

Qualifiers

None.

9.6. XFC SHOW IRP

Displays a subset of the fields of an I/O Request Packet that has relevance for XFC debugging.

Format

```
XFC SHOW IRP address
```

Parameters

address

The address of the IRP structure whose relevant fields are to be decoded and displayed.

Qualifiers

None.

9.7. XFC SHOW MEMORY

Displays information about memory used by the cache.

Format

```
XFC SHOW MEMORY [/BRIEF|/FULL]
```

Parameters

None.

Qualifiers

/BRIEF

Displays summary statistics on XFC memory use.

/FULL

Displays full statistics on XFC memory use. This is the default.

Examples

```
1. SDA> XFC SHOW MEMORY
XFC Memory Statistics
-----
Pool allocation calls      : 430
Pool allocation failures   : 0
Pool deallocation calls   : 0

Page allocation calls     : 2745
Page deallocation calls   : 6

Cache VA Regions and Limits
-----
Cache VA region from FFFFFFFFD8000000 to FFFFFFFF80000000 ( 1048576
pages)

    permanent area   : FFFFFFFFD8000000 to FFFFFFFFDBE800000 ( 128000
pages)
        pool        : FFFFFFFFD8000000 to FFFFFFFFD83200000 (   6400
pages)
            data    : FFFFFFFFD83200000 to FFFFFFFFDBE800000 ( 121600
pages)

    dynamic area    : FFFFFFFFDBE800000 to FFFFFFFF7F780000 ( 919488
pages)
        pool        : FFFFFFFFDBE800000 to FFFFFFFFDD4F2C000 (   45974
pages)
            data    : FFFFFFFFDD4F2C000 to FFFFFFFF7F780000 ( 873514
pages)
```

```

    extent hash table: FFFFFFFF7F780000 to FFFFFFFF7FF80000 (    1024
pages)
    file hash table  : FFFFFFFF7FF80000 to FFFFFFFF80000000 (     64
pages)
    file hash table  : FFFFFFFF7FF80000 to FFFFFFFF80000000 (     64
pages)

qhdPermanentPoolFreePages      : FFFFFFFF80D305B8
qhdPermanentDataFreePages     : FFFFFFFF80D305C8
Non-Paged Pool allocated      : 45248 (44.1 KB)
Non-Paged Pool number of - FKs :    403
Non-Paged Pool number of - DBMs :     3
Non-Paged Pool number of - CTXs :    10
Current Maximum Cache Size    : 8589934592 (8.0 GB)
Boottime Maximum Cache Size   : -1

Permanent Data Pages: Allocated :   121600
                       In use   :    2739
Pool Pages: Allocated :    6400
              In use   :    128

Dynamic Pages: Max Allowed :   919488
                Allocated  :     0
                In use     :     0
                Min Allowed :   20971
Data Pages: Allocated :   873514
             In use     :     0
Pool Pages: Allocated :   45974
             In use     :     0
              PFN List  :     0
              Non PFN List :     0

Total Cache Memory (bytes) : 1048621248 (1000.0 MB)

Private PFN List Stats
-----
Dynamic Area PFN List      : FFFFFFFF818EB340
Free physical pages on list : 0
Pages attributed to this list : 0
Pages being requested for return: 0
List priority              : 0
Callback routine           : 80DF8A40
Free PFN queue head       : FFFFFFFF818EB350
  First free page         : 0000000000000000
  Last free page          : 0000000000000000

MMG Callback Counters
-----
MMG callback active       : 0
MMG callback count       : 0
MMG callback requeues    : 0
MMG callback requeue again : 0
Expand attempts callback active : 0
Pages reclaimed          : 0
Trim reclaim attempts    : 0
LRU depose calls TrimWorkingSet : 0

```



```

Zone Purges: Permanent      : 0
                Dynamic PFNLST : 0
                Dynamic No PFNLST : 0

Pool Zone Stats (S2 Space)      Permanent      Dynamic
SECB: Size 112, PerPage 71
  Pages / MaxPages              12 / 6400      |||  0 / 45974
  FreePkts / TotalPkts          64 / 852      |||  0 / 0
  Hits                          5499           |||  0
  Not first page                0              |||  0
  Misses (expns/fails)          12 ( 12 /0)  |||  0 ( 0 /
0)

PECB: Size 176, PerPage 45
  Pages / MaxPages              85 / 6400      |||  0 / 45974
  FreePkts / TotalPkts          6 / 3825      |||  0 / 0
  Hits                          3740           |||  0
  Not first page                0              |||  0
  Misses (expns/fails)          85 ( 85 /0)  |||  0 ( 0 /
0)

CFB: Size 544, PerPage 14
  Pages / MaxPages              29 / 6400      |||  0 / 45974
  FreePkts / TotalPkts          3 / 406      |||  0 / 0
  Hits                          488           |||  0
  Not first page                0              |||  0
  Misses (expns/fails)          29 ( 29 /0)  |||  0 ( 0 /
0)

CVB: Size 608, PerPage 13
  Pages / MaxPages              2 / 6400      |||  0 / 45974
  FreePkts / TotalPkts          12 / 26      |||  0 / 0
  Hits                          12           |||  0
  Not first page                0              |||  0
  Misses (expns/fails)          2 ( 2 /0)  |||  0 ( 0 /
0)

IOSIZE: Size 3120, PerPage 2
  Pages / MaxPages              0 / 6400      |||  0 / 45974
  FreePkts / TotalPkts          0 / 0      |||  0 / 0
  Hits                          0           |||  0
  Not first page                0              |||  0
  Misses (expns/fails)          0 ( 0 /0)  |||  0 ( 0 /
0)

```

This example shows the full output from this command.

2. SDA> XFC SHOW MEMORY/BRIEF

XFC Memory Summary

```

-----
Current Maximum Cache Size      : 8589934592 (8.0 GB)
Boottime Maximum Cache Size     : -1

Permanent Data Pages: Allocated : 121600
                        In use    : 2739
Pool Pages: Allocated : 6400
              In use   : 128

```

```

Dynamic Pages: Max Allowed      : 919488
                  Allocated      :      0
                  In use         :      0
                  Min Allowed     : 20971
Data Pages: Allowed            : 873514
                  In use         :      0
Pool Pages: Allowed           : 45974
                  In use         :      0
                  PFN List       :      0
                  Non PFN List   :      0

Total Cache Memory (bytes)      : 1048621248 (1000.0 MB)

```

This example shows the brief output from this command.

9.8. XFC SHOW SUMMARY

Displays general information about the Extended File Cache.

Format

```
XFC SHOW SUMMARY [/STATISTICS]
```

Parameters

None.

Qualifiers

```
/STATISTICS
```

Additionally, displays read and write activity arranged by I/O size.

Example

```

SDA> XFC SHOW SUMMARY
XFC Summary
-----
Extended File Cache V1.0 Let unk I/Os through (Apr 18 2002 15:01:16)
Anchor Block Address:          FFFFFFFF80D30210
Build Id:
Cache State:                   0000A010
Cache in no-cache state:      False
MaxAllowedCacheMode:          eNodeFullXFC
Minimum cache size in Pages:   0001F400 ( 128000)

General
-----
Extent Hash Table Address:     FFFFFFFF7F780000
Extent Hash Table Buckets:     524287
File Hash Table Address:       FFFFFFFF7FF80000
File Hash Table Buckets:       32767
Count of private CTXs:         10
Count of private FKBs:         403
Count of private DIOBMs:       3

```

LRU

```

LRU Priority 0 Queue Address:  FFFFFFFF80D30288
                               Queue Length:  00000446 (    1094)
LRU Priority 1 Queue Address:  FFFFFFFF80D30298
                               Queue Length:  00000AA5 (    2725)
qhdContexts Address           FFFFFFFF80D302B0
qhdIRPs Address               FFFFFFFF80D302C0

```

Spinlock

```

Cache Spinlock:                8125E780
  Last Acquiring Module:       ROOT$: [XFC.TMPSRC]XFC_SYS.C;4
    Acquiring Line:            2887
    Acquiring IPL:              0

```

Cache Tracing

```

Number of trace entries:        10000
Size of trace buffer:           800000
Current trace level:            4
Lost trace entrys:              0
Current trace sequence number:  318768

```

System Wide I/O Statistics since last reset

```

Time of Last System-Wide Reset:  19-APR-2002 07:10:23.43

```

```

Total cache calls:              4505
Total cache calls:              4505
  - Sum of Paging I/Os:         2493
  - and other QIOs:             2012
  - and NoCVB or PermNoCache QIOs:  0

```

```

Total Virtual Reads:            4197
Total Virtual Writes:           112
Total PageIOs not cached:       196
Total Logical I/Os:              0
Total Physical I/Os:             0
Total bypass write I/Os:         0

```

```

Synchronous I/O completions:    598
Physical I/O completions:        0
Total PID completion I/Os:       0

```

```

Total num IOs on reserved files: 1606
Total num IOs on global sections: 247
Count of stalls performed:       13

```

```

System Wide Read Percentage:     97.40 %
System Wide Cache Hit ratio:     57.90 %

```

System-Wide Read Statistics since last reset

```

Virtual Reads:                  4197
  Sum of Read Around Count:      179
  and Read Through Count:        4018

```

Reads Completed:	4197
Read Hits:	2495
Read Cache Hit Percentage:	59.45 %
Total Synch Completion Count:	598
Read Around due to Het. Cluster:	0
Read Around due to Modifiers:	0
Read Around due to Size:	16
Total reads past EOF:	1
Total I/Os with read-ahead:	239
Read Hits due to read-ahead:	307
Paging I/Os:	2493

System-Wide Write Statistics since last reset

Virtual Writes:	112
Sum of Write Around Count:	0
and Write Through Count:	112
Write Around due to Het. Cluster:	0
Writes Completed:	112
Write Around due to Modifiers:	0
Write Around due to Size:	0
Total writes past EOF:	0

File/Volume Statistics

Open Files:	239
Closed Files in the Cache:	164
Number of files truncated:	3
Volumes in Full XFC Mode:	0
Volumes in VIOC Compatible Mode:	13
Volumes in No Caching Mode:	1
Volumes in Perm. No Caching Mode:	0
Volume Queue:	FFFFFFFF80D30238

File/Volume Statistics

FAL locks currently held:	370
FAL locks chosen to skip:	0
FAL locks acquired since boot:	374
FAL locks released since boot:	4
FAL locks converted:	55
I/Os that have stalled for FAL	0
CACHE\$ACCESS stalls for CFB	0
ulStallOpQStalls	1
Read-thro->Read-around conv.	0
Writes converted to write-around	0
ulLockResourceExhaustionRetries:	0
ulFALLocksEverInContention:	3
ulFALUpConversionRequests:	3
ulFALLocksConvertedToPR:	0
ulFALLocksConvertedToNL:	0
FAL BlkASTs received:	1
FAL BlkASTs ignored:	0
ECBs Split Right:	2229
ECBs Split Left:	1710
ECBs Split Three Ways:	786
ECBs Requiring no splits:	5802

Volume Lock Statistics

```

-----
VIL Blocking ASTs received           0
VIL Blocking ASTs stalled           0
VIL Blocking ASTs started           0
VIL Blocking ASTs completed         0
VIL Up-conversion requests made     0
VIL Up-conversion grants            0
VCML Blocking ASTs received         0
VCML Blocking ASTs stalled           0
VCML Blocking ASTs started           0
VCML Blocking ASTs completed         0
VCML Up-conversion requests made    0
VCML Up-conversion grants            0
Stalls on VCML up-conversion        0
Restarts on VCML up-conversion      0

```

Quiesce and Depose Statistics

```

-----
Quiesce and Depose files Stalled:    0
File Quiesce and Deposits Started:  114
File Quiesce and Deposits Cmpltd:    114
File Quiesce and Deposits Cmpltd:    114
Q&D CTX used count:                  0
Q&D CTX in use:                       False

Most recent Depose time               0.0005 msec.
Most recent Depose ECB count          0
Maximum Depose time                   0.1125 msec.
Maximum ECBs deposited                3
Total Depose time                     0.0002 seconds
Total ECBs deposited                  6

```

Pending Lock Up-conversion Statistics

```

-----
Up-conversions stalled:               0
Up-conversions started:               0

```

This example shows the output of detailed statistics and status for the cache.

9.9. XFC SHOW TABLES

Displays both the extent hash table (EHT) and the file hash table (FHT).

Format

```
XFC SHOW TABLES [/ALL][/EXTENT][/FILE][/SUMMARY]
```

Parameters

None.

Qualifiers

/ALL

Displays the contents of the extent hash table (EHT) and file hash table (FHT). This is the default.

/EXTENT

Displays only the contents of the EHT.

/FILE

Displays only the contents of the FHT.

/SUMMARY

Displays summary information about EHT and FHT.

Description

The SHOW TABLES command outputs information about the two hash tables used by XFC to locate key data structures.

Example

```
SDA> XFC SHOW TABLES/SUMMARY
Full Map of CFB HashTable
-----
FHT: Contents of 32768 buckets

0 (32366)
1 (401)
2 (1)
Total number of CFBs:      403
Longest chain length:     2
Shortest chain length:    0
Shortest chain length:    0
Average chain length:     0.01

Full Map of PECB HashTable
-----
EHT: verifying 524288 buckets

0 (520501)
1 (3755)
2 (32)
Total number of PECBs:    3819
Longest chain length:     2
Shortest chain length:    0
Average chain length:     0.01
```

This example shows summary output about each of the hash tables.

9.10. XFC SHOW TRACE

Displays all or selected portions of the XFC trace buffer, starting with the most recent entry and moving backward in time.

Format

```
XFC SHOW TRACE [/ALL]/CONTAINING=value | /CPU=cpu-num
| /LINENUMBER=linenumber
| /MATCH [= [AND|OR]] | /Px=value | /RAW]
```

Parameters

None.

Qualifiers

/ALL

Displays the entire trace buffer. This is the default.

/CONTAINING=*value*

Displays only records where any of the traced parameters is equal to *value*.

/CPU=*cpu-num*

Displays only records from threads executing on CPU *cpu-num*.

/LINENUMBER=*linenumber*

Displays only records from tracepoints at line *linenumber* in the relevant source files.

/MATCH [= AND|OR]

Alters the sense of the match condition when more than one of the filter qualifiers /CPU, /LINENUMBER, /FILENAME, /Px, or /CONTAINING are specified.

/Px=*value*

Displays only records where one of the traced parameters P1, P2, P3, or P4 is equal to *value*.

/RAW

Displays contents of trace records in hexadecimal format without interpretation. By default, the values are displayed in human readable format with filenames.

Description

The SHOW TRACE command outputs the contents of each entry in the XFC trace buffer. Currently, detailed XFC tracing is enabled only for debug versions of XFC.

Example

```
SDA> XFC SHOW TRACE
```

```
XFC Trace Buffer
```

```
-----
Sequence   Time   Label                                     Line C I P1                P2                P3                P4
319011 19-APR 09:11:16.70 SYS $IOPOST p1, p2, p3 8811 0 4 000000000001000C 0000000000000200 0000010B9BFF800 000002000087A72D
319010 19-APR 09:11:16.70 SYS $IOPOST          8803 0 4 FFFFFFFF81987940 0000000000000002 000000000000600B FFFFFFFF8150F200
319009 19-APR 09:11:16.69 Sys LOGIO          5305 3 2 0000000000000000 00000000000088000 0000000000000009 0000000000000010
319008 19-APR 09:11:16.69 Sys Logical_IO1   4989 3 2 00000000000088000 0000000000000000 FFFFFFFF8150F200 FFFFFFFF81905100
319007 19-APR 09:11:16.69 Sys Logical_IO   4981 3 2 FFFFFFFF81987940 FFFFFFFF81905100 0000000000000200 000000000087A72D
319006 19-APR 09:11:16.69 Mem FreeContext   1829 3 8 FFFFFFFF81905910 FFFFFFFF81905F80 0000000000000000 0000000000000000
319005 19-APR 09:11:16.69 Sys eiopCloseComplete 8276 3 8 FFFFFFFF81905910 FFFFFFFF81905F80 0000000000000000 0000000000000000
319004 19-APR 09:11:16.69 Common Restart CFBW 332 3 8 FFFFFFFF81905910 FFFFFFFF81905F80 0000000000000000 0000000000000000
319003 19-APR 09:11:16.69 Sys eiopCloFlushed 7700 3 8 FFFFFFFF81905910 FFFFFFFF81905F80 0000000000000000 0000000000000000
319002 19-APR 09:11:16.69 Sys eiopCloseInit 7659 3 8 FFFFFFFF81905910 FFFFFFFF81905F80 0000000000000000 0000000000000000
.
.
.
```

This example shows the output of XFC trace information.

9.11. XFC SHOW VOLUME

Displays the contents of a cache volume block (CVB).

Format

```
XFC SHOW VOLUME [address]/BRIEF|/FULL| /NAME=DISK $volume_label| /STATISTICS
```

Parameters

address

The address of a CVB. If no address is supplied, then all volumes are displayed.

Qualifiers

/BRIEF

Displays summary information for each volume.

/FULL

Displays a complete list of information about each volume. This is the default.

/NAME=*DISK**\$volume_label*

Displays information for the volume with the specified name.

/STATISTICS

Displays the read and write I/O activity for this volume. The /STATISTICS qualifier is incompatible with the /BRIEF qualifier.

Description

The SHOW VOLUME command shows state information and statistics about all volumes mounted on the system.

Examples

1. SDA> XFC SHOW VOLUME/BRIEF

```
Summary of XFC Cached Volumes (CVBs)
-----
Volume Name      CVB                Open   Closed   Total   Read   Read   Write   ... Response (Milliseconds)...
Files            Files              I/Os   Hits    Count  Count  Hits    disk    Average
DISK$SNKRNET     FFFFFFFD8311C080   0       0         0       0       0       0
DISK$FRROOGSYS   FFFFFFFD831FFD00   0       0         0       0       0       0
DISK$V73_DENBO2  FFFFFFFD831FFAA0   0       0         0       0       0       0
DISK$DENBO2_V73  FFFFFFFD831FF840   0       1         1       0       1       0       0.0000  14.2451  14.2451
DISK$VEALSYS     FFFFFFFD831FF5E0   0       0         0       0       0       0
DISK$SCRATCH2    FFFFFFFD831FF380   0       0         0       0       0       0
DISK$SCRATCH1    FFFFFFFD831FF120   0       0         0       0       0       0
DISK$BRAMHA_SCR  FFFFFFFD831FEEC0   0       0         0       0       0       0
DISK$COMMON      FFFFFFFD831FEC60   0       0         0       0       0       0
DISK$X907_BRAMHA FFFFFFFD831FEA00   0       0         0       0       0       0
DISK$OLDSYS      FFFFFFFD831FE7A0   0       1         1       0       1       0       0.0000  7.8946  7.8946
DISK$RAM_FRROOG  FFFFFFFD831FE540   0       0         0       0       0       0
DISK$RMSTA2_USER FFFFFFFD831FE2E0   3       5        115     89      112     3       0.0370  20.7218  4.7135
DISK$FRROOG_RUBY FFFFFFFD831FE080  236     157     4195    2408    4085    110     0.0789  4.8671  2.1186

Volumes found: 14
```

The above example shows the output derived from invoking the /BRIEF qualifier.

2. SDA> XFC SHOW VOLUME FFFFFFFD831FE080

Cache Volume Block (CVB)

Statistics Valid From: 19-APR-2002 07:10:23.54

```
Name:                DISK$FRROOG_RUBY
CVB Address:         FFFFFFFD831FE080
Flink:               FFFFFFFF80D30238
Blink:               FFFFFFFD831FE300
Volume (VCB):        FFFFFFFF81905100
Unit (UCB):          FFFFFFFF8150F200
Files Queue:         FFFFFFFD831FE0C0
    Flink:            FFFFFFFD83111800
    Blink:            FFFFFFFD831FC0A0
Cached Open Files:   236
Cached Closed Files: 157
Files Ever Opened:   502
Files Ever Deposited: 109
Pages Allocated:     2726
Total QIOs:          4195
Read Hit Count:      2408
Virtual Read Count:  4085
Virtual Write Count: 110
Read Percentage:     97 %
Hit Rate:             57 %
Average Overall I/O response time to this Volume
  in milliseconds:   2.1186
Average Cache Hit I/O response time to this Volume
  in milliseconds:   0.0789
Average Disk I/O response time to this Volume
  in milliseconds:   4.8671
Accuracy of I/O resp time: 83 %
Readahead Count:    233
Volume Caching Mode: evcmVIOCCompatible
Mounted /NOCACHE:   False    VCML Allows Caching: True
Quiescing:          False    Quiesce in Progress: False
No Cache from Logio: False    VIL Blk AST Stall: False
Flush Pending:      False    VCML Blk AST Stall: False
VCML Blk CTX Stall: False    VIL Blk CTX Stall: False
Dismount Stall:    False    Logio Stall: False
```

```
Flush in Progress:      False      Cluster Trans Stall:  False
Dismount Pending:      False      VIL Up Needed:        False
Tqe In Use:            False      VCML Up Needed:       False
VIL blocking AST CTX:  0000000000000000
VCML blocking AST CTX: 0000000000000000
Dismount Stall CTX:    0000000000000000
LogIO Stall CTX:       0000000000000000
Up conversion CTX:     0000000000000000
VIL lock id:           0100007A
VIL LogIO lock id:     00000000
VCML lock id:          010000FF
VCML LogIO lock id:    00000000
Logical IO safety:     elogioNotSafe
LogIOMutex:            00000000818EB610
Last LogIO time:       00000000
Active I/O count:      0
Stalled Ops Queue:     FFFFFFFD831FE0B0
  Flink:                FFFFFFFD831FE0B0
  Blink:                FFFFFFFD831FE0B0
```

Volumes found: 1

This example shows the output for a specific cache volume block (CVB).

Chapter 10. SDA Extensions and Callable Routines

This chapter describes how to write, debug, and invoke an SDA Extension. This chapter also describes the routines available to an SDA Extension.

10.1. Introduction

When analysis of a dump file or a running system requires intimate knowledge of data structures that are not known to the System Dump Analyzer, the functionality of SDA can be extended by the addition of new commands into which the necessary knowledge has been built. Note that in this description, whenever a reference is made to accessing a dump file (ANALYZE/CRASH_DUMP), this also includes accessing memory in the running system (ANALYZE/SYSTEM).

For example, a user-written device driver allocates nonpaged pool and records additional data about the device there (logging different types of I/O, perhaps), and a pointer to the new structure is saved in the device-specific extension of the UCB. After a system crash, the only way to look at the data from SDA is to do the following:

- Invoke the SDA command DEFINE to define a new symbol (for example, UCB\$L_FOOBAR) whose value is the offset in the UCB of the pointer to the new structure.
- Invoke the SDA commands "SHOW DEVICE <device>" and "FORMAT UCB" to obtain the address of the nonpaged pool structure.
- Invoke the SDA command "EXAMINE <address>;<length>" to display the contents of the data in the new nonpaged pool structure as a series of hexadecimal longwords.
- Decode manually the contents of the data structure from this hexadecimal dump.

An SDA extension that knows the layout of the nonpaged pool structure, and where to find the pointer to it in the UCB, could output the data in a formatted display that alerts the user to unexpected data patterns.

10.2. Description

The following discussion uses an example of an SDA extension that invokes the MBX command to output a formatted display of the status of the mailbox devices in the system. The source file, MBX\$SDA.C, is provided in SYS\$EXAMPLES.

An SDA extension consists of a shareable image, in this case MBX\$SDA.EXE, either located in the directory SYS\$LIBRARY or found by translating the logical name MBX\$SDA. It contains two universal symbols: SDA\$EXTEND, the entry point; and SDA\$EXTEND_VERSION, the address of a longword that contains the version of the interface used (in the format of major/minor ident), which allows SDA to confirm it has activated a compatible extension. The image contains at least two modules: MBX\$SDA, the user-written module that defines the two symbols and provides the code and data necessary to produce the desired formatted output; and SDA_EXTEND_VECTOR, which provides jackets for all of the callable SDA routines, and is found in SYS\$LIBRARY:VMS\$VOLATILE_PRIVATE_INTERFACES.OLB. The user-written portion can be split into multiple modules.

Whenever SDA receives an unrecognized command, like "SDA> MBX", it attempts to activate the shareable image MBX\$\$SDA at the SDA\$EXTEND entry point. If you choose a command name that matches the abbreviation of an existing command, SDA can be forced to activate the extension using the "DO" command. For example, if you had an SDA extension called VAL\$\$SDA, you could not activate it with a command like "SDA> VAL" as SDA would interpret that as an abbreviation of its VALIDATE command. But VAL\$\$SDA can be activated by issuing "SDA> DO VAL".

With or without the "DO" prefix, the rest of the command line is passed to the extension; it is up to the extension to parse it. The example extension MBX\$\$SDA includes support for commands of the form "SDA> MBX SUMMARY" and "SDA> MBX <address>" to demonstrate this. If the extension is invoked with no arguments, it should do no more than display a simple announcement message, or prompt for input. This assists in the debugging of the extension, as described in Section 10.3.

Section 10.2.1 describes how to compile, link, and invoke an SDA extension, and describes what an SDA extension should contain.

10.2.1. Compiling and Linking an SDA Extension

The user-written module is only supported when written in HP C (minimum Version 5.2), following the pattern of the example extension, MBX\$\$SDA.C. It should be compiled and linked using commands of the following form:

```
$cc mbx$$sda + sys$library:sys$lib_c /library
$link /share -
        mbx$$sda.obj, -
        sys$library:vms$volatile_private_interfaces /library, -
        sys$input /option
symbol_vector = (sda$extend=procedure)
symbol_vector = (sda$extend_version=data)
```

Note

1. You can include the qualifier /INSTRUCTION=NOFLOAT on the compile command line if floating-point instructions are not needed.
2. The + SYS\$LIBRARY:SYS\$LIB_C /LIBRARY is not needed on the compile command line if the logical name DECC\$TEXT_LIBRARIES is defined and translates to SYS\$LIBRARY:SYS\$LIB_C.TLB.
3. If the user-written extension needs to signal SDA condition codes, or output their text with \$PUTMSG, you should add the qualifier /INCLUDE=SDAMSG to the parameter SYS\$LIBRARY:VMS\$VOLATILE_PRIVATE_INTERFACES /LIBRARY.

10.2.2. Invoking an SDA Extension

You can invoke the SDA extension as follows:

```
$define mbx$$sda sys$disk:[]mbx$$sda
$analyze /system
SDA>mbx summary
SDA>mbx <address>
```

10.2.3. Contents of an SDA Extension

At a minimum, the user-written module must contain:

- #include statements for DESCRIP.H and SDA_ROUTINES.H
- The global variable SDA\$EXTEND_VERSION, initialized as follows:

```
int sda$extend_version = SDA_FLAGS$K_VERSION;
```

- The routine SDA\$EXTEND (prototype follows)

Optionally, the user-written module may also contain the statement:

```
#define __NEW_STARLET
```

You should use this option because it provides type checking of function arguments and gives consistency in casing and naming conventions.

The entry point in the user-written module, SDA\$EXTEND, is called as a routine with three arguments and no return value. The declaration is as follows:

```
void sda$extend (
    int *transfer_table,
    struct dsc$descriptor_s *cmd_line,
    SDA_FLAGS sda_flags)
```

The arguments in this code example have the following meanings:

Table 10.1. SDA\$EXTEND Arguments

Line of Code	Meaning	
transfer_table	Address of the vector table in the base image. The user-written routine SDA\$EXTEND must copy this to SDA\$VECTOR_TABLE (declared in SDA_ROUTINES.H) before any SDA routines can be called.	
cmd_line	Address of the descriptor of the command line as entered by the user, less the name of the extension. So, if you enter "SDA> MBX" or "SDA> DO MBX", the command line is a zero length string. If you enter the command "SDA> MBX 80102030", the command line is " 80102030" (the separating space is not stripped).	
sda_flags	Definition for the following four bits in this structure:	
	Bit	Meaning
	sda_flags.sda_flags\$v_override	Indicates SDA has been activated with the ANALYZE/CRASH_DUMP/OVERRIDE command
	sda_flags.sda_flags\$v_current	Indicates SDA has been activated with the ANALYZE/SYSTEM command or was invoked from the kept debugger during an SCD session
	sda_flags.sda_flags\$v_target	Indicates that SDA was invoked from the kept debugger during an SCD or SDD session or when analyzing a process dump

Line of Code	Meaning	
	sda_flags.sda_flags\$v_process	Indicates SDA was activated with the ANALYZE/CRASH_DUMP command to analyze a process dump
	sda_flags.sda_flags\$v_ia64	Indicates that SDA is analyzing an Integrity server system or dump
	None of the above bits set	Indicates SDA was activated with the ANALYZE/CRASH_DUMP command to analyze an Alpha system dump
	Other bits	Reserved to VSI:may be nonzero

The first executable statement of the routine must be to copy TRANSFER_TABLE to SDA \$VECTOR_TABLE (which is declared in SDA_ROUTINES.H):

```
sda$vector_table = transfer_table;
```

If this is not done, you cannot call any of the routines described below. Any attempts to call the routines receive a status return of SDA\$_VECNOTINIT. (For routines defined not to return a status, this value can be found only by examining the return value directly.)

The next statement should be one to establish a condition handler, as it is often difficult to track down errors in extensions such as access violations because the extension is activated dynamically with LIB \$FIND_IMAGE_SYMBOL. A default condition handler, SDA\$COND_HANDLER, is provided that outputs the following information in the event of an error:

- The error condition
- The VMS version
- A list of activated images, with start and end virtual addresses
- The signal array and register dump
- The current call frame chain

You can establish this condition handler as follows:

```
lib$establish (sda$cond_handler);
```

Note

The error condition, signal array, and register dump are output directly to SYS\$OUTPUT and/or SYS \$ERROR, and are not affected by the use of the SDA commands SET OUTPUT and SET LOG.

Thus, a minimal extension would be:

```
#define __NEW_STARLET 1
#include <descrip.h>
#include <sda_routines.h>
```

```

int sda$extend_version = SDA_FLAGS$K_VERSION;

void sda$extend (int *transfer_table,
                struct dsc$descriptor_s *cmd_line,
                SDA_FLAGS sda_flags)
{
    sda$vector_table = transfer_table;
    lib$establish (sda$cond_handler);

    sda$print ("hello, world");
    return;
}

```

10.3. Debugging an Extension

In addition to the "after-the-fact" information provided by the condition handler, you can debug SDA extensions using the OpenVMS Debugger. A second copy of the SDA image, SDA_DEBUG.EXE, is provided in SYS\$SYSTEM. By defining the logical name SDA to reference this image, you can debug SDA extensions as follows:

- Compile your extension /DEBUG/NOOPT and link it /DEBUG or /DSF.
- Define logical names for SDA and the extension, and invoke SDA.
- Type SET BREAK START_EXTENSION at the initial DBG> prompt, and then type GO.
- Invoke the extension at the SDA> prompt.
- When Debug prompts again, use Debug commands to set breakpoints, and so on, in the extension and then type GO.
- Invoke the extension, providing the necessary arguments.

An example of the preceding steps is as follows:

```

$ cc /debug /noopt mbx$sda + sys$library:sys$lib_c /library
$ link /debug /share -
    mbx$sda.obj, -
    sys$library:vms$volatile_private_interfaces /library, -
    sys$input /option
symbol_vector = (sda$extend=procedure)
symbol_vector = (sda$extend_version=data)
$ !
$ define mbx$sda sys$disk:[]mbx$sda
$ define sda sda_debug
$ analyze /system
...
DBG> set break start_extension
DBG> go
...
SDA> mbx
break at routine START\START_EXTENSION
...
DBG> set image mbx$sda
DBG> set language c
DBG> set break /exception

```

```

DBG> go
MBX commands: 'MBX SUMMARY' and 'MBX <address>'
SDA> mbx summary
...
SDA> mbx <address>
...
%DEBUG-I-DYNMODSET, setting module MBX$SDA
%SYSTEM-E-INVARG, invalid argument
...
DBG>

```

10.4. Callable Routines Overview

The user-written routine may call SDA routines to accomplish any of the following tasks:

- Read the contents of memory locations in the dump.
- Translate symbol names to values and vice-versa, define new symbols, and read symbol table files.
- Map an address to the activated image or executive image that contains that address.
- Output text to the terminal, with page breaks, page headings, and so on (or output to a file if the SDA commands SET OUTPUT or SET LOG have been used).
- Allocate and deallocate dynamic memory.
- Validate queues/lists.
- Format data structures.
- Issue any SDA command.

Note the following points before using the callable routines described here:

- The following three routines are used to read the contents of memory locations in the dump:
 - SDA\$TRYMEM is called from both SDA\$GETMEM and SDA\$REQMEM as the lower-level routine that actually does the work. SDA\$TRYMEM returns success/failure status in R0, but does not signal any errors. Use it directly when you expect that the location being read might be inaccessible. The caller of SDA\$TRYMEM handles this situation by checking the status returned by SDA\$TRYMEM.
 - SDA\$GETMEM signals a warning when any error status is returned from SDA\$TRYMEM. Signaling a warning prints out a warning message, but does not abort the SDA command in progress. You should use this routine when you expect the location to be read to be accessible. This routine does not prevent the command currently being executed from continuing. The caller of SDA\$GETMEM must allow for this by checking the status returned by SDA\$GETMEM.
 - SDA\$REQMEM signals an error when any error status is returned from SDA\$TRYMEM. Signaling an error prints out an error message, aborts the SDA command in progress, and returns to the "SDA>" prompt. You should use this routine when you expect the location to be read to be accessible. This routine prevents the command currently being executed from continuing. The caller of SDA\$REQMEM does not resume if an error occurs.
- You should use only the routines provided to output text. Do not use printf() or any other standard routine. If you do, the SDA commands SET OUTPUT and SET LOG will not produce the

expected results. Do not include control characters in output (except tab); in particular, avoid <CR>, <LF>, <FF>, and the FAO directives that create them. Use the FAO directive !AF when contents of memory returned by SDA\$TRYMEM, and so on, are being displayed directly, because embedded control characters will cause undesirable results. For example, displaying process names or resource names that contain particular control characters or escape sequences can lock up the terminal.

- You should use only the routines provided to allocate and deallocate dynamic memory. Do not use malloc() and free(). Where possible, allocate dynamic memory once, the first time the extension is activated, and deallocate it only if it needs to be replaced by a larger allocation. Because SDA commands can be interrupted by invoking another command at the "Press return for more" prompt, it is very easy to cause memory leaks.
- Some routines expect 32-bit pointers, and others expect 64-bit pointers. At first this not may appear to be logical, but in fact it is. All code and data used by SDA and any extensions must be in P0 or P1 space, as SDA does not need to (and does not) use P2 space for local data storage. However, addresses in the system dump (or running system, in the case of ANALYZE/SYSTEM) are 64-bit addresses, and SDA must provide access to all locations in the dump.

So, for example, the first two arguments to the routine SDA\$TRYMEM are:

```
VOID_PQ start    /* 64-bit pointer */
void *dest       /* 32-bit pointer */
```

They specify the address of interest in the dump and the address in local storage to which the dump contents are to be copied.

- Common Bitmask Block (CBB) routines, SDA\$CBB_xxx, are designed for use with local copies of the CBB structures that describe the CPUs in use in a system. The CBB structures are assumed to be at least CBB\$K_STATIC_BLOCK bytes in length. The definitions of the various CBB constants and field names used by these routines can be found in CBBDEF.H in SYS\$LIBRARY:SYS\$LIB_C.TLB.

The set of routines is not intended to be an exhaustive set of all possible CBB-related operations, but it provides those operations known to be needed. The routines might not work as expected with CBB structures that are set up for any purpose other than to describe CPUs.

10.5. Routines

The following sections describe the SDA extension callable routines.

10.5.1. SDA\$ADD_SYMBOL

Adds a symbol to SDA's local symbol table.

Format

```
void sda$add_symbol (char *symbol_name, uint64 symbol_value);
```

Arguments

symbol_name

OpenVMS usage	char_string
type	character string
access	read only
mechanism	by reference

Address of symbol name string (zero-terminated).

symbol_value

OpenVMS usage	quadword_unsigned
type	quadword (unsigned)
access	read only
mechanism	by value

The symbol value.

Description

SDA maintains a list of symbols and the corresponding values. `SDA$ADD_SYMBOL` is used to insert additional symbols into this list, so that they can be used in expressions and during symbolization.

Condition Values Returned

None.

Example

```
sda$add_symbol ("MBX", 0xFFFFFFFF80102030);
```

This call defines the symbol MBX to the hexadecimal valueFFFFFFFF80102030.

10.5.2. SDA\$ALLOCATE

Allocates dynamic memory.

Format

```
void sda$allocate (uint32 size, void **ptr_block);
```

Arguments

size

OpenVMS usage	longword_unsigned
type	longword (unsigned)
access	read only
mechanism	by value

Size of block to allocate (in bytes).

ptr_block

OpenVMS usage	address
type	longword (unsigned)
access	write only
mechanism	by reference

Address of longword to receive address of block.

Description

The requested memory is allocated and the address returned. Note that this is the only supported mechanism for allocation of dynamic memory.

Related Routine

SDA\$DEALLOCATE

Condition Values Returned

None.

If no memory is available, the error is signaled and the SDA session aborted.

Example

```
PCB *local_pcb;
...
sda$allocate (PCB$C_LENGTH, (void *)&local_pcb);
```

This call allocates a block of heap storage for a copy of a PCB, and stores its address in the pointer LOCAL_PCB.

10.5.3. SDA\$CBB_BOOLEAN_OPER

Performs a Boolean operation on a pair of CBBs.

Format

```
int sda$cbb_boolean_oper (CBB_PQ input_cbb, CBB_PQ output_cbb, int operation)
```

Arguments**input_cbb**

OpenVMS usage	address
type	CBB structure
access	read only
mechanism	by reference

The address of the first (input) CBB structure.

output_cbb

OpenVMS usage	address
type	CBB structure
access	read/write
mechanism	by reference

The address of the second (output) CBB structure.

operation

OpenVMS usage	longword
type	longword (unsigned)
access	read only
mechanism	by value

The desired operation from the following list:

CBB\$C_OR	The logical sum of the two CBBs is performed and the result ($B = A \mid B$) is written to the output CBB.
CBB\$C_BIC	The logical product with complement of the two CBBs is performed and the result ($B = B \& \sim A$) is written to the output CBB.

Description

The desired Boolean operation is performed on the two CBB structures, and the result is written to the second (output) structure.

Condition Values Returned

SS\$_BADPARAM	The number of valid bits in the input and output CBBs is different.
SS\$_WASCLR	All bits in the resulting output CBB are clear.
SS\$_WASSET	At least one bit in the resulting output CBB is set.

Example

```
int status;
extern CBB active_set,
        configure_set;
CBB inactive_set;
sda$cbb_copy (&configure_set, &inactive_set);
status = sda$cbb_boolean_oper (&active_set, &inactive_set, CBB$C_BIC);
if (status == SS$_WASSET)
    sda$print ("There are inactive CPUs in the system");
```

This example shows how the set of active CPUs and the set of configured CPUs can be manipulated to create a set of inactive CPUs.

10.5.4. SDA\$CBB_CLEAR_BIT

Clears the specified bit in a CBB.

Format

```
int sda$cbb_clear_bit (CBB_PQ cbb, int bit);
```

Arguments

cbb

OpenVMS usage	address
type	CBB structure
access	read/write
mechanism	by reference

The address of the CBB structure to be modified.

bit

OpenVMS usage	longword
type	longword (unsigned)
access	read only
mechanism	by value

The bit in the CBB to be cleared. If the bit number is -1, clears all bits.

Description

The specified bit (or all bits) in the CBB is cleared.

Condition Values Returned

SS\$NORMAL	Successful completion
SS\$BADPARAM	The bit number is out of range

Example

```
int status;
extern int next;
extern CBB active_set;
status = sda$cbb_clear_bit (&active_set, next);
if (!(status & 1))
    sda$print ("Bad CPU specified: !XL", next);
```

This example shows how a bit in a CBB is cleared.

10.5.5. SDA\$CBB_COPY

Copies the contents of one CBB to another.

Format

```
int sda$cbb_copy (CBB_PQ input_cbb, CBB_PQ output_cbb);
```

Arguments

input_cbb

OpenVMS usage	address
type	CBB structure
access	read only
mechanism	by reference

The address of the CBB structure to be copied.

output_cbb

OpenVMS usage	address
type	CBB structure
access	write only
mechanism	by reference

The address of the CBB structure to receive the copy.

Description

The specified CBB is copied.

Condition Values Returned

None.

10.5.6. SDA\$CBB_FFC

Locates the first clear bit in a CBB.

Format

```
int sda$cbb_ffc (CBB_PQ cbb, int start_bit);
```

Arguments

cbb

OpenVMS usage	address
type	CBB structure
access	read only
mechanism	by reference

The address of the CBB structure to be searched.

start_bit

OpenVMS usage	longword
type	longword (unsigned)
access	read only
mechanism	by value

The first bit in the CBB to be checked.

Description

The CBB structure is searched, starting at the specified bit, for a clear bit.

Condition Values Returned

<i>bit_number</i>	If a clear bit is found, its bit number is returned. If no clear bit is found (all bits from start_bit to cbb->cbb\$l_valid_bits are set), then the number of valid bits is returned.
-------------------	--

Example

```
int bit;
extern int start;
extern CBB active_set;
bit = sda$cbb_ffc (&active_set, start);
if (bit >= active_set.cbb$l_valid_bits)
    sda$print ("No clear bits in active set");
else
    sda$print ("First clear bit in active set = !XL", bit);
```

This example shows how the next clear bit in a CBB can be located.

10.5.7. SDA\$CBB_FFS

Locates the first set bit in a CBB.

Format

```
int sda$cbb_ffs (CBB_PQ cbb, int start_bit);
```

Arguments**cbb**

OpenVMS usage	address
type	CBB structure
access	read only
mechanism	by reference

The address of the CBB structure to be searched.

start_bit

OpenVMS usage	longword
type	longword (unsigned)
access	read only
mechanism	by value

The first bit in the CBB to be checked.

Description

The CBB structure is searched for a set bit, starting at the specified bit.

Condition Values Returned

<i>bit_number</i>	If a set bit is found, its bit number is returned. If no set bit is found (all bits from start_bit to cbb->cbb\$1_valid_bits are clear), then the number of valid bits is returned.
-------------------	---

Example

```
int bit;
extern int start;
extern CBB active_set;
bit = sda$cbb_ffs (&active_set, start);
if (bit >= active_set.cbb$1_valid_bits)
    sda$print ("No set bits in active set");
else
    sda$print ("First set bit in active set = !XL", bit);
```

This example shows how the next set bit in a CBB can be located.

10.5.8. SDA\$CBB_INIT

Initializes a CBB structure to a known state.

Format

```
void sda$cbb_init (CBB_PQ cbb);
```

Arguments**cbb**

OpenVMS usage	address
type	CBB structure
access	read only
mechanism	by reference

The address of the CBB structure to be initialized.

Description

The fields of the CBB that describe its layout are initialized as necessary for a CPU CBB. The actual bitmask is zeroed.

Condition Values Returned

None.

10.5.9. SDA\$CBB_SET_BIT

Sets the specified bit in a CBB.

Format

```
int sda$cbb_set_bit (CBB_PQ cbb,int bit);
```

Arguments

cbb

OpenVMS usage	address
type	CBB structure
access	read/write
mechanism	by reference

The address of the CBB structure to be modified.

bit

OpenVMS usage	longword
type	longword (unsigned)
access	read only
mechanism	by value

The bit in the CBB to be set. If the bit number is -1, set all bits.

Description

The specified bit (or all bits) in the CBB is set.

Condition Values Returned

SS\$NORMAL	Successful completion.
SS\$BADPARAM	The bit number is out of range.

Example

```
int status;
```

```
extern int next;
extern CBB active_set;
status = sda$cbb_set_bit (&active_set, next);
if (!(status & 1))
    sda$print ("Bad CPU specified: !XL", next);
```

This example shows how a bit in a CBB is set.

10.5.10. SDA\$CBB_TEST_BIT

Tests the specified bit in a CBB.

Format

```
int sda$cbb_test_bit (CBB_PQ cbb,int bit);
```

Arguments

cbb

OpenVMS usage	address
type	CBB structure
access	read only
mechanism	by reference

The address of the CBB structure to be tested.

bit

OpenVMS usage	longword
type	longword (unsigned)
access	read only
mechanism	by value

The bit in the CBB to be tested.

Description

The specified bit in the CBB is tested and its value returned.

Condition Values Returned

SS\$_WASSET	The specified bit was set.
SS\$_WASCLR	The specified bit was clear.
SS\$_BADPARAM	The bit number is out of range.

Example

```
int status;
extern int next;
```

```
extern CBB active_set;
status = sda$cbb_test_bit (&active_set, next);
if (!(status & 1))
    sda$print ("Bad CPU specified: !XL", next);
else if (status == SS$_WASSET)
    sda$print ("CPU !XL was set", next);
else
    sda$print ("CPU !XL was clear", next);
```

This example shows how a bit in a CBB is tested.

10.5.11. SDA\$DBG_IMAGE_INFO

Displays a list of activated images together with their virtual address ranges for debugging purposes.

Format

```
void sda$dbg_image_info ();
```

Arguments

None.

Description

A list of the images currently activated, with their start and end addresses, is displayed. This is provided as a debugging aid for SDA extensions.

Condition Values Returned

None.

Example

```
sda$dbg_image_info ();
```

SDA outputs the list of images in the following format:

```
Current VMS Version:    "X6DX-FT1"
```

```
    Process Activated Images:
```

Start VA	End VA	Image Name
00010000	000301FF	SDA
00032000	00177FFF	SDA\$SHARE
7B508000	7B58BFFF	DECC\$SHR
7B2D8000	7B399FFF	DPML\$SHR
7B288000	7B2C9FFF	CMA\$TIS_SHR
7B698000	7B6D9FFF	LBRSHR
0021A000	0025A3FF	SCRSHR
00178000	002187FF	SMGSHR
7B1E8000	7B239FFF	LIBRTL
7B248000	7B279FFF	LIBOTS
80C140D0	80C23120	SYS\$BASE_IMAGE
80C036B8	80C05288	SYS\$PUBLIC_VECTORS
002C6000	002D31FF	PRGDEVMSG

```

002D4000  002DA9FF  SHRIMGMSG
002DC000  002DFFFF  DECC$MSG
00380000  003E03FF  MBX$SDA

```

10.5.12. SDA\$DEALLOCATE

Deallocates and frees dynamic memory.

Format

```
void sda$deallocate (void *ptr_block, uint32 size);
```

Arguments

ptr_block

OpenVMS usage	address
type	longword (unsigned)
access	read only
mechanism	by value

Starting address of block to be freed.

size

OpenVMS usage	longword_unsigned
type	longword (unsigned)
access	read only
mechanism	by value

Size of block to deallocate (in bytes).

Description

The specified memory is deallocated. Note that this is the only supported mechanism for deallocation of dynamic memory.

Related Routine

SDA\$ALLOCATE

Condition Values Returned

None.

If an error occurs, it is signaled and the SDA session aborted.

Example

```
PCB *local_pcb;
...
```

```
sda$deallocate ((void *)local_pcb, PCB$C_LENGTH;
```

This call deallocates the block of length `PCB$C_LENGTH` whose address is stored in the pointer `LOCAL_PCB`.

10.5.13. SDA\$DELETE_PREFIX

Deletes all symbols with the specified prefix.

Format

```
void sda$delete_prefix (char *prefix);
```

Arguments

prefix

OpenVMS usage	char_string
type	character string
access	read only
mechanism	by reference

The address of the prefix string.

Description

This routine searches the SDA symbol table and deletes all symbols that begin with the specified string.

Condition Values Returned

None.

10.5.14. SDA\$DISPLAY_HELP

Displays online help.

Format

```
void sda$display_help (char *library_desc, char *topic_desc);
```

Arguments

library

OpenVMS usage	char_string
type	character string
access	read only
mechanism	by reference

Address of library filespec. Specify as zero-terminated ASCII string.

topic

OpenVMS usage	char_string
type	character string
access	read only
mechanism	by reference

Address of topic name. Specify as zero-terminated ASCII string.

Description

Help from the specified library is displayed on the given topic.

Condition Values Returned

None.

Example

```
sda$display_help ("SYS$HELP:SDA", "HELP");
```

This call produces the following output at the terminal:

```
HELP
```

The System Dump Analyzer (SDA) allows you to inspect the contents of memory as saved in the dump taken at crash time or as exists in a running system. You can use SDA interactively or in batch mode. You can send the output from SDA to a listing file. You can use SDA to perform the following operations:

```

Assign a value to a symbol
Examine memory of any process
Format instructions and blocks of data
Display device data structures
Display memory management data structures
Display a summary of all processes on the system
Display the SDA symbol table
Copy the system dump file
Send output to a file or device
Read global symbols from any object module
Send output to a file or device
Read global symbols from any object module
Search memory for a given value

```

For help on performing these functions, use the HELP command and specify a topic.

Format

```
HELP [topic-name]
```

Additional information available:

Parameter

HELP Subtopic?

10.5.15. SDA\$ENSURE

Ensures sufficient space on the current output page.

Format

```
void sda$ensure (uint32 lines);
```

Arguments

lines

OpenVMS usage	longword_unsigned
type	longword (unsigned)
access	read only
mechanism	by value

Number of lines to fit on a page.

Description

This routine checks and makes sure that the number of lines specified fit on the current page; otherwise, it issues a page break.

Condition Values Returned

None.

Example

```
sda$ensure (5);
```

This call ensures that there are five lines left on the current page, and it outputs a page break if there are not.

10.5.16. SDA\$FAO

Formats data into a buffer.

Format

```
char * sda$fao (char * ctrstr, char * buffer, int buflen, __optional_params);
```

Arguments

ctrstr

OpenVMS usage	char_string
---------------	--------------------

type	character-coded text string
access	read only
mechanism	by reference

Address of a zero-terminated FAO control string.

buffer

OpenVMS usage	char_string
type	character string
access	write only
mechanism	by reference

Address of a string buffer into which to store the formatted string.

buflen

OpenVMS usage	longword_unsigned
type	longword (unsigned)
access	read only
mechanism	by value

Maximum size of the string buffer.

prmlst

OpenVMS usage	varying_arg
type	quadword (signed or unsigned)
access	read only
mechanism	by value

Optional FAO parameters. All arguments after buflen are copied into a quadword parameter list, as used by \$FAOL_64.

Description

Formats data into a buffer as a zero-terminated string.

Condition Values Returned

Address of terminating zero	SDA\$FAO returns the address of the terminating zero in the output buffer. This allows successive calls to SDA\$FAO to append strings.
-----------------------------	--

Example

```
char faobuf [16];
char *faoptr;
faoptr = sda$fao ( "!XL",
```



```

        faobuf, sizeof (faobuf),
        0xffffffff);
sda$fao ( ".!XL",
        faoptr, sizeof (faobuf) - strlen (faobuf),
        0x80102030);

```

This example shows the use of SDA\$FAO to append a formatted string to another formatted string.

10.5.17. SDA\$FID_TO_NAME

Translates a file identification (FID) into the equivalent file name.

Format

```
int sda$fid_to_name (char *devptr, unsigned short *fidptr, char *bufptr, int
```

Arguments

devptr

OpenVMS usage	char_string
type	character string
access	read only
mechanism	by reference

The address of the device name string. The device name must be supplied in allocation-class device name (ALLDEVNAM) format, but any leading underscore or trailing colon are ignored.

fidptr

OpenVMS usage	address
type	file identification
access	read only
mechanism	by reference

The address of the three-word file identification.

bufptr

OpenVMS usage	char_string
type	character string
access	write only
mechanism	by reference

The address of a string buffer into which to store the file name string.

buflen

OpenVMS usage	longword
type	longword (unsigned)

access	read only
mechanism	by value

The maximum length of the string buffer.

Description

When analyzing the current system, this routine calls `LIB$FID_TO_NAME` to translate the file identification into a file name. When analyzing a dump, if there is a file data collection available and the specified disk and file identification is included in the collection, the recorded file name will be returned. Return the error condition `SDA$_NOCOLLECT` if there is no collection (for the entire system, this disk, or just this file).

Condition Values Returned

<code>SDA\$_SUCCESS</code>	File identification successfully translated.
<code>SDA\$_NOCOLLECT</code>	No collection available for the system, the specified disk, or the file identification.
Others	An error occurred when <code>LIB\$FID_TO_NAME</code> was called.

Example

```
int status;
char buffer [132];
char *device = $1$DKA0;
unsigned short fid [3] = {1, 1, 0};
status = sda$fid_to_name (device, &fid [0], buffer, 132);
if (status & 1)
    sda$print ("Filename is !AZ", buffer);
else
    sda$print ("File ID could not be translated");
```

This example shows the translation of file ID (1,1,0) on `1DKA0:`, which is `1DKA0:[000000]INDEXF.SYS;1`.

10.5.18. SDA\$FORMAT

Displays the formatted contents of a data structure.

Format

```
void sda$format (VOID_PQ struct_addr, __optional_params);
```

Arguments

struct_addr

OpenVMS usage	address
type	quadword (unsigned)
access	read only

mechanism	by value
-----------	-----------------

The address in the system dump of the data structure to be formatted.

options

OpenVMS usage	mask_longword
type	longword (unsigned)
access	read only
mechanism	by value

The following provides more information on options:

Option	Meaning
None	Uses structure type from the xxx\$B_TYPE and/or xxx\$B_SUBTYPE field of the structure. This is the default.
SDA_OPT\$M_FORMAT_TYPE	Uses the structure type given in struct_prefix.
SDA_OPT\$M_FORMAT_PHYSICAL	Indicates that struct_addr is a physical address instead of a virtual address.

struct_prefix

OpenVMS usage	char_string
type	character string
access	read only
mechanism	by reference

Address of structure name string (zero-terminated).

Description

This routine displays the formatted content of a data structure that begins at the address specified. If no symbol prefix is passed, then SDA tries to find the symbols associated with the block type specified in the block-type byte of the data structure.

Condition Values Returned

None.

Example

```
PCB *local_pcb;
PHD *local_phd;
...
sda$format (local_pcb);
sda$format (local_phd, SDA_OPT$M_FORMAT_TYPE, "PHD");
```

The first call formats the structure whose system address is held in the variable LOCAL_PCB, determining the type from the type and/or subtype byte of the structure. The second call formats the structure whose system address is held in the variable LOCAL_PHD, using PHD symbols.

10.5.19. SDA\$FORMAT_HEADING

Formats a new page heading.

Format

```
void sda$format_heading (char *ctrstr, __optional_params);
```

Arguments

ctrstr

OpenVMS usage	char_string
type	character-coded text string
access	read only
mechanism	by reference

Address of control string (zero-terminated ASCII string).

prmlst

OpenVMS usage	varying_arg
type	quadword (signed or unsigned)
access	read only
mechanism	by value

FAO parameters that are optional. All arguments after the control string are copied into a quadword parameter list as used by \$FAOL_64.

Description

This routine prepares and saves the page heading to be used whenever SDA\$NEW_PAGE is called. Nothing is output either until SDA\$NEW_PAGE is next called, or a page break is necessary because the current page is full.

Condition Values Returned

None.

If the \$FAOL_64 call issued by SDA\$FORMAT_HEADING fails, the control string is used as the page heading.

Example

```
char hw_name[64];
...
sda$get_hw_name (hw_name, sizeof(hw_name));
sda$format_heading (
    "SDA Extension Commands, system type !AZ",
    &hw_name);
sda$new_page ();
```

This example produces the following heading:

```
SDA Extension Commands, system type DEC 3000 Model 400
-----
```

10.5.20. SDA\$GET_ADDRESS

Gets the address value of the current memory location.

Format

```
void sda$get_address (VOID_PQ *address);
```

Arguments

address

OpenVMS usage	quadword_unsigned
type	quadword (unsigned)
access	write only
mechanism	by reference

Location to store the current 64-bit memory address.

Description

Returns the current address being referenced by SDA (location ".").

Condition Values Returned

None.

Example

```
VOID_PQ current_address;
...
sda$get_address (&current_address);
```

This call stores SDA's current memory location in the long pointer `CURRENT_ADDRESS`.

10.5.21. SDA\$GET_BLOCK_NAME

Returns the name of a structure, given its type and/or subtype.

Format

```
void sda$get_block_name (uint32 block_type, uint32 block_subtype, char *buffer);
```

Arguments

block_type

OpenVMS usage	longword_unsigned
type	longword (unsigned)
access	read only
mechanism	by value

Block type in range 0 - 255 (usually extracted from xxx\$b_type field).

block_subtype

OpenVMS usage	longword_unsigned
type	longword (unsigned)
access	read only
mechanism	by value

Block subtype in range 0 - 255 (ignored if the given block type has no subtypes).

buffer_ptr

OpenVMS usage	char_string
type	character string
access	write only
mechanism	by reference

Address of buffer to save block name, which is returned as a zero-terminated string.

buffer_len

OpenVMS usage	longword_unsigned
type	longword (unsigned)
access	read only
mechanism	by value

Length of buffer to receive block name.

Description

Given the block type and/or subtype of a structure, this routine returns the name of the structure. If the structure type is one that has no subtypes, the given subtype is ignored. If the structure type is one that has subtypes, and the subtype is given as zero, the name of the block type itself is returned. If an invalid type or subtype (out of range) is given, an empty string is returned.

Note

The buffer should be large enough to accommodate the largest possible block name (25 bytes plus the termination byte). The block name is truncated if it is too long for the supplied buffer.

Condition Values Returned

None.

Example

```
char buffer[32];
...
sda$get_block_name (0x6F, 0x20,
    buffer,
    sizeof (buffer));
if (strlen (buffer) == 0)
    sda$print ("Block type: no named type/subtype");
else
    sda$print ("Block type: !AZ", buffer);
```

This example produces the following output:

```
Block type: VCC_CFCB
```

10.5.22. SDA\$GET_BUGCHECK_MSG

Gets the text associated with a bugcheck code.

Format

```
void sda$get_bugcheck_msg (uint32 bugcheck_code, char *buffer_ptr, uint32 buff
```

Arguments

bugcheck_code

OpenVMS usage	longword_unsigned
type	longword (unsigned)
access	read only
mechanism	by value

The bugcheck code to look up.

buffer_ptr

OpenVMS usage	char_string
type	character string
access	write only
mechanism	by reference

Address of buffer to save bugcheck message.

buffer_len

OpenVMS usage	longword_unsigned
type	longword (unsigned)
access	read only
mechanism	by value

Length of buffer to receive message.

Description

Gets the string representing the bugcheck code passed as the argument. The bugcheck message string is passed in the buffer (represented as a pointer and length) as a zero-terminated ASCII string.

Note

The buffer should be large enough to accommodate the largest possible bugcheck message (128 bytes including the termination byte). The text is terminated if it is too long for the supplied buffer.

Condition Values Returned

None.

Example

```
char buffer[128];
...
sda$get_bugcheck_msg (0x108, buffer, sizeof(buffer));
sda$print ("Bugcheck code 108 (hex) =");
sda$print ("!_\"!AZ\\"", buffer);
```

This example produces the following output:

```
Bugcheck code 108 (hex) =
      "DOUBLDALOC, Double deallocation of swap file space"
```

10.5.23. SDA\$GET_CURRENT_CPU

Gets the CPU database address of the currently selected CPU.

Format

```
void sda$get_current_cpu (CPU **cpudb);
```

Arguments

cpudb

OpenVMS usage	address
type	longword (unsigned)
access	write only
mechanism	by reference

Location to which the address of the CPU database is to be returned.

Description

This routine causes SDA to return the address of the database for the currently selected CPU.

Condition Values Returned

None.

Example

```
#include <cpudef>
CPU *current_cpu;
sda$get_current_cpu ( &current_cpu );
```

In this example, the system address of the database for the current CPU is returned in variable *current_cpu*.

10.5.24. SDA\$GET_CURRENT_PCB

Gets the PCB address of the "SDA current process" currently selected.

Format

```
void sda$get_current_pcb (PCB **pcbaddr);
```

Arguments

pcbaddr

OpenVMS usage	quadword_unsigned
type	quadword (unsigned)
access	write only
mechanism	by reference

Location in which to store the current PCB address.

Description

The PCB address of the process currently selected by SDA is returned in the specified location.

Condition Values Returned

None.

Example

```
PCB *current_pcb;
...
sda$get_current_pcb ( &current_pcb );
```

This call stores the system address of the PCB of the process currently being referenced by SDA in the pointer *CURRENT_PCB*.

10.5.25. SDA\$GET_DEVICE_NAME

Gets the device name, given the UCB address of the device.

Format

```
int sda$get_device_name (VOID_PQ ucb_addr, char *name_buf, intname_len);
```

Arguments

ucb_addr

OpenVMS usage	address
type	quadword (unsigned)
access	read only
mechanism	by value

System address of the Unit Control Block of the device.

name_buf

OpenVMS usage	char_string
type	character string
access	write only
mechanism	by reference

Address of buffer to receive device name.

name_len

OpenVMS usage	longword_unsigned
type	longword (unsigned)
access	read only
mechanism	by value

Length of buffer to receive device name.

Description

This routine creates and returns the name for the device described by the given UCB. The device name is returned as a zero-terminated ASCII string.

Note

The buffer should be large enough to accommodate the largest possible device name (32 bytes including the termination byte). The text is terminated if it is too long for the supplied buffer.

Condition Values Returned

SDA\$_SUCCESS	Successful completion
SDA\$_NOTAUCB	The address given is not the address of a UCB

SDA\$_NOREAD	The data is inaccessible for some reason
Others	The data is inaccessible for some reason

Example

```
VOID_PQ address;
    char buffer[32];
    ...
    sda$parse_command ("SHOW DEVICE DKB0:");
    sda$symbol_value ("UCB", (uint64 *)&address);
    sda$get_device_name (address, buffer, 32);
    sda$print ("UCB address: !XL = \"!AZ:\", address, buffer);
```

This example produces the following output:

```
UCB address: 814A9A40 = "$31$DKB0:"
```

10.5.26. SDA\$GET_FLAGS

Obtain environment flags that indicate how SDA is being used.

Format

```
int sda$get_flags (SDA_FLAGS *flagaddr);
```

Arguments

flagaddr

OpenVMS usage	address
type	SDA_FLAGS structure
access	write only
mechanism	by reference

The address of the location where the environment flags are to be returned.

Description

SDA provides a set of flag bits that indicate if it is being used to analyze the current system, a system dump, a process dump, and so on. The flag bits that can be returned are described in Table 10.1 and are defined in SDA_FLAGSDEF.H in SYS\$LIBRARY:SYS\$LIB_C.TLB.

Condition Values Returned

None.

Example

```
SDA_FLAGS flags;
sda$get_flags (&flags);
if (flags.sda_flags$v_current)
```

```
sda$print (Analyzing the current system);
```

This example shows the use of SDA\$GET_FLAGS.

10.5.27. SDA\$GET_HEADER

Returns pointers to local copies of the dump file header and the error log buffer together with the sizes of those data structures; optionally returns pointers and sizes for the crash error log entry and trap data(if any).

Format

```
void sda$get_header (DMP **dmp_header, uint32 *dmp_header_size, void**errlog_buf,
```

Arguments

dmp_header

OpenVMS usage	address
type	longword (unsigned)
access	write only
mechanism	by reference

Location in which to store the address of the copy of the dump file header held by SDA.

dmp_header_size

OpenVMS usage	longword_unsigned
type	longword (unsigned)
access	write only
mechanism	by reference

Location in which to store the size of the dump file header.

errlog_buf

OpenVMS usage	address
type	longword (unsigned)
access	write only
mechanism	by reference

Location in which to store the address of the copy of the error log buffer held by SDA.

errlog_buf_size

OpenVMS usage	longword_unsigned
type	longword (unsigned)
access	write only

mechanism	by reference
-----------	---------------------

Location in which to store the size of the error log buffer.

crasherl_buf

OpenVMS usage	address
type	longword (unsigned)
access	write only
mechanism	by reference

Location in which to store the address of the copy of the crash error log entry held by SDA.

crasherl_buf_size

OpenVMS usage	longword_unsigned
type	longword (unsigned)
access	write only
mechanism	by reference

Location in which to store the size of the crash error log entry.

trapinfo_buf

OpenVMS usage	address
type	longword (unsigned)
access	write only
mechanism	by reference

Location in which to store the address of the copy of the trap info, if any, held by SDA.

trapinfo_buf_size

OpenVMS usage	longword_unsigned
type	longword (unsigned)
access	write only
mechanism	by reference

Location in which to store the size of the trap data, if any.

Description

This routine returns the addresses and sizes of the dump header, error logs, and optionally the crash error log entry and trap data read by SDA when the dump file is opened. If this routine is called when the running system is being analyzed with ANALYZE/SYSTEM, then the following occurs:

- Returns the address and size of SDA's dump header buffer, but the header contains zeroes
- Returns zeroes for the address and size of SDA's error log buffer, the crash error log entry and trap data

Trap data only exists if an access violation occurs while the dump is being written. Usually, the returned `trapinfo_buf` and `trapinfo_buf_size` will be zero.

Condition Values Returned

None.

Example

```
DMP *dmp_header;
uint32 dmp_header_size;
char *errlog_buffer;
uint32 errlog_buffer_size;
...
sda$get_header (&dmp_header,
               &dmp_header_size,
               (void **)&errlog_buffer,
               &errlog_buffer_size);
```

This call stores the address and size of SDA's copy of the dump file header in `DMP_HEADER` and `DMP_HEADER_SIZE`, and stores the address and size of SDA's copy of the error log buffers in `ERRLOG_BUFFER` and `ERRLOG_BUFFER_SIZE`, respectively.

10.5.28. SDA\$GET_HW_NAME

Returns the full name of the hardware platform where the dump was written.

Format

```
void sda$get_hw_name (char *buffer_ptr, uint32 buffer_len);
```

Arguments

`buffer_ptr`

OpenVMS usage	char_string
type	character string
access	write only
mechanism	by reference

Address of buffer to save HW name.

`buffer_len`

OpenVMS usage	longword_unsigned
type	longword (unsigned)
access	read only
mechanism	by value

Length of buffer to receive HW name.

Description

Returns a zero-terminated ASCII string representing the platform hardware name and puts it in the buffer passed as the argument.

Note

The buffer should be large enough to accommodate the largest possible hardware platform name (120 bytes including the termination byte). The name is truncated if it is too long for the supplied buffer.

Condition Values Returned

None.

Example

```
char hw_name[64];
...
sda$get_hw_name (hw_name, sizeof(hw_name));
sda$print ("Platform name: \"!AZ\\"", hw_name);
```

This example produces output of the form:

```
Platform name: "DEC 3000 Model 400"
```

10.5.29. SDA\$GET_IMAGE_OFFSET

Maps a given virtual address onto an image or execllet.

Format

```
COMP_IMG_OFF sda$get_image_offset (VOID_PQ va, VOID_PQ img_info, VOID_PQ subin
```

Arguments

va

OpenVMS usage	address
type	quadword (unsigned)
access	read only
mechanism	by value

Virtual address of interest.

img_info

OpenVMS usage	address
type	quadword (unsigned)
access	write only
mechanism	by reference

Pointer to return addr of LDRIMG or IMCB block.

subimg_info

OpenVMS usage	address
type	quadword (unsigned)
access	write only
mechanism	by reference

Pointer to return addr of ISD_OVERLAY or KFERES.

offset

OpenVMS usage	quadword_unsigned
type	quadword (unsigned)
access	write only
mechanism	by reference

Pointer to address to return offset from image.

Description

Given a virtual address, this routine finds in which image it falls and returns the image information and offset. The loaded image list is traversed first to find this information. If it is not found, then the activated image list of the currently selected process is traversed. If still unsuccessful, then the resident installed images are checked.

Condition Values Returned

SDA_CIO\$V_VALID	Set if image offset is found
SDA_CIO\$V_PROCESS	Set if image is an activated image
SDA_CIO\$V_SLICED	Set if the image is sliced
SDA_CIO\$V_COMPRESSED	Set if activated image contains compressed data sections
SDA_CIO\$V_ISD_INDEX	Index into ISD_LABELS table (on Alpha, only for LDRIMG execlts)

The status returned indicates the type of image if a match was found.

SDA_CIO\$V_xxx flags set:	img_info type:	subimg_info type:
VALID	LDRIMG	n/a
VALID && SLICED	LDRIMG	ISD_OVERLAY
VALID && PROCESS	IMCB	n/a
VALID && PROCESS && SLICED	IMCB	KFERES_SECTION

On Integrity servers, SDA_CIO\$V_SLICED will always be set if SDA_CIO\$V_VALID is set.

Table 10.2 and Table 10.3 describe the ISD_LABELS index on Alpha and Integrity server systems.

Table 10.2. Alpha ISD_LABELS Index

Index	Name	Meaning
0	SDA_CIO\$K_NPRO	Nonpaged read only
1	SDA_CIO\$K_NPRW	Nonpaged read/write
2	SDA_CIO\$K_PRO	Paged read only
3	SDA_CIO\$K_PRW	Paged read/write
4	SDA_CIO\$K_FIX	Fixup
5	SDA_CIO\$K_INIT	Initialization

Table 10.3. Integrity server ISD_Labels Index

Index	Name	Meaning
0	SDA_CIO\$K_FIX	Fixup
1	SDA_CIO\$K_PROMO_CODE	Promote (code)
2	SDA_CIO\$K_PROMO_DATA	Promote (data)
3	SDA_CIO\$K_INIT_CODE	Initialization (code)
4	SDA_CIO\$K_INIT_DATA	Initialization (data)
5	SDA_CIO\$K_CODE	Code
6	SDA_CIO\$K_SHORT_RW	Short data (read/write)
7	SDA_CIO\$K_SHORT_RO	Short data (read only)
8	SDA_CIO\$K_RW	Data (read/write)
9	SDA_CIO\$K_RO	Data (read only)
10	SDA_CIO\$K_SHORT_DZ	Short data (demand zero)
11	SDA_CIO\$K_SHORT_TDZ	Short data (trailing demand zero)
12	SDA_CIO\$K_DZERO	Demand zero
13	SDA_CIO\$K_TR_DZERO	Trailing demand zero

Example

```

VOID_PQ va = (VOID_PQ)0xFFFFFFFF80102030;
COMP_IMG_OFF sda_cio;
int64 img_info;
int64 subimg_info;
int64 offset;
...
sda_cio = sda$get_image_offset (va,
                               &img_info,
                               &subimg_info,
                               &offset);

```

For an example of code that interprets the returned COMP_IMG_OFF structure, see the supplied example program, SYS\$EXAMPLES:MBX\$SDA.C.

10.5.30. SDA\$GET_INPUT

Reads input commands.

Format

```
int sda$get_input (char *prompt, char *buffer, uint32 buflen);
```

Arguments

prompt

OpenVMS usage	char_string
type	character string
access	read only
mechanism	by reference

Address of prompt string (zero-terminated ASCII string).

buffer

OpenVMS usage	char_string
type	character string
access	write only
mechanism	by reference

Address of buffer to store command.

buflen

OpenVMS usage	longword_unsigned
type	longword (unsigned)
access	read only
mechanism	by value

Maximum length of buffer.

Description

The command entered is returned as a zero-terminated string. The string is not uppercased. If you do not enter input but simply press<return> or <ctrl/Z>, the routine returns a null string.

Condition Values Returned

SS\$_NORMAL	Successful completion.
RMS\$_EOF	User pressed <ctrl/Z>

Example

```
int status;
char buffer[128];
...
status = sda$get_input ( "MBX> ", buffer, sizeof (buffer) );
```

This call prompts you for input with "MBX> " and stores the response in the buffer.

10.5.31. SDA\$GET_LINE_COUNT

Obtains the number of lines currently printed on the current page.

Format

```
void sda$get_line_count (uint32 *line_count);
```

Arguments

line_count

OpenVMS usage	longword_unsigned
type	longword (unsigned)
access	write only
mechanism	by reference

The number of lines printed on current page.

Description

Returns the number of lines that have been printed so far on the current page.

Condition Values Returned

None.

Example

```
uint32 line_count;
...
sda$get_line_count (&line_count);
```

This call copies the current line count on the current page of output to the location LINE_COUNT.

10.5.32. SDA\$GETMEM

Reads dump or system memory and signals a warning if inaccessible.

Format

```
int sda$getmem (VOID_PQ start, void *dest, int length, __optional_params);
```

Arguments

start

OpenVMS usage	address
type	quadword (unsigned)

access	read only
mechanism	by value

Starting virtual address in dump or system.

dest

OpenVMS usage	address
type	varies
access	write only
mechanism	by reference

Return buffer address.

length

OpenVMS usage	longword_unsigned
type	longword (unsigned)
access	read only
mechanism	by value

Length of transfer.

physical

OpenVMS usage	longword_unsigned
type	longword (unsigned)
access	read only
mechanism	by value

0: <start> is a virtual address. This is the default.

1: <start> is a physical address.

Description

This routine transfers an area from the memory in the dump file or the running system to the caller's return buffer. It performs the necessary address translation to locate the data in the dump file. SDA \$GETMEM signals a warning and returns an error status if the data is inaccessible.

Related Routines

SDA\$REQMEM and SDA\$TRYMEM

Condition Values Returned

SDA\$_SUCCESS	Successful completion
SDA\$_NOREAD	The data is inaccessible for some reason.

SDA\$_NOTINPHYS	The data is inaccessible for some reason.
Others	The data is inaccessible for some reason.

If a failure status code is returned, it has already been signaled as a warning.

Example

```
int status;
PCB *current_pcb;
PHD *current_phd;
...
status = sda$getmem ((VOID_PQ)&current_pcb->pcb$l_phd, &current_phd, 4);
```

This call returns the contents of the PCB\$L_PHD field of the PCB, whose system address is in the pointer CURRENT_PCB, to the pointer CURRENT_PHD.

10.5.33. SDA\$INSTRUCTION_DECODE

Translates one machine instruction into the assembler string equivalent.

Format

```
int sda$instruction_decode (void *istream_ptr, char *buffer, uint32buflen, __c
```

Arguments

istream_ptr

OpenVMS usage	address
type	longword (unsigned)
access	read/write
mechanism	by reference

Address of the pointer that points to a copy of the i-stream in a local buffer.

buffer

OpenVMS usage	char_string
type	character string
access	write only
mechanism	by reference

Address of a string buffer into which to store the output assembler string.

buflen

OpenVMS usage	longword_unsigned
type	longword (unsigned)
access	read only

mechanism	by value
-----------	-----------------

Maximum size of the string buffer.

template_buffer

OpenVMS usage	char_string
type	character string
access	write only
mechanism	by reference

(Integrity servers only.) Address of a string buffer into which to store the template string.

template_buflen

OpenVMS usage	longword_unsigned
type	longword (unsigned)
access	read only
mechanism	by value

(Integrity servers only.) Maximum size of the template buffer.

Description

Translates a machine instruction into the assembler string equivalent. Alpha instructions are always 4 bytes long; Integrity server instructions are always in bundles that are 16 bytes long. The instruction stream must first be read into local memory and then the address of a pointer to the local copy of the instruction stream is passed to the routine. For every successful translated instruction, the pointer is automatically updated to point to the next instruction on Alpha or slot on Integrity servers.

The output assembler string and optionally the template string is zero-terminated and in case of a failure a null string is returned.

The `template_buffer` and `template_buflen` arguments only apply to Integrity servers and are optional.

Condition Values Returned

SS\$_NORMAL	Successful completion.
SS\$_BADPARAM	Any of the following failures:
	Output buffer too small Invalid register Invalid opcode class/format Could not translate instruction

Examples

1. Alpha servers

```
int status;
VOID_PQ va = (VOID_PQ)0xFFFFFFFF80102030;
uint32 instruction;
uint32 *istream = &instruction;
char buffer[64];
```

```

...
sda$reqmem (va, &instruction, 4);
status = sda$instruction_decode (&istream, buffer, sizeof (buffer));
if ( !$VMS_STATUS_SUCCESS (status) )
    sda$print ( "SDA$INSTRUCTION_DECODE failed, status = !XL", status);
else
    sda$print ( "VA: !AZ", buffer );)

```

This example on an Alpha system reads the instruction at dump location VA and decodes it, putting the result into BUFFER, and displays the instruction. Pointer ISTREAM is incremented (to the next longword).

2. Integrity servers

```

int status;
VOID_PQ va = (VOID_PQ)0xFFFFFFFF80102030;
uint64 instruction [2];
uint64 *istream = &instruction;
char buffer [64];
char template [16];
sda$reqmem (va, &instruction, 16);
status = sda$instruction_decode ( &istream, buffer, sizeof (buffer),
                                template, sizeof (template) );
if ( !$VMS_STATUS_SUCCESS (status) )
    sda$print ( "SDA$INSTRUCTION_DECODE failed, status = !XL", status);
else
    {
        sda$print ( "                { !AZ", template );
        sda$print ( "VA:                !AZ", buffer );
        while (((int)istream & 7) != 0) // local buffer only has to be quadword
            aligned
            {
                status = sda$instruction_decode ( &istream, buffer, sizeof
            (buffer) );
                if ( !$VMS_STATUS_SUCCESS (status) )
                    {
                        sda$print ( "SDA$INSTRUCTION_DECODE failed, status = !XL",
            status);
                        break;
                    }
                else
                    sda$print ( "                !AZ", buffer );
            }
        sda$print ( "                }" );
    }

```

This example for Integrity servers reads the instruction bundle at dump location VA and decodes it, displaying each of the instructions in the bundle. Pointer ISTREAM is incremented (to the next octaword bundle).

10.5.34. SDA\$NEW_PAGE

Begins a new page of output.

Format

```
void sda$new_page ();
```

Arguments

None.

Description

This routine causes a new page to be written and outputs the page heading (established with `SDA$FORMAT_HEADING`) and the current subheading (established with `SDA$SET_HEADING_ROUTINE`).

Condition Values Returned

None.

Example

```
sda$new_page ();
```

This call outputs a page break and displays the current page heading and subheading (if any).

10.5.35. SDA\$PARSE_COMMAND

Parses and executes an SDA command line.

Format

```
void sda$parse_command (char *cmd_line, __optional_params);
```

Arguments

cmd_line

OpenVMS usage	char_string
type	character string
access	read only
mechanism	by reference

Address of a valid SDA command line (zero-terminated).

options

OpenVMS usage	longword_unsigned
type	longword (unsigned)
access	read only
mechanism	by value

The **options** argument has the following values:

Value	Meaning
<code>SDA_OPT\$K_PARSE_DONT_SAVE</code>	Indicates "do not save this command." This is the default.

Value	Meaning
SDA_OPT\$K_PARSE_SAVE	Indicates "save this command." That is, it can be recalled with KPO or REPEAT.

Description

Not every SDA command has a callable extension interface. For example, to redirect SDA's output, you would pass the command string "SET OUTPUTMBX.LIS" to this parse command routine. Abbreviations are allowed.

Condition Values Returned

None.

Example

```
sda$parse_command ("SHOW ADDRESS 80102030");
```

This call produces the following output:

```
FFFFFFFF.80102030 is an S0/S1 address

Mapped by Level-3 PTE at: FFFFFFFD.FFE00408
Mapped by Level-2 PTE at: FFFFFFFD.FF7FF800
Mapped by Level-1 PTE at: FFFFFFFD.FF7FDF8
Mapped by Selfmap PTE at: FFFFFFFD.FF7FDF0

Also mapped in SPT window at: FFFFFFFF.FFDF0408
```

The "SHOW ADDRESS" command is not recorded as the most recent command for use with the KPO key or the REPEAT command.

10.5.36. SDA\$PRINT

Formats and prints a single line.

Format

```
int sda$print (char *ctrstr, __optional_params);
```

Arguments

ctrstr

OpenVMS usage	char_string
type	character-coded text string
access	read only
mechanism	by reference

Address of a zero-terminated FAO control string.

prmlst

OpenVMS usage	varying_arg
type	quadword (signed or unsigned)
access	read only
mechanism	by value

Optional FAO parameters. All arguments after the control string are copied into a quadword parameter list, as used by \$FAOL_64.

Description

Formats and prints a single line. This is normally output to the terminal, unless you used the SDA commands SET OUTPUT or SET LOG to redirect or copy the output to a file.

Condition Values Returned

SDA\$_SUCCESS	Indicates a successful completion.
SDA\$_CNFLTARGS	Indicates more than twenty FAO parameters given.
Other	Returns from the \$PUT issued by SDA\$PRINT (the error is also signaled). If the \$FAOL_64 call issued by SDA\$PRINT fails, the control string is output.

Example

```
char buffer[32];
...
sda$get_block_name (0x6F, 0x20,
    buffer,
    sizeof (buffer));
sda$print ("Block type: !AZ", buffer);
```

This example outputs the following line:

```
Block type: VCC_CFCB
```

10.5.37. SDA\$READ_SYMFILE

Reads symbols from a given file.

Format

```
int sda$read_symfile (char *filespec, uint32 options, __optional_params);
```

Arguments

filespec

OpenVMS usage	char_string
type	character string
access	read only

mechanism	by reference
-----------	---------------------

Address of file or directory specification from which to read the symbols (zero-terminated ASCII string).

options

OpenVMS usage	longword_unsigned
type	longword (unsigned)
access	read only
mechanism	by value

Indicates type of symbol file and flags, as shown in the following:

Flags	Effect
SDA_OPT\$M_READ_FORCE	read/force <file>
SDA_OPT\$M_READ_IMAGE	read/image <file>
SDA_OPT\$M_READ_SYMVA	read/symva <file>
SDA_OPT\$M_READ_RELO	read/relo <file>
SDA_OPT\$M_READ_EXEC	read/exec [<dir>]
SDA_OPT\$M_READ_NOLOG	/nolog, suppress count of symbols read
SDA_OPT\$M_READ_FILESPEC	<file> or <dir> given
SDA_OPT\$M_READ_NOSIGNAL	return status, without signaling errors

relocate_base

OpenVMS usage	address
type	longword (unsigned)
access	read only
mechanism	by value

Base address for symbols (nonsliced symbols).

symvect_va

OpenVMS usage	address
type	longword (unsigned)
access	read only
mechanism	by value

The symbol vector address (symbols are offsets into the symbol vector).

symvect_size

OpenVMS usage	longword_unsigned
type	longword (unsigned)
access	read only

mechanism	by value
-----------	-----------------

Size of symbol vector.

loaded_img_info

OpenVMS usage	address
type	longword (unsigned)
access	read only
mechanism	by reference

The address of \$LDRIMG data structure with execlt information.

Description

This command reads symbols from a given file to add symbol definitions to the working symbol table by reading GST entries. The file is usually a symbol file (.STB) or an image (.EXE). If SDA_OPT \$M_READ_EXEC is specified in the options, then the filespec is treated as a directory specification, where symbol files and/or image files for all execlts may be found (as with READ/EXECUTIVE). If no directory specification is given, the logical name SDA\$READ_DIR is used.

Note that when SDA reads symbol files and finds routine names, the symbol name that matches the routine name is set to the address of the procedure or function descriptor. A second symbol name, the routine name with "_C" appended, is set to the start of the routine's prologue.

Condition Values Returned

SDA\$_SUCCESS	Successful completion.
SDA\$_CNFLTARGS	No filename given and SDA_OPT \$M_READ_EXEC not set.

Other errors are signaled and/or returned, exactly as though the equivalent SDA READ command had been used. Use HELP/MESSAGE for explanations.

Example

```
sda$read_symfile ("SDA$READ_DIR:SYSDEF", SDA_OPT$M_READ_NOLOG);
```

The symbols in SYSDEF.STB are added to SDA's internal symbol table, and the number of symbols found is not output to the terminal.

10.5.38. SDA\$REQMEM

Reads dump or system memory and signals an error if inaccessible.

Format

```
int sda$reqmem (VOID_PQ start, void *dest, int length, __optional_params);
```

Arguments

start

OpenVMS usage	address
type	quadword (unsigned)
access	read only
mechanism	by value

Starting virtual address in dump or system.

dest

OpenVMS usage	address
type	varies
access	write only
mechanism	by reference

Return buffer address.

length

OpenVMS usage	longword_unsigned
type	longword (unsigned)
access	read only
mechanism	by value

Length of transfer.

physical

OpenVMS usage	longword_unsigned
type	longword (unsigned)
access	read only
mechanism	by value

0: <start> is a virtual address. This is the default.

1: <start> is a physical address.

Description

This routine transfers an area from the memory in the dump file or the running system to the caller's return buffer. It performs the necessary address translation to locate the data in the dump file. SDA \$REQMEM signals an error and aborts the current command if the data is inaccessible.

Related Routines

SDA\$GETMEM and SDA\$TRYMEM

Condition Values Returned

SDA\$_SUCCESS	Successful completion.
---------------	------------------------

Any failure is signaled as an error and the current command aborts.

Example

```
VOID_PQ address;
uint32 instruction;
...
sda$symbol_value ("EXE_STD$ALLOCATE_C", (uint64 *)&address);
sda$reqmem (address, &instruction, 4);
```

This example reads the first instruction of the routine EXE_STD\$ALLOCATE into the location INSTRUCTION.

10.5.39. SDA\$SET_ADDRESS

Stores a new address value as the current memory address (".").

Format

```
void sda$set_address (VOID_PQ address);
```

Arguments

address

OpenVMS usage	quadword_unsigned
type	quadword (unsigned)
access	read only
mechanism	by value

Address value to store in current memory location.

Description

The specified address becomes SDA's current memory address (the predefined SDA symbol ".").

Condition Values Returned

None.

Example

```
sda$set_address ((VOID_PQ) 0xFFFFFFFF80102030);
```

This call sets SDA's current address to FFFFFFFF.80102030.

10.5.40. SDA\$SET_CPU

Sets a new SDA CPU context.

Format

```
int sda$set_cpu (int cpu_id);
```

Arguments

cpu_id

OpenVMS usage	longword_unsigned
type	longword (unsigned)
access	read only
mechanism	by value

The desired CPU ID.

Description

This routine causes SDA to set the specified CPU as the currently selected CPU.

Condition Values Returned

SDA\$_SUCCESS	Successful completion.
---------------	------------------------

Any failure is signaled as an error and the current command aborts.

Example

```
int cpu_id = 2;
status = sda$set_cpu ( cpu_id );
```

In this example, SDA's current CPU context is set to the CPU whose number is held in the variable CPU_ID.

10.5.41. SDA\$SET_HEADING_ROUTINE

Sets the current heading routine to be called after each page break.

Format

```
void sda$set_heading_routine (void (*heading_rtn) ());
```

Arguments

heading_rtn

OpenVMS usage	procedure
type	procedure value
access	read only
mechanism	by value

Address of routine to be called after each new page.

Description

When SDA begins a new page of output (either because SDA\$NEW_PAGE was called, or because the current page is full), it outputs two types of headings. The first is the page title, and is set by calling the

routine `SDA$FORMAT_HEADING`. This is the title that is included in the index page of a listing file when you issue a `SET OUTPUT` command. The second heading is typically for column headings, and as this can vary from display to display, you must write a routine for each separate heading. When you call `SDA$SET_HEADING_ROUTINE` to specify a user-written routine, the routine is called each time SDA begins a new page.

To stop the routine from being invoked each time SDA begins a new page, call either `SDA$FORMAT_HEADING` to set a new page title, or `SDA$SET_HEADING_ROUTINE` and specify the routine address as `NULL`.

If the column headings need to be output during a display (that is, in the middle of a page), and then be re-output each time SDA begins a new page, call the user-written routine directly the first time, then call `SDA$SET_HEADING_ROUTINE` to have it be called automatically thereafter.

Condition Values Returned

None.

Example

```
void mbx$title (void)
{
  sda$print ("Mailbox      UCB      ...");
  sda$print ("  Unit      Address  ...");
  sda$print ("-----");
  return;
}
...
sda$set_heading_routine (mbx$title);
...
sda$set_heading_routine (NULL);
```

This example sets the heading routine to the routine `MBX$TITLE`, and later clears it. The routine is called if any page breaks are generated by the intervening code.

10.5.42. SDA\$SET_LINE_COUNT

Sets the number of lines printed so far on the current page.

Format

```
void sda$set_line_count (uint32 line_count);
```

Arguments

line_count

OpenVMS usage	longword_unsigned
type	longword (unsigned)
access	read only
mechanism	by value

The number of lines printed on current page.

Description

The number of lines that have been printed so far on the current page is set to the given value.

Condition Values Returned

None.

Example

```
sda$set_line_count (5);
```

This call sets SDA's current line count on the current page of output to 5.

10.5.43. SDA\$SET_PROCESS

Sets a new SDA process context.

Format

```
int sda$set_process (const char *proc_name, int proc_index, int proc_addr);
```

Arguments

proc_name

OpenVMS usage	character_string
type	character string
access	read only
mechanism	by reference

Address of the process name string (zero-terminated).

proc_index

OpenVMS usage	longword_unsigned
type	longword (unsigned)
access	read only
mechanism	by value

The index of the desired process.

proc_addr

OpenVMS usage	address
type	longword (unsigned)
access	read only
mechanism	by value

The address of the PCB for the desired process.

Description

This routine causes SDA to set the specified process as the currently selected process.

Note

The `proc_name`, `proc_index`, and `proc_addr` are mutually exclusive.

Condition Values Returned

SDA\$_SUCCESS	Successful completion.
---------------	------------------------

Any failure is signaled as an error and the current command aborts.

Example

```
status = sda$set_process ( "JOB_CONTROL", 0, 0);
```

In this example, SDA's current process context is set to the `JOB_CONTROL` process.

10.5.44. SDA\$SKIP_LINES

This routine outputs a specified number of blank lines.

Format

```
void sda$skip_lines (uint32 lines);
```

Arguments

`lines`

OpenVMS usage	longword_unsigned
type	longword (unsigned)
access	read only
mechanism	by value

Number of lines to skip.

Description

The specified number of blank lines are output.

Condition Values Returned

None.

Example

```
sda$skip_lines (2);
```

This call causes two blank lines to be output.

10.5.45. SDA\$SYMBOL_VALUE

Obtains the 64-bit value of a specified symbol.

Format

```
int sda$symbol_value (char *symb_name, uint64 *symb_value);
```

Arguments

symb_name

OpenVMS usage	char_string
type	character string
access	read only
mechanism	by reference

Zero-terminated string containing symbol name.

symb_value

OpenVMS usage	quadword_unsigned
type	quadword (unsigned)
access	write only
mechanism	by reference

Address to receive symbol value.

Description

A search through SDA's symbol table is made for the specified symbol. If found, its 64-bit value is returned.

Condition Values Returned

SDA\$_SUCCESS	Symbol found.
SDA\$_BADSYM	Symbol not found.

Example

```
int status;
VOID_PQ address;
...
status = sda$symbol_value ("EXE_STD$ALLOCATE_C", (uint64 *)&address);
```

This call returns the start address of the prologue of routine

EXE_STD\$ALLOCATE to location ADDRESS.

10.5.46. SDA\$SYMBOLIZE

Converts a value to a symbol name and offset.

Format

```
int sda$symbolize (uint64 value, char *symbol_buf, uint32 symbol_len);
```

Arguments

value

OpenVMS usage	quadword_unsigned
type	quadword (unsigned)
access	read only
mechanism	by value

Value to be translated.

symbol_buf

OpenVMS usage	char_string
type	character string
access	write only
mechanism	by reference

Address of buffer to which to return string.

symbol_len

OpenVMS usage	longword_unsigned
type	longword (unsigned)
access	read only
mechanism	by value

Maximum length of string buffer.

Description

This routine accepts a value and returns a string that contains a symbol and offset corresponding to that value. First the value is checked in the symbol table. If no symbol can be found (either exact match or up to 0XFFF less than the specified value), the value is then checked to see if it falls within one of the loaded or activated images.

Condition Values Returned

SS\$_NORMAL	Successful completion.
SS\$_BUFFEROVF	Buffer too small, string truncated.

SS\$_NOTRAN	No symbolization for this value (null string returned).
-------------	---

Example

```
VOID_PQ va = VOID_PQ(0xFFFFFFFF80102030);
char buffer [64]
status = sda$symbolize (va, buffer, sizeof(buffer));
sda$print ("FFFFFFFF.80102030 = \"!AZ\"", buffer);
```

This example outputs the following:

```
FFFFFFFF.80102030 = "EXE$WRITE_PROCESS_C+00CD0"
```

10.5.47. SDA\$TRYMEM

Reads dump or system memory and returns the error status (without signaling) if inaccessible.

Format

```
int sda$trymem (VOID_PQ start, void *dest, int length, __optional_params);
```

Arguments

start

OpenVMS usage	address
type	quadword (unsigned)
access	read only
mechanism	by value

Starting virtual address in dump or system.

dest

OpenVMS usage	address
type	varies
access	write only
mechanism	by reference

Return buffer address.

length

OpenVMS usage	longword_unsigned
type	longword (unsigned)
access	read only
mechanism	by value

Length of transfer.

physical

OpenVMS usage	longword_unsigned
type	longword (unsigned)
access	read only
mechanism	by value

0: <start> is a virtual address. This is the default.

1: <start> is a physical address.

Description

This routine transfers an area from the memory in the dump file or the running system to the caller's return buffer. It performs the necessary address translation to locate the data in the dump file. SDA \$TRYMEM does not signal any warning or errors. It returns the error status if the data is inaccessible.

Related Routines

SDA\$GETMEM and SDA\$REQMEM

Condition Values Returned

SDA\$_SUCCESS	Successful completion.
SDA\$_NOREAD	The data is inaccessible for some reason.
SDA\$_NOTINPHYS	The data is inaccessible for some reason.
Others	The data is inaccessible for some reason.

Example

```
int status;
DDB *ddb;
...
status = sda$trymem (ddb->ddb$ps_link, ddb, DDB$K_LENGTH);
if ($VMS_STATUS_SUCCESS (status))
    sda$print ("Next DDB is successfully read from dump");
else
    sda$print ("Next DDB is inaccessible");
```

This example attempts to read the next DDB in the DDB list from the dump.

10.5.48. SDA\$TYPE

Formats and types a single line to SYS\$OUTPUT.

Format

```
int sda$type (char *ctrstr, __optional_params);
```

Arguments

ctrstr

OpenVMS usage	char_string
type	character-coded text string
access	read only
mechanism	by reference

Address of a zero-terminated FAO control string.

prmlst

OpenVMS usage	varying_arg
type	quadword (signed or unsigned)
access	read only
mechanism	by value

Optional FAO parameters. All arguments after the control string are copied into a quadword parameter list, as used by \$FAOL_64.

Description

Formats and prints a single line to the terminal. This is unaffected by the use of the SDA commands SET OUTPUT or SET LOG.

Condition Values Returned

SDA\$_SUCCESS	Indicates a successful completion.
SDA\$_CNFLTARGS	Indicates more than twenty FAO parameters given.
Other	Returns from the \$PUT issued by SDA\$TYPE (the error is also signaled). If the \$FAOL_64 call issued by SDA\$TYPE fails, the control string is output.

Example

```
int status;
...
status = sda$type ("Invoking SHOW SUMMARY to output file...");
```

This example displays the message "Invoking SHOW SUMMARY to output file..." to the terminal.

10.5.49. SDA\$VALIDATE_QUEUE

Validates queue structures.

Format

```
void sda$validate_queue (VOID_PQ queue_header, __optional_params);
```

Arguments

queue_header

OpenVMS usage	address
---------------	----------------

type	quadword (unsigned)
access	read only
mechanism	by value

Address from which to start search.

options

OpenVMS usage	mask_longword
type	longword (unsigned)
access	read only
mechanism	by value

The following table shows the flags that indicate the type of queue:

Flag	Meaning
None	Defaults to doubly-linked longword queue
SDA_OPT\$M_QUEUE_BACKLINK	Validates the integrity of a doubly-linked queue using the back links instead of the forward links
SDA_OPT\$M_QUEUE_LISTQUEUE	Displays queue elements for debugging
SDA_OPT\$M_QUEUE_QUADLINK	Indicates a quadword queue
SDA_OPT\$M_QUEUE_SELF	Indicates a self-relative queue
SDA_OPT\$M_QUEUE_SINGLINK	Indicates a singly-linked queue

Description

You can use this routine to validate the integrity of doubly-linked, singly-linked or self-relative queues either with longword or quadword links. If you specify the option SDA_OPT\$M_QUEUE_LISTQUEUE, the queue elements are displayed for debugging. Otherwise a one-line summary indicates how many elements were found and whether the queue is intact.

Condition Values Returned

None.

If an error occurs, it is signaled by SDA\$VALIDATE_QUEUE.

Example

```
int64 temp;
int64 *queue;
...
sda$symbol_value ("EXE$GL_NONPAGED", &temp);
temp += 4;
sda$reqmem ((VOID_PQ)temp, &queue, 4);
sda$validate_queue (queue, SDA_OPT$M_QUEUE_SINGLINK);
```

This sequence validates the nonpaged pool free list, and outputs a message of the form:

```
Queue is zero-terminated, total of 204 elements in the queue
```

Part II. OpenVMS System Code Debugger and System Dump Debugger

This part describes the System Code Debugger (SCD) and the System Dump Debugger (SDD). It presents how to use SCD and SDD by doing the following:

- Building a system image to be debugged
- Setting up the target system for connections
- Setting up the host system
- Starting SCD
- Troubleshooting connections and network failures
- Looking at a sample SCD session
- Analyzing memory as recorded in a system dump
- Looking at a sample SDD session

Chapter 11. OpenVMS System Code Debugger

This chapter describes the OpenVMS System Code Debugger (SCD) and how it can be used to debug nonpageable system code and device drivers running at any interrupt priority level (IPL).

You can use SCD to perform the following tasks:

- Control the system software's execution---stop at points of interest, resume execution, intercept fatal exceptions, and so on
- Trace the execution path of the system software
- Monitor exception conditions
- Examine and modify the values of variables
- Test the effect of modifications, in some cases, without having to edit the source code, recompile, and relink

The use of SCD requires two systems:

- The host system, probably also the system where the image to be debugged has been built
- The target system, usually a standalone test system, where the image being debugged is executed
- Host and target systems must be the same architecture, that is, both must be Alpha systems or Integrity server systems.

SCD is a symbolic debugger. You can specify variable names, routine names, and so on, precisely as they appear in your source code. SCD can also display the source code where the software is executing, and allow you to step by source line.

SCD recognizes the syntax, data typing, operators, expressions, scoping rules, and other constructs of a given language. If your code or driver is written in more than one language, you can change the debugging context from one language to another during a debugging session.

To use SCD, you must do the following:

- Build a system image or device driver to be debugged.
- Set up the target kernel on a standalone system.

The **target kernel** is the part of SCD that resides on the system that is being debugged. It is integrated with XDELTA and is part of the SYSTEM_DEBUG execlset.

- Set up the host system environment, which is integrated with the OpenVMS Debugger.

The following sections cover these tasks in more detail, describe the available user-interface options, summarize applicable OpenVMS Debugger commands, and provide a sample SCD session.

11.1. User-Interface Options

SCD has the following user-interface options:

- A DECwindows Motif interface for workstations

When using this interface, you interact with SCD by using a mouse and pointer to choose items from menus, click on buttons, select names in windows, and so on.

Note that you can also use OpenVMS Debugger commands with the DECwindows Motif interface.

- A character cell interface for terminals and workstations

When using this interface, you interact with SCD by entering commands at a prompt. The sections in this chapter describe how to use the system code debugger with the character cell interface.

For more information about using the OpenVMS DECwindows Motif interface and OpenVMS Debugger commands with SCD, see the *VSI OpenVMS Debugger Manual*.

11.2. Building a System Image to Be Debugged

1. Compile the sources you want to debug, and be sure to use the `/DEBUG` and `/NOOPT` qualifiers.

Note

Debugging optimized code is much more difficult and is not recommended unless you know the Alpha or Integrity server architecture well. The instructions are reordered so much that single-stepping by source line will look like you are randomly jumping all over the code. Also note that you cannot access all variables. SCD reports that they are optimized away.

2. Link your image using the `/DSF` (debug symbol file) qualifier. Do not use the `/DEBUG` qualifier, which is for debugging user programs. The `/DSF` qualifier takes an optional filename argument similar to the `/EXE` qualifier. For more information, see the *VSI OpenVMS Linker Utility Manual*. If you specify a name in the `/EXE` qualifier, you will need to specify the same name for the `/DSF` qualifier. For example, you would use the following command:

```
$ LINK/EXE=EXE$ :MY_EXECLET/DSF=EXE$ :MY_EXECLET OPTIONS_FILE/OPT
```

The `.DSF` and `.EXE` file names must be the same. Only the extensions will be different, that is `.DSF` and `.EXE`.

The contents of the `.EXE` file should be exactly the same as if you had linked without the `/DSF` qualifier. The `.DSF` file will contain the image header and all the debug symbol tables for `.EXE` file. It is not an executable file, and cannot be run or loaded.

3. Put the `.EXE` file on your target system.
4. Put the `.DSF` file on your host system, because when you use SCD to debug code in your image, it will try to look for a `.DSF` file first and then look for an `.EXE` file. The `.DSF` file is better because it has symbols in it. Section 11.4 describes how to tell SCD where to find your `.DSF` and `.EXE` files.

11.3. Setting Up the Target System for Connections

The target kernel is controlled by flags and devices specified when the system is booted, by XDELTA commands, by a configuration file, and by several system parameters. The following sections contain more information about these items.

Boot Flags

You can specify flags on the boot command line. Boot flags are specified as a hex number; each bit of the number represents a true or false value for a flag. The following flag values are relevant to the system code debugger.

- **8000**

This is the SCD boot flag. It enables operation of the target kernel. If this SCD boot flag is not set, not only will it be impossible to use SCD to debug the system, but the additional XDELTA commands related to the target kernel will generate an XDELTA error message. If this boot flag is set, SYSTEM_DEBUG is loaded, and SCD is enabled.

- **0004**

This is the initial breakpoint boot flag. It controls whether the system calls INI\$BRK at the beginning and end of EXEC_INIT. Notice that if SCD is the default debugger, the first breakpoint is not as early as it is for XDELTA. It is delayed until immediately after the PFN database is set up.

- **0002**

This is the XDELTA boot flag, which controls whether XDELTA is loaded. It behaves slightly differently when the SCD boot flag is also set.

If the SCD boot flag is clear, this flag simply determines if XDELTA is loaded. If the SCD boot flag is set, this flag determines whether XDELTA or the system code debugger is the default debugger. If the XDELTA flag is set, XDELTA will be the default debugger. In this state, the initial system breakpoints and any calls to INI\$BRK trigger XDELTA, and you must enter an XDELTA command to start using SCD. If the XDELTA boot flag is clear, the initial breakpoints and calls to INI\$BRK go to SCD. You cannot use XDELTA if the XDELTA boot flag is clear.

Boot Command

The form of the boot command varies depending on the platform and type OpenVMS system. However, all SCD boot commands have the concept of boot flags, boot device, and dedicated Ethernet device. In all environments, you must specify an Ethernet device on the target system to use to communicate with the host debugger. It is currently a restriction that this device must not be used for anything else (either for booting or network software such as DECnet, TCP/IP products, and LAT products).

To use Alpha SCD, you must specify the Ethernet device with the boot command. In this example, we are using DEC 3000 Model 400 Alpha Workstation syntax. We are booting from the DKB100 disk and using the ESA0 Ethernet device. We are also setting the SCD, XDELTA, and initial (earliest) breakpoint flags:

```
>>> show device
```

```
.
```

```
.
.
>>> boot dkb100,esa0 -fl 0,8006
```

You can set these devices and flags to be the default values so that you will not have to specify them each time you boot:

```
>>> set bootdef_dev dkb100,esa0
>>> set boot_osflags 0,8006
```

To use Integrity server SCD, you can specify an Ethernet device (`debug_dev`) BEFORE loading the Operating System and AFTER you have selected the device/partition. Setting `debug_dev` is sticky. That is, you only need to set it once. Using a VSI rx2600 syntax:

A sample Integrity server Boot Menu follows.

```

Please select a boot option

EFI Shell [Built-in]
PESOS - X8.2-AHI (Topaz BL2) on $1$DGA3890:[SYS2.]
PESOS - X8.2-AHI (Topaz BL2) on $1$DGA3890:[SYS2.] sysboot
PESOS - E8.2-ADH (Topaz BL1) on $1$DGA3891:[SYS2.]
PESOS - E8.2-ADH (Topaz BL1) on $1$DGA3891:[SYS2.] sysboot
Boot Option Maintenance Menu
System Configuration Menu
```

Select the EFI Shell [Built-in].

```

Loading.: EFI Shell [Built-in]
EFI Shell version 1.10 [14.61]
Device mapping table

fs0 : Acpi (HWP0002,100)/Pci (1|0)/Scsi (Pun0,Lun0) /
HD (Part1,SigA02952
fs1 : Acpi (HWP0002,300)/Pci (1|0) /
Fibre (WWN50001FE10011B15D,Lun2200)
fs2 : Acpi (HWP0002,300)/Pci (1|0) /
Fibre (WWN50001FE10011B15D,Lun2200)
fs3 : Acpi (HWP0002,300)/Pci (1|0) /
Fibre (WWN50001FE10011B15D,Lun2300)
.
.
.

Shell>
```

Select the desired device/partition:

```
Shell> fs1:
fs1:\>
```

Use the utilities in `\efi\vms`. Use `vms_show` to list the devices and `vms_set` to set Ethernet device (`debug_dev`), if necessary.

```
fs1:\> \efi\vms\vms_show device
VMS: EIA0
EFI: Acpi (000222F0,0)/Pci (3|0)/Mac (00306E39F77B)
```

```
VMS: DKB200
EFI: fs1: Acpi(000222F0,100)/Pci(1|1)/Scsi(Pun2,Lun0)

VMS: DKB0
EFI: fs0: Acpi(000222F0,100)/Pci(1|1)/Scsi(Pun0,Lun0)

VMS: EWA0
EFI: Acpi(000222F0,100)/Pci(2|0)/Mac(00306E3977C5)
.
.
.
```

Set the Ethernet device.

```
fs1:\> \efi\vms\vms_set debug_dev eia0
VMS: EIA0 0-30-6E-39-F7-CF
EFI: Acpi(000222F0,0)/Pci(3|0)/Mac(00306E39F7CF)
```

Finally, load the OS. In this example, the boot is with the SCD and initial (earliest) breakpoint flags using root 2 (SYS2), that will vary with system setups.

```
fs1:\> \efi\vms\vms_loader -flags "2,8004"
```

You can set the flags to be the default value instead of specifying them for each and every OS load:

```
fs1:\> set vms_flags "2,8004"
```

You can also build the entire boot device, OS load command with flags setting as a Boot Option. See the "Boot Option Maintenance Menu", described in the *VSI OpenVMS System Manager's Manual, Volume 1: Essentials*.

SCD Configuration File

The SCD target system reads a configuration file in SYSS\$SYSTEM named DBGTK\$CONFIG.SYS. The first line of this file contains a default password, which must be specified by the host debug system to connect to the target. The default password may be the null string; in this case the host must supply the null string as the password (/PASSWORD="") on the connect command as described in Section 11.5, or no password at all. Other lines in this file are reserved by VSI. Note that you must create this file because VSI does not supply it. If this file does not exist prior to booting with SCD enabled, you can only run SCD by specifying a default password with the XDELTA ;R command described in the following section.

XDELTA Commands

When the system is booted with both the XDELTA boot flag and the SCD boot flag, the following two additional XDELTA commands are enabled:

- n\xxxx\;R ContRol SCD connection

You can use this command to do the following:

- Change the password which the SCD host must present
- Disconnect the current session from SCD
- Give control to SCD by simulating a call to INI\$BRK

- Any combination of these

Optional string argument `xxxx` specifies the password that the system code debugger must present for its connection to be accepted. If this argument is left out, the required password is unchanged. The initial password is taken from the first line of the `SYSS$SYSTEM:DBGTK$CONFIG.SYS` file. The new password does not remain in effect across a boot of the target system.

The optional integer argument `n` controls the behavior of the `;R` command as follows:

Value of N	Action
+1	Gives control to SCD by simulating a call to <code>INI\$BRK</code>
+2	Returns to XDELTA after changing the password. <code>2;R</code> without a password is a no-op
0	Performs the default action
-1	Changes the password, breaks any existing connection to SCD, and then simulates a call to <code>INI\$BRK</code> (which will wait for a new connection to be established and then give control to SCD)
-2	Returns to XDELTA after changing the password and breaking an existing connection

Currently, the default action is the same action as +1.

If SCD is already connected, the `;R` command transfers control to SCD, and optionally changes the password that must be presented the next time a system code debugger tries to make a connection. This new password does not last across a boot of the target system.

- `n;K` Change `inibrK` behavior

If optional argument `n` is 1, future calls to `INI$BRK` will result in a breakpoint being taken by SCD. If the argument is 0, or no argument is specified, future calls to `INI$BRK` will result in a breakpoint being taken by XDELTA.

SYSTEM Parameters

- **BREAKPOINTS**

This parameter is a bitmask, enabling existing `INI$BRK` calls within OpenVMS in the following situations:

Bit 0	At the start of INIT
Bit 1	At the end of INIT
Bit 2	At the point in INIT just prior to starting secondary CPUs
Bit 3	If <code>INI\$BRK</code> is called from an outer mode
Bit 4	Before calling the initialization routine of a newly-loaded executive image
Bits 5-31	Reserved by VSI

Notes on the use of BREAKPOINTS parameter:

1. Calling INI\$BRK from executive mode when bit 3 of BREAKPOINTS is not set will result in process exit, or a SSRVEXCEPT bugcheck (if SYSTEM_CHECK or BUGCHECKFATAL is also set).
2. Changing BREAKPOINTS from its default value of 3 may allow the security of the system to be compromised, and should only be used with caution.

- **DBGTK_SCRATCH**

Bits 0 through 7 specify how many pages of memory are allocated for SCD. This memory is allocated only if system code debugging is enabled with the SCD boot flag (described earlier in this section). Usually, the default value of 1 is adequate; however, if SCD displays an error message, increase this value.

Bits 8 through 31 are reserved by VSI.

- **SCSNODE**

Identifies the target kernel node name for SCD. See Section 11.3.1 for more information.

- **S0_PAGING**

If the image you are debugging includes pageable code or data, set S0_PAGING to 3 to ensure that such code and data are always resident in memory. SCD cannot examine, deposit to, set breakpoints at, and so on, any locations in pageable sections that are not currently valid. [This applies only to Alpha. Integrity server executive images and drivers do not contain pageable code or data.]

- **POOLPAGING**

If the image you are debugging uses paged pool, set POOLPAGING to zero to ensure that paged pool is always resident in memory. SCD cannot examine or deposit to any locations in paged pool that are not currently valid.

- **TIME_CONTROL** This parameter is a bitmask, disabling certain time control functions within VMS:

Bit 0	Disables system clock
Bit 1	Disables CPU sanity timeouts
Bit 2	Disables CPU spinwait timeouts

When XDELTA or SCD is loaded (bit 1 or bit 15 of boot flags is set), the value of TIME_CONTROL is changed from its default of zero to 6 (disable CPU sanity and CPU spinwait timeouts). This is to prevent these timeouts from occurring when the system is waiting at a breakpoint. If necessary, these settings can be altered, using the SYSGEN utility or a Deposit command within XDELTA or SCD. Bit 0 should never be set.

11.3.1. Making Connections Between the Target Kernel and the System Code Debugger

It is always SCD on the host system that initiates a connection to the target kernel. When SCD initiates this connection, the target kernel accepts or rejects the connection based on whether the remote debugger

presents it with a node name and password that matches the password in the target system (either the default password from the SYS\$SYSTEM:DBGTK\$CONFIG.SYS file, or a different password specified via XDELTA). SCD obtains the node name from the SCSNODE system parameter.

The target kernel can accept a connection from SCD any time the system is running below IPL 22, or if XDELTA is in control (at IPL 31). However, the target kernel actually waits at IPL 31 for a connection from the SCD host in two cases: when it has no existing connection to an SCD host and (1) it receives a breakpoint caused by a call to INI\$BRK (including either of the initial breakpoints), or (2) when you enter a 1;R or -1;R command to XDELTA.

11.3.2. Interactions Between XDELTA and the Target Kernel/System Code Debugger

XDELTA and the target kernel are integrated into the same system. Normally, you choose to use one or the other. However, XDELTA and the target kernel can be used together. This section explains how they interoperate.

The XDELTA boot flag controls which debugger (XDELTA or the SCD target kernel) gets control first. If it is not set, the target kernel gets control first, and it is not possible to use XDELTA without rebooting. If it is set, XDELTA gets control first, but you can use XDELTA commands to switch to the target kernel and to switch INI\$BRK behavior such that the target kernel gets control when INI\$BRK is called.

Breakpoints always *stick* to the debugger that set them; for example, if you set a breakpoint at location "A" with XDELTA, and then you enter the commands 1;K (switch INI\$BRK to the system code debugger) and ;R (start using the system code debugger) then, from SCD, you can set a breakpoint at location "B". If the system executes the breakpoint at A, XDELTA reports a breakpoint, and SCD will see nothing (though you could switch to SCD by issuing the XDELTA ;R command). If the system executes the breakpoint at B, SCD will get control and report a breakpoint (you cannot switch to XDELTA from SCD).

Notice that if you examine location A with SCD, or location B with XDELTA, you will see a BPT instruction, not the instruction that was originally there. This is because neither debugger has any information about the breakpoints set by the other debugger.

One useful way to use both debuggers together is when you have a system that exhibits a failure only after hours or days of heavy use. In this case, you can boot the system with SCD enabled (8000), but with XDELTA the default (0002) and with initial breakpoints enabled (0004). When you reach the initial breakpoint, set an XDELTA breakpoint at a location that will only be reached when the error occurs. Then proceed. When the error breakpoint is reached, possibly days later, then you can set up a remote system to debug it and enter the ;R command to XDELTA to switch control to SCD.

Here is another technique to use on Alpha when you do not know where to put an error breakpoint as previously mentioned. Boot the system with only the SCD boot flag set. When you see that the error has occurred, halt the system and initiate an IPL 14 interrupt, as you would to start XDELTA. The target kernel will get control and wait for a connection for SCD.

The equivalent technique on Integrity servers is as follows:

Boot the system with only the SCD flag set (bit 15). When you see that the error has occurred, type Ctrl/P at the console. This will give control to XDELTA (even though the XDELTA boot flag is not set) and you can now type 1;R. The target kernel will get control and wait for a connection for SCD.

11.3.3. Interactions between the Target Kernel, the System Code Debugger, and other system components

The target kernel must have exclusive use of its Ethernet device. Some system components, such as DECnet, will not start if the System Code Debugger is loaded. If there are multiple Ethernet devices, and the system is configured to give exclusive access of the SCD Ethernet device to the target kernel, the logical name `DBGTK$OVERRIDE` must be defined, indicating that the affected system components should start up as normal. The logical name can either be defined systemwide, or in the process where the startup command for the system component will be executed.

11.4. Setting Up the Host System

To set up the host system, you need access to all system images and drivers that are loaded (or can be loaded) on the target system. You should have access to a source listings kit or a copy of the following directories:

```
SYS$LOADABLE_IMAGES:
SYS$LIBRARY:
SYS$MESSAGE:
```

You need all the .EXE files in those directories. The .DSF files are available with the OpenVMS source listings kit.

Optionally, you need access to the source files for the images to be debugged. SCD will look for the source files in the directory where they were compiled. If your build system and host system are different, you must use the `SET SOURCE` command to point SCD to the location of the source code files. For an example of the `SET SOURCE` command, see Section 11.12.

Before making a connection to the target system, you must set up the logical name `DBGHK$IMAGE_PATH`, which must be set up as a search list to the area where the system images or .DSF files are kept. For example, if the copies are in the following directories:

```
DEVICE: [SYS$LDR]
DEVICE: [SYSLIB]
DEVICE: [SYSMSG]
```

you would define `DBGHK$IMAGE_PATH` as follows:

```
$ define dbghk$image_path DEVICE:[SYS$LDR],DEVICE:[SYSLIB],DEVICE:[SYSMSG]
```

This works well for debugging using all the images normally loaded on a given system. However, you might be using the debugger to test new code in an `execlet` or a new driver. Because that image is most likely in your default directory, you must define the logical name as follows:

```
$ define dbghk$image_path [],DEVICE:[SYS$LDR],DEVICE:[SYSLIB],DEVICE:
[SYSMSG]
```

If SCD cannot find one of the images through this search path, a warning message is displayed. SCD will continue initialization as long as it finds at least two images. If SCD cannot find the `SYS$BASE_IMAGE` and `SYS$PUBLIC_VECTORS` files, which are the OpenVMS operating system's main image files, an error message is displayed and the debugger exits.

If and when this happens, check the directory for the image files and compare it to what is loaded on the target system.

11.5. Starting the System Code Debugger

To start SCD on the host side, enter the following command:

```
$ DEBUG/KEEP
```

SCD displays the `DBG>` prompt. With the `DBGHK$IMAGE_PATH` logical name defined, you can invoke the `CONNECT` command and the optional qualifiers `/PASSWORD` and `/IMAGE_PATH`.

To use the `CONNECT` command and the optional qualifiers (`/PASSWORD` and `/IMAGE_PATH`) to connect to the node with name *nodename*, enter the following command:

```
DBG> CONNECT %NODE_NAME nodename /PASSWORD="password"
```

If a password has been set up on the target system, you must use the `/PASSWORD` qualifier. If a password is not specified, a zero length string is passed to the target system as the password.

The `/IMAGE_PATH` qualifier is also optional. If you do not use this qualifier, SCD uses the `DBGHK$IMAGE_PATH` logical name as the default. The `/IMAGE_PATH` qualifier is a quick way to change the logical name. However, when you use it, you cannot specify a search list. You can use only a logical name or a device and directory, although the logical name can be a search list.

Usually, SCD obtains the source file name from the object file. This is put there by the compiler when the source is compiled with the `/DEBUG` qualifier. The `SET SOURCE` command can take a list of paths as a parameter. It treats them as a search list.

11.6. Summary of System Code Debugger Commands

In general, any OpenVMS debugger command can be used in SCD. For a complete list, refer to the *VSI OpenVMS Debugger Manual*. The following are a few examples:

- Commands to manipulate the source display, such as `TYPE` and `SCROLL`.
- Commands used in OpenVMS debugger command programs, such as `DO` and `IF`.
- Commands that affect output formats, such as `SET RADIX`.
- Commands that manipulate symbols and scope, such as `EVALUATE`, `SET LANGUAGE`, and `CANCEL SCOPE`. Note that the debugger `SHOW IMAGE` command is equivalent to the `XDELTA ;L` command, and the debugger `DEFINE` command is equivalent to the `XDELTA ;X` command.
- Commands that cause code to be executed, such as `STEP` and `GO`. Note that the debugger `STEP` command is equivalent to the `XDELTA S` and `O` commands, and the debugger `GO` command is equivalent to the `XDELTA ;P` and `;G` commands.
- Commands that manipulate breakpoints, such as `SET BREAK` and `CANCEL BREAK`. These commands are equivalent to the `XDELTA ;B` command. However, unlike `XDELTA`, there is no limit on the number of breakpoints in SCD.
- Commands that affect memory, such as `DEPOSIT` and `EXAMINE`. These commands are equivalent to the `XDELTA /,!,[,','` commands.

You can also use the OpenVMS debugger command SDA to examine the target system with System Dump Analyzer semantics. This command, which is not available when debugging user programs, is described in the next section.

11.7. Using System Dump Analyzer Commands

Once a connection has been established to the target system, you can use the commands listed in the previous section to examine the target system. You can also use some System Dump Analyzer (SDA) commands, such as `SHOW SUMMARY` and `SHOW DEVICE`. This feature allows the system programmer to take advantage of the strengths of both the OpenVMS Debugger and SDA to examine the state of the target system and to debug system programs such as device drivers.

To obtain access to SDA commands, you simply type "SDA" at the OpenVMS Debugger prompt ("DBG>") at any time after a connection has been established to the target system. SDA initializes itself and then outputs the "SDA>" prompt. Enter SDA commands as required. (See Chapter 4 for more information.) To return to the OpenVMS Debugger, you enter "EXIT" at the "SDA>" prompt. Optionally, you may invoke SDA to perform a single command and then return immediately to the OpenVMS Debugger, as in the following example:

```
DBG>SDA SHOW SUMMARY
```

You may reenter SDA at any time, with or without the optional SDA command. Once SDA has been initialized, the SDA> prompt is output more quickly on subsequent occasions.

Note that there are some limitations on the use of SDA from within SCD.

- You cannot switch between processes, whether requested explicitly (`SET PROCESS <name>`) or implicitly (`SHOW PROCESS <name>`). The exception to this is that access to the system process is possible.
- You cannot switch between CPUs.
- SDA has no knowledge of the OpenVMS debugger's Motif or Windows interfaces. Therefore, all SDA input and output occurs at the terminal or window where the OpenVMS debugger was originally invoked. Also, while using SDA, the OpenVMS debugger window is not refreshed; you must exit SDA to allow the OpenVMS debugger window to be refreshed.
- When you invoke SDA from SCD with an immediate command, and that command produces a full screen of output, SDA displays the message "Press RETURN for more." followed by the "SDA>" prompt before continuing. If you enter another SDA command at this prompt, SDA does not automatically return to SCD upon completion. To do this, you must enter an EXIT command.

11.8. System Code Debugger Network Information

The SCD host and the target kernel use a private Ethernet protocol to communicate. The best way to ensure that the two systems can see each other is for them both to be on the same Ethernet segment. Otherwise, your network and its bridges must be set up to pass through the packets with the protocol 08-00-2B-80-4B and multicast address 09-00-2B-02-01-0F.

The network portion of the target system uses the specified Ethernet device and communicates through it. The network portion of the host system finds the first Ethernet device and communicates through it. If the host SCD picks the wrong device for your needs, then you can force it to use the correct device by defining the logical `DBGHK$ADAPTOR` as the template device name for the appropriate adaptor.

11.9. Troubleshooting Checklist

If you have trouble starting a connection, perform the following tasks to correct the problem:

- Check `SCSNODE` on the target system.
It must match the name you are using in the host `CONNECT` command.
- Make sure that both the Ethernet and boot device have been specified correctly.
- Make sure that the host system is using the correct Ethernet device, and that the host and target systems are connected to the same Ethernet segment.
- Check the version of the operating system and make sure that both the host and target systems are running the same version of the OpenVMS operating system.

11.10. Troubleshooting Network Failures

There are three possible network errors:

- `NETRETRY`
Indicates the system code debugger connection is lost
- `SENDRETRY`
Indicates a message send failure
- `NETFAIL`
Results from the two previous errors

The netfail error message has a status code that can be one of the following values:

Value	Status
2, 4, 6	Internal network error, submit a problem report to VSI.
8,10,14,16,18,20,26,28,34,38	Network protocol error, submit a problem report to VSI.
22,24	Too many errors on the network device most likely due to congestion. Reduce the network traffic or switch to another network backbone.
30	Target system scratch memory not available. Check <code>DBGTK_SCRATCH</code> . If increasing this value does not help, submit a problem report to VSI.

Value	Status
32	Ran out of target system scratch memory. Increase value of DBGTK_SCRATCH.
All others	There should not be any other network error codes printed. If one occurs that does not match the previous ones, submit a problem report to VSI.

11.11. Access to Symbols in OpenVMS Executive Images


Accessing OpenVMS executive images' symbols is not always straightforward with SCD. Only a subset of the symbols may be accessible at one time and in some cases, the symbol value the debugger currently has may be stale. To understand these problems and their solutions, you must understand how the debugger maintains its symbol tables and what symbols exist in the OpenVMS executive images. The following sections briefly summarize these topics.

11.11.1. Overview of How the OpenVMS Debugger Maintains Symbols

The debugger can access symbols from any image in the OpenVMS loaded system image list by reading in either the .DSF or .EXE file for that particular image. The .EXE file contains information only about symbols that are part of the symbol vector for that image. The current image symbols for any set module are defined. (You can tell if you have the .DSF or .EXE file by doing a SHOW MODULE. If there are no modules, you have the .EXE file.) This includes any symbols in the SYS\$BASE_IMAGE.EXE symbol vector for which the code or data resides in the current image. However, you cannot access a symbol that is part of the SYS\$BASE_IMAGE.EXE symbol vector that resides in another image.

In general, at any one point in time, the debugger can access only the symbols from one image. It does this to reduce the time it takes to search for a symbol in a table. To load the symbols for a particular image, use the SET IMAGE command. When you set an image, the debugger loads all the symbols from the new image and makes that image the current image. The symbols from the previous image are in memory, but the debugger will not look through them to translate symbols.

There is a set of modules for each image the debugger accesses. The symbol tables in the image that are part of these modules are not loaded with the SET IMAGE command. Instead they can be loaded with the SET MODULE <module-name> or SET MODULE/ALL commands. As they are loaded, a new symbol table is created in memory under the symbol table for the image. The figure below shows what this looks like.



When the debugger needs to look up a symbol name, it first looks at the current image to find the information. If it does not find it there, it then looks into the appropriate module. It determines which module is appropriate by looking at the module range symbols which are part of the image symbol table.

To see the symbols that are currently loaded, use the debugger's `SHOW SYMBOL` command. This command has a few options to obtain more than just the symbol name and value. (See the *VSI OpenVMS Debugger Manual* for more details.)

11.11.2. Overview of OpenVMS Executive Image Symbols

Depending on whether the debugger has access to the `.DSF` or `.EXE` file, different kinds of symbols could be loaded. Most users will have the `.EXE` file for the OpenVMS executive images and a `.DSF` file for their private images---that is, the images they are debugging.

The OpenVMS executive consists of two base images, `SYSS$BASE_IMAGE.EXE` and `SYSS$PUBLIC_VECTORS.EXE`, and a number of separately loadable executive images.

The two base images contain symbol vectors. For `SYSS$BASE_IMAGE.EXE`, the symbol vector is used to define symbols accessible by all the separately loadable images. This allows these images to communicate with each other through cross-image routine calls and memory references. For `SYSS$PUBLIC_VECTORS.EXE`, the symbol vector is used to define the OpenVMS system services. Because these symbol vectors are in the `.EXE` and the `.DSF` files, the debugger can load these symbols no matter which one you have.

All images in the OpenVMS executive also contain global and local symbols. However, none of these symbols ever gets into the `.EXE` file for the image. These symbols are put in the specific module's section of the `.DSF` file if that module was compiled using `/DEBUG` and the image was linked using `/DSF`.

11.11.3. Possible Problems You May Encounter

Access to All Executive Image Symbols

When the current image is not `SYSS$BASE_IMAGE`, but one of the separately loaded images, the debugger does not have access to any of the symbols in the `SYSS$BASE_IMAGE` symbol vector. This means you cannot access (set breakpoints, and so on) any of the cross-image routines or data cells. The only symbols you have access to are the ones defined by the current image.

If the debugger has access only to the `.EXE` file, then only symbols that have vectors in the base image are accessible. For `.DSF` files, the current image symbols for any set module are defined. (You can tell if you have the `.DSF` or `.EXE` by using the `SHOW MODULE` command---if there are no modules you have the `.EXE`). This includes any symbols in the `SYSS$BASE_IMAGE.EXE` symbol vector for which the code or data resides in the current image. However, the user cannot access a symbol that is part of the `SYSS$BASE_IMAGE.EXE` symbol vector that resides in another image. For example, if you are in one image and you want to set a breakpoint in a cross-image routine from another image, you do not have access to the symbol. Of course, if you know in which image it is defined, you can do a `SET IMAGE`, `SET MODULE/ALL`, and then a `SET BREAK`.

There is a debugger workaround for this problem. The debugger and SCD let you use the `SET MODULE` command on an image by prefixing the image name with `SHARE$` (`SHARE$$SYSS$BASE_IMAGE`, for example). This treats that image as a module which is part of the current image. In the previous figure, think of it as another module in the module list for an image. Note, however, that

only the symbols for the symbol vector are loaded. None of the symbols for the modules of the SHARE \$xxx image are loaded. Therefore, this command is only useful for base images.

So, in other words, by doing SET MODULE SHARE\$SY\$BASE_IMAGE, the debugger gives you access to all cross-image symbols for the OpenVMS executive.

11.12. Sample System Code Debugging Session

This section provides a sample session that shows the use of some OpenVMS debugger commands as they apply to SCD. The examples in this session show how to work with C code that has been linked into the SYSTEM_DEBUG execlt. It is called as an initialization routine for SYSTEM_DEBUG.

To reproduce this sample session, the host system needs access to the SYSTEM_DEBUG.DSF matching the SYSTEM_DEBUG.EXE file on your target system, and to the source file C_TEST_ROUTINES.C, which is available in SYS\$EXAMPLES. The target system is booted with the boot flags 0, 8004, so it stops at an initial breakpoint. The system disk is DKB200, and the network device is ESA0 in the Alpha examples and EIA0 in the Integrity server examples.

Note that the example displays from Example 11-5 onwards are all taken from an OpenVMS Integrity server system. On an OpenVMS Alpha system, some of the output is different, but the commands entered are the same on both platforms, except in one case, as noted in the accompanying text.

Example 11.1. Booting an Alpha Target System

```
>>> b -f1 0,8004 dkb200,esa0
INIT-S-CPU...
INIT-S-RESET_TC...
INIT-S-ASIC...
INIT-S-MEM...
INIT-S-NVR...
INIT-S-SCC...
INIT-S-NI...
INIT-S-SCSI...
INIT-S-ISDN...
INIT-S-TC0...
AUDIT_BOOT_STARTS ...
AUDIT_CHECKSUM_GOOD
AUDIT_LOAD_BEGINS
AUDIT_LOAD_DONE
```

```
%SYSBOOT-I-GCTFIL, Using a configuration file to boot as a Galaxy instance.
```

```
OpenVMS (TM) Alpha Operating System, Version V8.3
© Copyright 1976-2006 Hewlett-Packard Development Company, L.P.
```

```
DBGTK: Initialization succeeded. Remote system debugging is now possible.
```

```
DBGTK: Waiting at breakpoint for connection from remote host.
```

A sample Integrity server Boot Menu follows (long lines wrapped for clarity).

Example 11.2. Booting an Integrity server Target System

```
Please select a boot option
```

```

EFI Shell [Built-in]
PESOS - X8.2-AHI (Topaz BL2) on $1$DGA3890:[SYS2.]
PESOS - X8.2-AHI (Topaz BL2) on $1$DGA3890:[SYS2.] sysboot
PESOS - E8.2-ADH (Topaz BL1) on $1$DGA3891:[SYS2.]
PESOS - E8.2-ADH (Topaz BL1) on $1$DGA3891:[SYS2.] sysboot
Boot Option Maintenance Menu
System Configuration Menu

```

Select the "EFI Shell [Built-in]"

```

Loading.: EFI Shell [Built-in]
EFI Shell version 1.10 [14.61]
Device mapping table

fs0   : Acpi (HWP0002,100) /Pci (1|1) /Scsi (Pun0,Lun0) /HD (Part2,
        SigB3A4A931-1F2A-11D8-9EA1-AA000400FEFF)
fs1   : Acpi (HWP0002,100) /Pci (1|1) /Scsi (Pun2,Lun0) /HD (Part1,
        SigF7B864C3)
fs2   : Acpi (HWP0002,300) /Pci (1|0) /Fibre (WWN50001FE10011B15D,
        Lun2200) /HD (Part1, Sig51C7BEE1-070B-11D9-8099-AA000400FEFF)
fs3   : Acpi (HWP0002,300) /Pci (1|0) /Fibre (WWN50001FE10011B15D,
        Lun2200) /HD (Part4, Sig51C7BEE0-070B-11D9-809A-AA000400FEFF)
.
.
.

```

Shell>

Select the desired device/partion:

```

Shell> fs1:
fs1:\>

```

Use the utilities in `\efi\vms`. Use `vms_show` to list the devices and `vms_set` to set Ethernet device (`debug_dev`), if necessary. Note that this set is sticky so it only needs to be done once. Then load the operating system with the desired flags. Note that Alpha and Integrity servers use the same flags with the same meanings.

```

fs1:\> dir \efi\vms
Directory of: fs1:\efi\vms

09/13/04  10:13a <DIR>          2,048  .
09/13/04  10:13a <DIR>          2,048  ..
09/13/04  10:13a <DIR>          2,048  tools
09/13/04  10:13a                3,101,184  ipb.exe
09/13/04  10:13a <DIR>          2,048  update
09/13/04  10:13a                846,336  vms_loader.efi
09/13/04  10:13a                244,224  vms_bcfg.efi
09/13/04  10:13a                218,112  vms_set.efi
09/13/04  10:13a                215,040  vms_show.efi
          5 File(s)    4,624,896 bytes
          4 Dir(s)

fs1:\> \efi\vms\vms_show device
VMS: EIA0
EFI: Acpi (000222F0,0) /Pci (3|0) /Mac (00306E39F77B)

```

```

VMS: DKB200
EFI: fs1: Acpi (000222F0,100) /Pci (1|1) /Scsi (Pun2, Lun0)

VMS: DKB0
EFI: fs0: Acpi (000222F0,100) /Pci (1|1) /Scsi (Pun0, Lun0)

VMS: EWA0
EFI: Acpi (000222F0,100) /Pci (2|0) /Mac (00306E3977C5)
.
.
.

```

Set the `debug_dev` to one of the connected Ethernet devices:

```

fs1:\> \efi\vms\vms_set debug_dev eia0
VMS: EIA0 0-30-6E-39-F7-CF
EFI: Acpi (000222F0,0) /Pci (3|0) /Mac (00306E39F7CF)
fs1:\> \efi\vms\vms_show debug_dev
VMS: EIA0 0-30-6E-39-F7-CF
EFI: Acpi (000222F0,0) /Pci (3|0) /Mac (00306E39F7CF)

```

Boot up the OS. In this example, the boot is with the SCD and initial (early) breakpoint flags, using root 2 (SYS2), that will vary with system setups:

```

fs1:\> \efi\vms\vms_loader -flags "2,8004"

      HP OpenVMS Industry Standard 64 Operating System, V8.3
      © Copyright 1976-2006 Hewlett-Packard Development Company, L.P.

%EIA-I-BOOTDRIVER, Starting auto-negotiation
%EIA-I-BOOTDRIVER, Auto-negotiation selected 100BaseTX FDX

DBGTK: Initialization succeeded. Remote system debugging is now
possible.

DBGTK: Waiting at breakpoint for connection from remote host.

```

Example 11.3. Invoking the Alpha System Code Debugger

```

$ define dbg$decw$display " "
$ debug/keep

      OpenVMS Alpha Debug64 Version V8.3-003

DBG>

```

Example 11.4. Invoking the Integrity server System Code Debugger

```

$ define dbg$decw$display " "
$ debug/keep

      OpenVMS I64 Debug64 Version V8.3-003

```

DBG>

Use the `CONNECT` command to connect to the target system. In this example, the target system's default password is the null string, and the logical name `DBGHK$IMAGE_PATH` is used for the image path; so the command qualifiers `/PASSWORD` and `/IMAGE_PATH` are not being used. You may need to use them.

When you have connected to the target system, the `DBG>` prompt is displayed. Enter the `SHOW IMAGE` command to see what has been loaded. Because you are reaching a breakpoint early in the boot process, there are very few images. See the example below. Notice that `SYS$BASE_IMAGE` has an asterisk next to it. This is the currently set image, and all symbols currently loaded in the debugger come from that image.

Example 11.5. Connecting to the Target System

```
DBG> connect %node_name TSTSYS
%DEBUG-I-INIBRK, target system interrupted
DBG> show image
image name                set    base address            end address

ERRORLOG                  no     0000000000000000
FFFFFFFFFFFFFFFF
EXEC_INIT                 no     0000000000000000
FFFFFFFFFFFFFFFF
SYS$ACPI                  no     0000000000000000
FFFFFFFFFFFFFFFF
*SYS$BASE_IMAGE          yes    0000000000000000
FFFFFFFFFFFFFFFF
SYS$DKBTDRIVER           no     0000000000000000
FFFFFFFFFFFFFFFF
SYS$DKBTDRIVER           no     0000000000000000
FFFFFFFFFFFFFFFF
SYS$DKBTDRIVER           no     0000000000000000
FFFFFFFFFFFFFFFF
SYS$DKBTDRIVER           no     0000000000000000
FFFFFFFFFFFFFFFF
SYS$EGBTDRIVER           no     0000000000000000
FFFFFFFFFFFFFFFF
SYS$OPDRIVER             no     0000000000000000
FFFFFFFFFFFFFFFF
SYS$PKMBTDRIVER          no     0000000000000000
FFFFFFFFFFFFFFFF
SYS$PKMBTDRIVER          no     0000000000000000
FFFFFFFFFFFFFFFF
SYS$PKMBTDRIVER          no     0000000000000000
FFFFFFFFFFFFFFFF
SYS$PLATFORM_SUPPORT    no     0000000000000000
FFFFFFFFFFFFFFFF
SYS$PUBLIC_VECTORS       no     0000000000000000
FFFFFFFFFFFFFFFF
SYS$SRBTDRIVER           no     0000000000000000
FFFFFFFFFFFFFFFF
SYSTEM_DEBUG             no     0000000000000000
FFFFFFFFFFFFFFFF
SYSTEM_PRIMITIVES        no     0000000000000000
FFFFFFFFFFFFFFFF
SYSTEM_SYNCHRONIZATION  no     0000000000000000
FFFFFFFFFFFFFFFF
```

```
total images: 18
DBG>
```

The example below shows the target system's console display during the connect sequence. Note that for security reasons, the name of the host system, the user's name, and process ID are displayed.

Example 11.6. Target System Connection Display

```
DBGTK: Connection attempt from host HSTSYS user GUEST process
2E801C2F
DBGTK: Connection attempt succeeded
```

To set a breakpoint at the first routine in the C_TEST_ROUTINES module of the SYSTEM_DEBUG.EXE execut, do the following:

1. Load the symbols for the SYSTEM_DEBUG image with the DEBUG SET IMAGE command.
2. Use the SET MODULE command to obtain the symbols for the module.
3. Set the language to be C and set a breakpoint at the routine test_c_code.

The language must be set because C is case sensitive and test_c_code needs to be specified in lowercase. The language is normally set to the language of the main image, in this example SYS \$BASE_IMAGE.EXE. Currently that is not C.

Example 11.7. Setting a Breakpoint

```
DBG> set image system_debug
%DEBUG-I-DYNLNGSET, setting language IMACRO
DBG> show module
module name                symbols  language  size
AUX_TARGET                 no      C          0
BUFSRV_TARGET              no      C          0
BUGCHECK_CODES             no      BLISS     0
C_TEST_ROUTINES            no      C          0
LIB$$UNWIND_WEAK           no      BLISS     0
LIB$EF                     no      IMACRO    0
LIB$MALLOC                 no      C          0
LIB$MALLOC_64              no      C          0
LINMGR_TARGET              no      C          0
OBJMGR                     no      C          0
PLUMGR                     no      C          0
POOL                       no      C          0
PROTOMGR_TARGET            no      C          0
SOCMGR                     no      C          0
SYS$DOINIT                 yes     IMACRO    122526
TMRMGR_TARGET              no      C          0
```

```
total modules: 16
```

```
DBG> set module c_test_routines
DBG> show module c_test_routines
module name                symbols  size
C_TEST_ROUTINES            yes     5672
```

```
total C modules: 1
```

```
DBG> set language c
DBG> show symbol test_c_code*
routine C_TEST_ROUTINES\test_c_code
routine C_TEST_ROUTINES\test_c_code2
routine C_TEST_ROUTINES\test_c_code3
routine C_TEST_ROUTINES\test_c_code4
routine C_TEST_ROUTINES\test_c_code5
DBG> set break test_c_code
```

Now that the breakpoint is set, you can proceed and activate the breakpoint. When that occurs, the debugger tries to open the source code for that location in the same place as where the module was compiled. Because that is not the same place as on your system, you need to tell the debugger where to find the source code. This is done with the debugger's SET SOURCE command, which takes a search list as a parameter so you can make it point to many places.

Example 11.8. Finding the Source Code

```
DBG> set source/latest sys$examples,sys$library
DBG> go
break at routine C_TEST_ROUTINES\test_c_code
  113:      x = c_test_array[0];
```

Now that the debugger has access to the source, you can put the debugger into screen mode to see exactly where you are and the code surrounding it.

Example 11.9. Using the Set Mode Screen Command

```
DBG> Set Mode Screen; Set Step Nosource

- SRC: module C_TEST_ROUTINES -scroll-
source-----
  98:      c_test_array[5] = in64;
  99:      c_test_array[6] = in32;
100:      if (c_test_array[9] > 0)
101:          *pVar = (*pVar + c_test_array[17]) & c_test_array[9];
102:      else
103:          *pVar = (*pVar + c_test_array[17]);
104:      c_test_array[7] = test_c_code3(10);
105:      c_test_array[3] = test;
106:      return c_test_array[23];
107: }
108: void test_c_code(void)
109: {
110:     int x,y;
111:     __int64 x64,y64;
112:
-> 113:     x = c_test_array[0];
    114:     y = c_test_array[1];
    115:     x64 = c_test_array[2];
    116:     y64 = c_test_array[3];
    117:     c_test_array[14] = test_c_code2(x64+y64,x+y,x64+x,&y64);
    118:     test_c_code4();
    119:     return;
    120: }
- OUT -
output-----
```

```
- PROMPT -error-program-
```

```
prompt-----
```

```
DBG>
```

Now, you want to set another breakpoint inside the `test_c_code3` routine. You use the debugger's `SCROLL/UP` command (8 on the keypad) to move to that routine and see that line 93 would be a good place to set the breakpoint. It is at a recursive call. Then you proceed to that breakpoint with the `GO` command.

Example 11.10. Using the `SCROLL/UP DEBUG` Command

```
- SRC: module C_TEST_ROUTINES -scroll-
```

```
source-----
```

```
80: void test_c_code4(void)
81: {
82:     int i,k;
83:     for(k=0;k<1000;k++)
84:     {
85:         test_c_code5(&i);
86:     }
87:     return;
88: }
89: int test_c_code3(int subrtnCount)
90: {
91:     subrtnCount = subrtnCount - 1;
92:     if (subrtnCount != 0)
93:         subrtnCount = test_c_code3(subrtnCount);
94:     return subrtnCount;
95: }
96: int test_c_code2(__int64 in64,int in32, __int64 test, __int64*
pVar)
97: {
98:     c_test_array[5] = in64;
99:     c_test_array[6] = in32;
100:    if (c_test_array[9] > 0)
101:        *pVar = (*pVar + c_test_array[17]) & c_test_array[9];
102:    else
```

```
- OUT -
```

```
output-----
```

```
- PROMPT -error-program-
prompt-----
```

```
DBG> Scroll/Up
DBG> set break %line 93
DBG> go
DBG>
```

When you reach that breakpoint, the source code display is updated to show where you currently are, which is indicated by an arrow. A message also appears in the OUT display indicating you reach the breakpoint at that line.

Example 11.11. Breakpoint Display

```
- SRC: module C_TEST_ROUTINES -scroll-
source-----
    82:      int i,k;
    83:      for(k=0;k<1000;k++)
    84:      {
    85:          test_c_code5(&i);
    86:      }
    87:      return;
    88: }
    89: int test_c_code3(int subrtnCount)
    90: {
    91:     subrtnCount = subrtnCount - 1;
    92:     if (subrtnCount != 0)
->  93:         subrtnCount = test_c_code3(subrtnCount);
    94:     return subrtnCount;
    95: }
    96: int test_c_code2(__int64 in64,int in32, __int64 test, __int64*
pVar)
    97: {
    98:     c_test_array[5] = in64;
    99:     c_test_array[6] = in32;
   100:     if (c_test_array[9] > 0)
   101:         *pVar = (*pVar + c_test_array[17]) & c_test_array[9];
   102:     else
   103:         *pVar = (*pVar + c_test_array[17]);
   104:     c_test_array[7] = test_c_code3(10);
- OUT -
output-----
break at C_TEST_ROUTINES\test_c_code3\%LINE 93
```



```
- PROMPT -error-program-
prompt-----
```

```
DBG> Scroll/Up
DBG> set break %line 93
DBG> go
DBG>
```

Now you try the debugger's STEP command. The default behavior for STEP is STEP/OVER, unlike XDELTA and DELTA, which is STEP/INTO, so, normally you would expect to step to line 94 in the code. However, because you have a breakpoint inside test_c_code3 that is called at line 93, you will reach that event first.

Example 11.12. Using the Debug Step Command

```
- SRC: module C_TEST_ROUTINES -scroll-
source-----
    82:     int i,k;
    83:     for(k=0;k<1000;k++)
    84:     {
    85:         test_c_code5(&i);
    86:     }
    87:     return;
    88: }
    89: int test_c_code3(int subrtnCount)
    90: {
    91:     subrtnCount = subrtnCount - 1;
    92:     if (subrtnCount != 0)
->  93:         subrtnCount = test_c_code3(subrtnCount);
    94:     return subrtnCount;
    95: }
    96: int test_c_code2(__int64 in64,int in32, __int64 test, __int64*
pVar)
    97: {
    98:     c_test_array[5] = in64;
    99:     c_test_array[6] = in32;
   100:     if (c_test_array[9] > 0)
   101:         *pVar = (*pVar + c_test_array[17]) & c_test_array[9];
   102:     else
   103:         *pVar = (*pVar + c_test_array[17]);
   104:     c_test_array[7] = test_c_code3(10);
- OUT -
output-----
break at C_TEST_ROUTINES\test_c_code3\%LINE 93
break at C_TEST_ROUTINES\test_c_code3\%LINE 93
```

```
- PROMPT -error-program-
prompt-----
```

```
DBG>
DBG> set break %line 93
DBG> go
DBG> Step
DBG>
```

Now, you try a couple of other commands, EXAMINE and SHOW CALLS. The EXAMINE command allows you to look at all the C variables. Note that the C_TEST_ROUTINES module is compiled with the /NOOPTIMIZE switch which allows access to all variables. The SHOW CALLS command shows you the call sequence from the beginning of the stack. In this case, you started out in the image EXEC_INIT. (The debugger prefixes all images other than the main image with SHARE\$ so it shows up as SHARE\$EXEC_INIT. The suffix _CODE0 is appended if the executive image is sliced.)

Example 11.13. Using the Examine and Show Calls Commands

```
- SRC: module C_TEST_ROUTINES -scroll-
source-----
    82:     int i,k;
    83:     for(k=0;k<1000;k++)
    84:     {
    85:         test_c_code5(&i);
    86:     }
    87:     return;
    88: }
    89: int test_c_code3(int subrtnCount)
    90: {
    91:     subrtnCount = subrtnCount - 1;
    92:     if (subrtnCount != 0)
->  93:         subrtnCount = test_c_code3(subrtnCount);
    94:     return subrtnCount;
    95: }
    96: int test_c_code2(__int64 in64,int in32, __int64 test, __int64*
pVar)
    97: {
    98:     c_test_array[5] = in64;
    99:     c_test_array[6] = in32;
   100:     if (c_test_array[9] > 0)
   101:         *pVar = (*pVar + c_test_array[17]) & c_test_array[9];
   102:     else
   103:         *pVar = (*pVar + c_test_array[17]);
   104:     c_test_array[7] = test_c_code3(10);
- OUT -
output-----
```

```

C_TEST_ROUTINES\test_c_code3\subrtnCount:      8
  module name      routine name      line      rel PC      abs PC
*C_TEST_ROUTINES test_c_code3          93      0000000000000DC0
  FFFFFFFF800BAFC0
*C_TEST_ROUTINES test_c_code3          93      0000000000000DE0
  FFFFFFFF800BAFE0
*C_TEST_ROUTINES test_c_code2         104      0000000000000F40
  FFFFFFFF800BB140
*C_TEST_ROUTINES test_c_code         117      00000000000010B0
  FFFFFFFF800BB2B0
  XDT$INIT      00000000000015C0
  FFFFFFFF880955C0
*SYS$DOINIT      EXE$INITIALIZE    1973      0000000000000360
  FFFFFFFF88094360
  SHARE$EXEC_INIT_CODE0      0000000000005C240
  FFFFFFFF803BB640
  SHARE$EXEC_INIT_CODE0      00000000000057F20
  FFFFFFFF803B7320
  SHARE$EXEC_INIT_CODE0      00000000000047850
  FFFFFFFF803A6C50
  SHARE$EXEC_INIT_CODE0      00000000000042E90
  FFFFFFFF803A2290
- PROMPT -error-program-
prompt-----
DBG> set break %line 93
DBG> go
DBG> Step
DBG> examine subrtnCount
DBG> show calls
DBG>

```

If you want to proceed because you are done debugging this code, first cancel all the breakpoints and then enter the GO command. Notice, however, that you do not keep running but receive a message that you have stepped to line 94. This happens because the STEP command used earlier never completed. It was interrupted by the breakpoint on line 93.

Note that the debugger remembers all step events and only removes them once they have completed.

Example 11.14. Canceling the Breakpoints

```

- SRC: module C_TEST_ROUTINES -scroll-
source-----
  83:      for(k=0;k<1000;k++)
  84:      {
  85:          test_c_code5(&i);
  86:      }
  87:      return;
  88: }
  89: int test_c_code3(int subrtnCount)
  90: {
  91:     subrtnCount = subrtnCount - 1;
  92:     if (subrtnCount != 0)
  93:         subrtnCount = test_c_code3(subrtnCount);
-> 94:     return subrtnCount;
  95: }
  96: int test_c_code2(__int64 in64,int in32, __int64 test, __int64*
pVar)
  97: {

```

```

 98:      c_test_array[5] = in64;
 99:      c_test_array[6] = in32;
100:      if (c_test_array[9] > 0)
101:          *pVar = (*pVar + c_test_array[17]) & c_test_array[9];
102:      else
103:          *pVar = (*pVar + c_test_array[17]);
104:      c_test_array[7] = test_c_code3(10);
105:      c_test_array[3] = test;
- OUT -
output-----
 module name      routine name      line      rel PC      abs PC
*C_TEST_ROUTINES test_c_code3      93        000000000000DC0
FFFFFFFFF800BAFC0
*C_TEST_ROUTINES test_c_code3      93        000000000000DE0
FFFFFFFFF800BAFE0
*C_TEST_ROUTINES test_c_code2      104       000000000000F40
FFFFFFFFF800BB140
*C_TEST_ROUTINES test_c_code      117       00000000000010B0
FFFFFFFFF800BB2B0
                XDT$INIT      00000000000015C0
FFFFFFFFF880955C0
*SYS$DOINIT      EXE$INITIALIZE   1973      0000000000000360
FFFFFFFFF88094360
SHARE$EXEC_INIT_CODE0      0000000000005C240
FFFFFFFFF803BB640
SHARE$EXEC_INIT_CODE0      00000000000057F20
FFFFFFFFF803B7320
SHARE$EXEC_INIT_CODE0      00000000000047850
FFFFFFFFF803A6C50
SHARE$EXEC_INIT_CODE0      00000000000042E90
FFFFFFFFF803A2290
stepped to C_TEST_ROUTINES\test_c_code3\%LINE 94
- PROMPT -error-program-
prompt-----
DBG> Step
DBG> examine subrtnCount
DBG> show calls
DBG> cancel break/all
DBG> go
DBG>

```

The **STEP/RETURN** command, a different type of step command, single steps assembly code until it finds a return instruction. This command is useful if you want to see the return value for the routine, which is done here by examining the R0 register on Alpha, or the R8 register on Integrity servers.

For more information about using other **STEP** command qualifiers, see the *VSI OpenVMS Debugger Manual*.

Example 11.15. Using the Step/Return Command

```

- SRC: module C_TEST_ROUTINES -scroll-
source-----
 83:      for (k=0;k<1000;k++)
 84:          {
 85:              test_c_code5(&i);
 86:          }
 87:      return;
 88: }

```

```

89: int test_c_code3(int subrtnCount)
90: {
91:     subrtnCount = subrtnCount - 1;
92:     if (subrtnCount != 0)
93:         subrtnCount = test_c_code3(subrtnCount);
-> 94:     return subrtnCount;
95: }
96: int test_c_code2(__int64 in64,int in32, __int64 test, __int64*
pVar)
97: {
98:     c_test_array[5] = in64;
99:     c_test_array[6] = in32;
100:    if (c_test_array[9] > 0)
101:        *pVar = (*pVar + c_test_array[17]) & c_test_array[9];
102:    else
103:        *pVar = (*pVar + c_test_array[17]);
104:    c_test_array[7] = test_c_code3(10);
105:    c_test_array[3] = test;

```

- OUT -

output-----

```

*C_TEST_ROUTINES test_c_code3      93      00000000000000DE0
FFFFFFFF800BAFE0
*C_TEST_ROUTINES test_c_code2     104     00000000000000F40
FFFFFFFF800BB140
*C_TEST_ROUTINES test_c_code     117     000000000000010B0
FFFFFFFF800BB2B0
          XDT$INIT                    000000000000015C0
FFFFFFFF880955C0
*SYS$DOINIT      EXE$INITIALIZE   1973    00000000000000360
FFFFFFFF88094360
SHARE$EXEC_INIT_CODE0              00000000000005C240
FFFFFFFF803BB640
SHARE$EXEC_INIT_CODE0              000000000000057F20
FFFFFFFF803B7320
SHARE$EXEC_INIT_CODE0              000000000000047850
FFFFFFFF803A6C50
SHARE$EXEC_INIT_CODE0              000000000000042E90
FFFFFFFF803A2290

```

stepped to C_TEST_ROUTINES\test_c_code3\%LINE 94

stepped on return from C_TEST_ROUTINES\test_c_code3\%LINE 94 to

C_TEST_ROUTINES\test_c_code3\%LINE 94+17

C_TEST_ROUTINES\test_c_code3\%R8: 0

- PROMPT -error-program-

prompt-----

```

DBG> show calls
DBG> cancel break/all
DBG> go
DBG> step/return
DBG> examine r8
DBG>

```

After you finish the SCD session, enter the GO command to leave this module. You will encounter another INI\$BRK breakpoint at the end of EXEC_INIT. An error message is displayed indicating there are no source lines, because debug information on INI\$BRK is not available.

Also notice that there is no message in the OUT display for this event. That is because INI\$BRKs are special breakpoints that are handled as SS\$_DEBUG signals. They are a method for the system code to break into the debugger and there is no real breakpoint in the code.

Enter the `SHOW IMAGE` command. You will see more images displayed as the boot path has progressed further.

Finally, enter `GO`, allowing the target system to boot completely, because there are no more breakpoints in the boot path. The debugger will wait for another event to occur.

Example 11.16. Using the Show Image Command

```
- SRC: module C_TEST_ROUTINES -scroll-
source-----
 83:     for(k=0;k<1000;k++)
 84:     {
 85:         test_c_code5(&i);
 86:     }
 87:     return;
 88: }
 89: int test_c_code3(int subrtnCount)
 90: {
 91:     subrtnCount = subrtnCount - 1;
 92:     if (subrtnCount != 0)
 93:         subrtnCount = test_c_code3(subrtnCount);
-> 94:     return subrtnCount;
 95: }
 96: int test_c_code2(__int64 in64,int in32, __int64 test, __int64*
pVar)
 97: {
 98:     c_test_array[5] = in64;
 99:     c_test_array[6] = in32;
100:     if (c_test_array[9] > 0)
101:         *pVar = (*pVar + c_test_array[17]) & c_test_array[9];
102:     else
103:         *pVar = (*pVar + c_test_array[17]);
104:     c_test_array[7] = test_c_code3(10);
105:     c_test_array[3] = test;
- OUT -
output-----
SYS$UTC_SERVICES          no      0000000000000000
FFFFFFFFFFFFFFFF
SYS$VM                    no      0000000000000000
FFFFFFFFFFFFFFFF
SYS$XFCACHE_MON          no      0000000000000000
FFFFFFFFFFFFFFFF
SYSDEVICE                 no      0000000000000000
FFFFFFFFFFFFFFFF
SYSGETSYI                 no      0000000000000000
FFFFFFFFFFFFFFFF
SYSLDR_DYN                no      0000000000000000
FFFFFFFFFFFFFFFF
SYSLICENSE                no      0000000000000000
FFFFFFFFFFFFFFFF
SYSTEM_DEBUG              yes     0000000000000000
FFFFFFFFFFFFFFFF
SYSTEM_PRIMITIVES        no      0000000000000000
FFFFFFFFFFFFFFFF
SYSTEM_SYNCHRONIZATION   no      0000000000000000
FFFFFFFFFFFFFFFF

total images: 53
```

```
- PROMPT -error-program-  
prompt-----  
DBG> go  
%DEBUG-I-INIBRK, target system interrupted  
%DEBUG-I-DYNIMGSET, setting image SYS$BASE_IMAGE  
%DEBUG-W-SCRNOSRCLIN, No source line for address: FFFFFFFF80000310  
DBG> show image  
DBG> go
```


Chapter 12. OpenVMS System Dump Debugger

This chapter describes the OpenVMS System Dump Debugger (SDD) and how you can use it to analyze system crash dumps.

SDD is similar in concept to SCD as described in Chapter 11. Where SCD allows connection to a running system with control of the system's execution and the examination and modification of variables, SDD allows analysis of memory as recorded in a system dump.

Use of the SDD usually involves two systems, although all the required environment can be set up on a single system. The description that follows assumes that two systems are being used:

- The build system, where the image that causes the system crash has been built
- The test system, where the image is executed and the system crash occurs

In common with SCD, the OpenVMS debugger's user interface allows you to specify variable names, routine names, and so on, precisely as they appear in your source code. Also, SDD can display the source code where the software was executing at the time of the system crash.

SDD recognizes the syntax, data typing, operators, expressions, scoping rules, and other constructs of a given language. If your code or driver is written in more than one language, you can change the debugging context from one language to another during a debugging session.

To use SDD, you must do the following:

- Build the system image or device driver that is causing the system crash.
- Boot a system, including the system image or device driver, and perform the necessary steps to cause the system crash.
- Reboot the system and save the dump file.
- Invoke SDD, which is integrated with the OpenVMS debugger.

The following sections cover these tasks in more detail, describe the available user-interface options, summarize applicable OpenVMS Debugger commands, and provide a sample SDD session.

12.1. User-Interface Options

SDD has the following user-interface options.

- A DECwindows Motif interface for workstations.

When using this interface, you interact with SDD by using a mouse and pointer to choose items from menus, click on buttons, select names in windows, and so on.

Note that you can also use OpenVMS Debugger commands with the DECwindows Motif interface.

- A character cell interface for terminals and workstations.

When using this interface, you interact with SDD by entering commands at a prompt. The sections in this chapter describe how to use the system dump debugger with the character cell interface.

For more information about using the OpenVMS DECwindows Motif interface and OpenVMS Debugger commands with SDD, see the *VSI OpenVMS Debugger Manual*.

12.2. Preparing a System Dump to Be Analyzed

To prepare a system dump for analysis, perform the following steps:

1. Compile the sources you will want to analyze, and use the `/DEBUG` (mandatory) and `/NOOPT` (preferred) qualifiers.

Note

Because you are analyzing a snapshot of the system, it is not as vital to use unoptimized code as it is with the system code debugger. But note that you cannot access all variables. SDD may report that they are optimized away.

2. Link your image using the `/DSF` (debug symbol file) qualifier. Do not use the `/DEBUG` qualifier, which is for debugging user programs. The `/DSF` qualifier takes an optional filename argument similar to the `/EXE` qualifier. For more information, see the *VSI OpenVMS Linker Utility Manual*. If you specify a name in the `/EXE` qualifier, you will need to specify the same name for the `/DSF` qualifier. For example, you would use the following command:

```
$ LINK/EXE=EXE$:MY_EXECLET/DSF=EXE$:MY_EXECLET OPTIONS_FILE/OPT
```

The `.DSF` and `.EXE` file names must be the same. Only the extensions will be different, that is, `.DSF` and `.EXE`.

The contents of the `.EXE` file should be exactly the same as if you had linked without the `/DSF` qualifier. The `.DSF` file will contain the image header and all the debug symbol tables for `.EXE` file. It is not an executable file, and cannot be run or loaded.

3. Put the `.EXE` file on your test system.
4. Boot the test system and perform the necessary steps to cause the system crash.
5. Reboot the test system and copy the dump to the build system using the System Dump Analyzer (SDA) command `COPY`. See Chapter 4.

12.3. Setting Up the Test System

The only requirement for the test system is that the `.DSF` file matching the `.EXE` file that causes the crash is available on the build system.

There are no other steps necessary in the setup of the test system. With the system image copied to the test system, it can be booted in any way necessary to produce the system crash. Since SDD can analyze most system crash dumps, any system can be used, from a standalone system to a member of a production cluster.

Note

It is assumed that the test system has a dump file large enough for the system dump to be recorded. Any dump style may be used (full or selective, compressed or uncompressed). A properly AUTOGENed system will meet these requirements.

12.4. Setting Up the Build System

To set up the build system, you need access to all system images and drivers that were loaded on the test system. You should have access to a source listings kit or a copy of the following directories:

```
SYS$LOADABLE_IMAGES:
SYS$LIBRARY:
SYS$MESSAGE:
```

You need all the .EXE files in those directories. The .DSF files are available with the OpenVMS source listings kits.

Optionally, you need access to the source files for the images to be debugged. SDD will look for the source files in the directory where they were compiled. You must use the SET SOURCE command to point SDD to the location of the source code files if they are not in the directories used when the image was built. For an example of the SET SOURCE command, see Section 12.9.

Before you can analyze a system dump with SDD, you must set up the logical name DBGHK\$IMAGE_PATH, which must be set up as a search list to the area where the system images or .DSF files are kept. For example, if the copies are in the following directories:

```
DEVICE:[SYS$LDR]
DEVICE:[SYS$LIB]
DEVICE:[SYS$MSG]
```

you would define DBGHK\$IMAGE_PATH as follows:

```
$ define dbghk$image_path DEVICE:[SYS$LDR],DEVICE:[SYS$LIB],DEVICE:[SYS$MSG]
```

This works well for analyzing a system dump using all the images normally loaded on a given system. However, you might be using SDD to analyze new code either in an execut or a new driver. Because that image is most likely in your default directory, you must define the logical name as follows:

```
$ define dbghk$image_path [],DEVICE:[SYS$LDR],DEVICE:[SYS$LIB],DEVICE:
[SYS$MSG]
```

If SDD cannot find one of the images through this search path, a warning message is displayed. SDD will continue initialization as long as it finds at least two images. If SDD cannot find the SYS\$BASE_IMAGE and SYS\$PUBLIC_VECTORS files, which are the OpenVMS operating system's main image files, an error message is displayed and the debugger exits.

If and when this happens, check the directory for the image files and compare it to what was loaded on the test system.

12.5. Starting the System Dump Debugger

To start SDD on the build system, enter the following command.

```
$ DEBUG/KEEP
```

SDD displays the `DBG>` prompt. With the `DBGHK$IMAGE_PATH` logical name defined, you can invoke the `ANALYZE/CRASH_DUMP` command and optional qualifier `/IMAGE_PATH`.

To use the `ANALYZE/CRASH_DUMP` command and optional qualifier (`/IMAGE_PATH`) to analyze the dump in file `<file-name>` enter the following command:

```
DBG> ANALYZE/CRASH_DUMP file-name
```

The `/IMAGE_PATH` qualifier is optional. If you do not use this qualifier, SDD uses the `DBGHK$IMAGE_PATH` logical name as the default. The `/IMAGE_PATH` qualifier is a quick way to change the logical name. However, when you use it, you cannot specify a search list. You can use only a logical name or a device and directory, although the logical name can be a search list.

Usually, SDD obtains the source file name from the object file. This is put there by the compiler when the source is compiled with the `/DEBUG` qualifier. The `SET SOURCE` command can take a list of paths as a parameter. It treats them as a search list.

12.6. Summary of System Dump Debugger Commands

Only a subset of OpenVMS debugger commands can be used in SDD. The following are a few examples of commands that you can use in SDD:

- Commands to manipulate the source display, such as `TYPE` and `SCROLL`
- Commands used in OpenVMS debugger command programs, such as `DO` and `IF`
- Commands that affect output formats, such as `SET RADIX`
- Commands that manipulate symbols and scope, such as `EVALUATE`, `SET LANGUAGE`, and `CANCEL SCOPE`
- Commands that read the contents of memory and registers, such as `EXAMINE`

Examples of commands that **cannot** be used in SDD are as follows:

- Commands that cause code to be executed, such as `STEP` and `GO`
- Commands that manipulate breakpoints, such as `SET BREAK` and `CANCEL BREAK`
- Commands that modify memory or registers, such as `DEPOSIT`

You can also use the OpenVMS debugger command `SDA` to examine the system dump with System Dump Analyzer semantics. This command, which is not available when debugging user programs, is described in the next section.

12.7. Using System Dump Analyzer Commands

Once a dump file has been opened, you can use the commands listed in the previous section to examine the system dump. You can also use some System Dump Analyzer (SDA) commands, such as `SHOW SUMMARY` and `SHOW DEVICE`. This feature allows the system programmer to take advantage of the strengths of both the OpenVMS Debugger and SDA to examine the system dump and to debug system programs such as device drivers, without having to invoke both the OpenVMS debugger and SDA separately.

To obtain access to SDA commands, you simply type "SDA" at the OpenVMS Debugger prompt ("DBG>") at any time after the dump file has been opened. SDA initializes itself and then outputs the "SDA>" prompt. Enter SDA commands as required. (See Chapter 4 for more information.) To return to the OpenVMS Debugger, you enter "EXIT" at the "SDA>" prompt. Optionally, you may invoke SDA to perform a single command and then return immediately to the OpenVMS Debugger, as in the following example:

```
DBG> SDA SHOW SUMMARY
```

SDA may be reentered at any time, with or without the optional SDA command. Once SDA has been initialized, the SDA> prompt is output more quickly on subsequent occasions.

Note that there are some limitations on the use of SDA from within SDD:

- You cannot switch between processes, whether requested explicitly (SET PROCESS <name>) or implicitly (SHOW PROCESS <name>). The exception to this is that access to the system process is possible.
- You cannot switch between CPUs.
- SDA has no knowledge of the OpenVMS debugger's Motif or Windows interfaces. Therefore, all SDA input and output occurs at the terminal or window where the OpenVMS debugger was originally invoked. Also, while using SDA, the OpenVMS debugger window is not refreshed; you must exit SDA to allow the OpenVMS debugger window to be refreshed.
- When you invoke SDA from SDD with an immediate command, and that command produces a full screen of output, SDA displays the message "Press RETURN for more." followed by the "SDA>" prompt before continuing. At this prompt, if you enter another SDA command, SDA does not automatically return to SDD upon completion. To do this, you must enter an EXIT command.

If the need arises to switch between processes or CPUs in the system dump, then you must invoke SDA separately using the DCL command ANALYZE/CRASH_DUMP.

12.8. Limitations of the System Dump Debugger

SDD provides a narrow window into the context of the system that was current at the time that the system crashed (stack, process, CPU, and so on). It does not provide full access to every part of the system as is provided by SDA. However, it does provide a view of the failed system using the semantics of the OpenVMS debugger---source correlation and display, call frame traversal, examination of variables by name, language constructs, and so on.

SDD therefore provides an additional approach to analyzing system dumps that is difficult to realize with SDA, often allowing quicker resolution of system crashes than is possible with SDA alone. When SDD cannot provide the needed data from the system dump, you should use SDA instead.

12.9. Access to Symbols in OpenVMS Executive Images

For a discussion and explanation of how the OpenVMS debugger accesses symbols in OpenVMS executive images, see Section 11.11.

12.10. Sample System Dump Debugging Session

This section provides a sample session that shows the use of some OpenVMS debugger commands as they apply to the system dump debugger. The examples in this section show how to work with a dump created as follows:

1. Follow the steps in Section 11.12, up to and including Example 11.9 (Using the Set Mode Screen Command).
2. Enter the following OpenVMS Debugger commands:

```
DBG> SET BREAK TEST_C_CODE5
DBG> GO
DBG> DEPOSIT K=0
DBG> GO
```

3. The system then crashes and a dump is written.
4. When the system reboots, copy the contents of SYS\$SYSTEM:SYSDUMP.DMP to the build system with SDA:

```
$ analyze/crash sys$system:sysdump.dmp

OpenVMS (TM) system dump analyzer
...analyzing a selective memory dump...

%SDA-W-NOTSAVED, global pages not saved in the dump file
Dump taken on 1-JAN-1998 00:00:00.00
INVEXCEPTN, Exception while above ASTDEL

SDA> copy hstsys::sysdump.dmp
SDA>
```

To reproduce this sample session, you need access to the SYSTEM_DEBUG.DSF matching the SYSTEM_DEBUG.EXE file on your test system and to the source file C_TEST_ROUTINES.C, which is available in SYS\$EXAMPLES.

The example begins by invoking the system dump debugger's character cell interface on the build system.

Note that the example displays from Example 12-1 onwards are all taken from an OpenVMS Integrity server system. On an OpenVMS Alpha system, some of the output is different, but the commands entered are the same on both platforms.

Example 12.1. Invoking the System DumpDebugger

```
$ define dbg$decw$display " "
$ debug/keep
```

```
OpenVMS I64 Debug64 Version V8.3-003
```

```
DBG>
```

Use the ANALYZE/CRASH_DUMP command to open the system dump. In this example, the logical name DBGHK\$IMAGE_PATH is used for the image path, so the command qualifier /IMAGE_PATH is not being used. You may need to use it.

When you have opened the dump file, the `DBG>` prompt is displayed. You should now do the following:

1. Set the language to be C, the language of the module that was active at the time of the system crash.
2. Set the source directory to the location of the source of the module. Use the debugger's `SET SOURCE` command, which takes a search list as a parameter so you can make it point to many places.

Example 12.2. Accessing the System Dump

```
DBG> analyze/crash_dump sysdump.dmp
%SDA-W-NOTSAVED, global pages not saved in the dump file
%DEBUG-I-INIBRK, target system interrupted
%DEBUG-I-DYNIMGSET, setting image SYSTEM_DEBUG
%DEBUG-I-DYNMODSET, setting module C_TEST_ROUTINES
DBG> set language c
DBG> set source/latest sys$examples,sys$library
DBG>
```

Now that the debugger has access to the source, you can put the debugger into screen mode to see exactly where you are and the code surrounding it.

Example 12.3. Displaying the Source Code

```
DBG> Set Mode Screen; Set Step Nosource
```

```
- SRC: module C_TEST_ROUTINES -scroll-
source-----
 67:
 68:     /* We want some global data cells */
 69: volatile __int64 c_test_array[34];
 70:
 71: void test_c_code5(int *k)
 72: {
 73:     int i;
 74:     char str[100];
 75:     for(i=0;i<100;i++)
 76:         str[i]= 'a';
 77:     str[99]=0;
-> 78:     *k = 9;
 79: }
 80: void test_c_code4(void)
 81: {
 82:     int i,k;
 83:     for(k=0;k<1000;k++)
 84:     {
 85:         test_c_code5(&i);
 86:     }
 87:     return;
 88: }
 89: int test_c_code3(int subrtnCount)
- OUT -
output-----
```

```
- PROMPT -error-program-
prompt-----
```

```
%DEBUG-I-SCRNOTORIGSRC, original version of source file not found for
  display in SRC
      file used is SYS$COMMON:[SYSHLP.EXAMPLES]C_TEST_ROUTINES.C;1
DBG>
```

Now, you try a couple of other commands, EXAMINE and SHOW CALLS. The EXAMINE command allows you to look at all the C variables. Note that the C_TEST_ROUTINES module is compiled with the /NOOPTIMIZE switch which allows access to all variables. The SHOW CALLS command shows you the call sequence from the beginning of the stack. In this case, you started out in the image EXEC_INIT. (The debugger prefixes all images other than the main image with SHARE\$ so it shows up as SHARE\$EXEC_INIT.)

Example 12.4. Using the Examine and Show Calls Commands

```
DBG> Set Mode Screen; Set Step Nosource

- SRC: module C_TEST_ROUTINES -scroll-
source-----
  67:
  68:     /* We want some global data cells */
  69: volatile __int64 c_test_array[34];
  70:
  71: void test_c_code5(int *k)
  72: {
  73:     int i;
  74:     char str[100];
  75:     for(i=0;i<100;i++)
  76:         str[i]= 'a';
  77:     str[99]=0;
-> 78:     *k = 9;
  79: }
  80: void test_c_code4(void)
  81: {
  82:     int i,k;
  83:     for(k=0;k<1000;k++)
  84:     {
  85:         test_c_code5(&i);
  86:     }
  87:     return;
  88: }
  89: int test_c_code3(int subrtnCount)
```


- OUT -

```

output-----
C_TEST_ROUTINES\test_c_code5\i: 100
C_TEST_ROUTINES\test_c_code5\k: 0
  module name      routine name      line      rel PC      abs PC
*C_TEST_ROUTINES test_c_code5        78        000000000000CD0
  FFFFFFFF800BAED0
*C_TEST_ROUTINES test_c_code4        85        000000000000D60
  FFFFFFFF800BAF60
*C_TEST_ROUTINES test_c_code        118       00000000000010D0
  FFFFFFFF800BB2D0
                                XDT$INIT
                                00000000000015C0
  FFFFFFFF880955C0
*SYS$DOINIT      EXE$INITIALIZE    1973     0000000000000360
  FFFFFFFF88094360
  SHARE$EXEC_INIT_CODE0
                                0000000000005C240
  FFFFFFFF803BB640
  SHARE$EXEC_INIT_CODE0
                                00000000000057F20
  FFFFFFFF803B7320
  SHARE$EXEC_INIT_CODE0
                                00000000000047850
  FFFFFFFF803A6C50
  SHARE$EXEC_INIT_CODE0
                                00000000000042E90
  FFFFFFFF803A2290
- PROMPT -error-program-
prompt-----

```

```

%DEBUG-I-SCRNOTORIGSRC, original version of source file not found for
display in SRC

```

```

file used is SYS$COMMON:[SYSHLP.EXAMPLES]C_TEST_ROUTINES.C;1

```

```

DBG> examine i,k

```

```

DBG> show calls

```

```

DBG>

```

Part III. OpenVMS Alpha Watchpoint Utility

This part describes the Alpha Watchpoint utility. It presents how to use the Watchpoint utility by doing the following:

- Loading the watchpoint driver
- Creating and deleting watchpoints
- Looking at watchpoint driver data
- Acquiring collected watchpoint data
- Looking at the protection attributes and access fault mechanism
- Looking at some watchpoint restrictions

Chapter 13. Watchpoint Utility (Alpha Only)

The Alpha Watchpoint utility (WP) enables you to monitor write access to user-specified locations. The chapter contains the following sections:

Section 13.1 presents an introduction of the Watchpoint utility.

Section 13.2 describes how to load the watchpoint driver.

Section 13.3 describes the creation and deletion of watchpoints and the constraints upon watchpoint locations.

Section 13.4 contains detailed descriptions of the watchpoint driver data structures, which you might need to know to analyze collected watchpoint data.

Section 13.5 discusses acquiring collected watchpoint data.

Section 13.6 describes the watchpoint protection facility.

Section 13.7 describes the utility's restrictions.

13.1. Introduction

A watchpoint is a data field to which write access is monitored. The field is from 1 to 8 bytes long and must be contained within a single page. Typically, watchpoints are in nonpaged pool. However, subject to certain constraints (see Section 13.3.1), they can be defined in other areas of system space. The Watchpoint facility can simultaneously monitor a large number (50 or more) watchpoints.

The utility is implemented in the WPDRIVER device driver and the utility program WP. This document concentrates on the device driver, which can be invoked directly or through the WP utility.

For information on the WP utility, see its help files, which can be displayed with the following DCL command:

```
$ HELP/LIBRARY=SYS$HELP:WP
```

Once the driver has been loaded, a suitably privileged user can designate a watchpoint in system space. Any write to a location designated as a watchpoint is trapped. Information is recorded about the write, including its time, the register contents, and the program counter (PC) and processor status longword (PSL) of the writing instruction. Optionally, one or both of the following user-specified actions can be taken:

- An XDELTA breakpoint (see the note below) or SCD breakpoint which occurs just after the write to the watchpoint
- A fatal watchpoint bugcheck which occurs just after the write to the watchpoint

You define a watchpoint by issuing QIO requests to the watchpoint driver; entering commands to the WP utility, which issues requests to the driver; or, from kernel mode code, invoking a routine within the watchpoint driver.

The WPDRIVER data structures store information about writes to a watchpoint. This information can be obtained either through QIO requests to the WPDRIVER, commands to the WP utility, XDELTA commands issued during a requested breakpoint, or SDA commands issued during the analysis of a requested crashdump.

Note

For simplicity, this chapter only mentions XDELTA. Any reference to XDELTA breakpoints also implies SCD breakpoints.

13.2. Initializing the Watchpoint Utility

From a process with CMKRNL privilege, run the SYSMAN utility to load the watchpoint driver, SYS\$WPDRIVER.EXE. Enter the following commands:

```
$ RUN SYS$SYSTEM:SYSMAN
SYSMAN> IO CONNECT WPA0:/NOADAPTER/DRIVER=SYS$WPDRIVER
SYSMAN> EXIT
```

SYSMAN creates system I/O data structures for the pseudo-device WPA0, loads WPDRIVER, and invokes its initialization routines. WPDRIVER initialization includes the following actions:

- Allocating nonpaged pool and physical memory for WPDRIVER data structures
- Appropriating the SCB vector specific to access violations
- Recording in system space the addresses of the WPDRIVER routines invoked by kernel mode code to create and delete watchpoints

Memory requirements for WPDRIVER and its data structures are:

- Device driver and UCB---approximately 3K bytes of nonpaged pool
- Trace table and a related array---36 bytes for each of system parameter WPTTE_SIZE trace table entries
- Watchpoint restore entries---system parameter WPRE_SIZE pages of physically contiguous memory
- Each watchpoint---176 bytes of nonpaged pool

It is advisable to load the watchpoint driver relatively soon after system initialization to ensure its allocation of physically contiguous memory. If the driver cannot allocate enough physically contiguous memory, it does not set WPA0: online. If the unit is offline, you will not be able to use the watchpoint utility.

13.3. Creating and Deleting Watchpoints

There are three different ways to create and delete watchpoints:

- An image can assign a channel to device WPA0: and then request the Queue I/O Request (\$QIO) system service to create or delete a watchpoint.
- Code running in kernel mode can dispatch directly to routines within the WPDRIVER to create and delete watchpoints.

- You can enter commands to the WP utility.

The first two methods are described in detail in the sections that follow.

13.3.1. Using the \$QIO Interface

An image first assigns a channel to the pseudo-device WPA0: and then issues a \$QIO request on that channel. The process must have the privilege PHY_IO; otherwise, the \$QIO request is rejected with the error SS\$_NOPRIV.

The table below shows the functions that the driver supports.

Table 13.1. Driver Supported Functions

Function	Activity
IO\$_ACCESS	Creates a watchpoint
IO\$_DEACCESS	Deletes a watchpoint
IO\$_RDSTATS	Receives trace information on a watchpoint

The IO\$_ACCESS function requires the following device/function dependent arguments:

- P2---Length of the watchpoint. A number larger than 8 is reduced to 8.
- P3---Starting address of the watchpoint area.

The following are the constraints on the watchpoint area. It must be:

- Nonpageable system space.
- Write-accessible from kernel mode.
- Within one page. If it is not, the requested length is reduced to what will fit within the page containing the starting address.
- Within a page accessed only from kernel mode and by instructions that incur no pagefaults.
- Within a page whose protection is not altered while the watchpoint is in place.
- Outside of certain address ranges. These are the WPDRIVER code, its data structures, and the system page table.

Because of the current behavior of the driver, there is an additional requirement that there be no "unexpected" access violations referencing a page containing a watchpoint. See Section 13.7 for further details.

To specify that an XDELTA breakpoint or a fatal bugcheck occur if the watchpoint is written, use the following I/O function code modifiers:

- IO\$_M_CTRL to request an XDELTA breakpoint
- IO\$_M_ABORT to request a fatal bugcheck

For an XDELTA breakpoint to be taken, OpenVMS must have been booted specifying that XDELTA and/or the SCD be resident (bit 1 or bit 15 in the boot flags must be set). If both watchpoint options

are requested, the XDELTA breakpoint is taken first. At exit from the breakpoint, the driver crashes the system.

A request to create a watchpoint can succeed completely, succeed partially, or fail. The table below shows the status codes that can be returned in the I/O status block.

Table 13.2. Returned Status Codes

Status Code	Meaning
SS\$_NORMAL	Success.
SS\$_BUFFEROVF	A watchpoint was established, but its length is less than was requested because the requested watchpoint would have straddled a page boundary.
SS\$_EXQUOTA	The watchpoint could not be created because too many watchpoints already exist.
SS\$_INSFMEM	The watchpoint could not be created because there was insufficient nonpaged pool to create data structures specific to this watchpoint.
SS\$_IVADDR	The requested watchpoint resides in one of the areas in which the WPDRIVER is unable to create watchpoints.
SS\$_WASSET	An existing watchpoint either coincides or overlaps with the requested watchpoint.

The following example MACRO program assigns a channel to the WPA0 device and creates a watchpoint of 4 bytes, at starting address 80001068. The program requests neither an XDELTA breakpoint nor a system crash for that watchpoint.

```

                                $IODEF
                                .PSECT   RWDATA, NOEXE, RD, WRT, LONG
                                ;
    WP_IOSB:  .BLKL   2                ; I/O status block.
    WP_ADDR:  .LONG   ^X80001068      ; Address of watchpoint to
create.
    WP_NAM:   .ASCID   /WPA0:/        ; Device to which to assign
channel.
    WP_CHAN:  .BLKW   1                ; Channel number.
                                .PSECT   PROG, EXE, NOWRT
                                ;
    START:   .CALL_ENTRY
                                ;
                                $ASSIGN_S DEVNAM=WP_NAM, CHAN=WP_CHAN
                                BLBC     R0, RETURN
                                ;
                                $QIOW_S  CHAN=WP_CHAN, -
                                FUNC=#IO$_ACCESS, -
                                IOSB=WP_IOSB, -
                                P2=#4, -
                                P3=WP_ADDR
                                BLBC     R0, RETURN
                                MOVL     WP_IOSB, R0      ; Move status to R0.
    RETURN:  RET      ; Return to caller.
                                .END     START

```


A watchpoint remains in effect until it is explicitly deleted. (Note, however, that watchpoint definitions do not persist across system reboots.) To delete an existing watchpoint, issue an `IO$_DEACCESS QIO` request.

The `IO$_DEACCESS` function requires the following device/function dependent argument: P3 - Starting address of the watchpoint to be deleted.

The table below shows the status values that are returned in the I/O status block.

Table 13.3. Returned Status Values

Status Value	Meaning
SS\$_NORMAL	Success.
SS\$_IVADDR	The specified watchpoint does not exist.

Section 13.5 describes the use of the `IO$_RDSTATS QIO` request.

13.3.2. Invoking WPDRIVER Entry Points from System Routines

When the `WPDRIVER` is loaded, it initializes two locations in system space with the addresses of routines within the driver. These locations, `WP$CREATE_WATCHPOINT` and `WP$DELETE_WATCHPOINT`, enable dispatch to create and delete watchpoint routines within the loaded driver. Input arguments for both routines are passed in registers.

Code running in kernel mode can execute the following instructions:

```
JSB    @G^WP$CREATE_WATCHPOINT ; create a watchpoint
```

and

```
JSB    @G^WP$DELETE_WATCHPOINT ; delete a watchpoint
```

Both these routines save IPL at entry and set it to the fork IPL of the `WPDRIVER`, IPL 11. Thus, they should not be invoked by code threads running above IPL 11. At exit, the routines restore the entry IPL.

These two locations contain an `RSB` instruction prior to the loading of the driver. As a result, if a system routine tries to create or delete a watchpoint before the `WPDRIVER` is loaded, control immediately returns.

`WP$CREATE_WATCHPOINT` has the following register arguments:

- R0---User-specified watchpoint options
 - Bit 1 equal to 1 specifies that a fatal `OPERCASH` bugcheck should occur after a write to the watchpoint area.
 - Bit 2 equal to 1 specifies that an `XDELTA` breakpoint should occur after a write to the watchpoint area.
- R1---Length of the watchpoint area
- R2---Starting address of the watchpoint area

Status is returned in R0. The status values and their interpretations are identical to those for the `QIO` interface to create a watchpoint. The only difference is that the `SS$_NOPRIV` status cannot be returned with this interface.

WPS\$DELETE_WATCHPOINT has the following register argument:

- R2---Starting address of the watchpoint area

Status is returned in R0. The status values and their interpretations are identical to those for the QIO interface.

13.4. Data Structures

The WPDRIVER uses three different kinds of data structures:

- One watchpoint restore entry (WPRE) for each page of system space in which one or more active watchpoints are located
- One watchpoint control block (WPCB) for each active watchpoint
- Trace table entries (WPTTEs) in a circular trace buffer which maintains a history of watchpoint writes

These data structures are described in detail and illustrated in the sections that follow.

13.4.1. Watchpoint Restore Entry (WPRE)

There is one WPRE for each system page that contains a watchpoint. That is, if nine watchpoints are defined which are in four different system pages, four WPREs are required to describe those pages. When WPDRIVER is loaded, its initialization routine allocates physically contiguous memory for the maximum number of WPREs. The number of pages to be allocated is specified by system parameter WPRE_SIZE.

The WPDRIVER allocates WPREs starting at the beginning of the table and maintains a tightly packed list. That is, when a WPRE in the middle of those in use is "deallocated," its current contents are replaced with the contents of the last WPRE in use. The number in use at any given time is in the driver variable WP\$L_WP_COUNT. The system global EXE\$GA_WP_WPRE points to the beginning of the WPRE table.

The WPRE for a page contains information useful for:

- Determining whether a given access violation refers to an address in the page associated with this WPRE
- Restoring the original SPTE value for the associated page
- Reestablishing the modified SPTE value when watchpoints are reenabled
- Invalidating the translation buffer when the SPTE is modified
- Locating the data structures associated with individual watchpoints defined in this system page

13.4.2. Watchpoint Control Blocks (WPCB)

The WPCBs associated with a given system page are singly-linked to a list header in the associated WPRE. A WPCB is allocated from a nonpaged pool when a watchpoint is created. A WPCB contains static information about the watchpoint such as the following:

- Its starting address and length
- Original contents of the watchpoint at the time it was established
- User-specified options for this watchpoint

In addition, the WPCB contains dynamic data associated with the most recent write reference to the watchpoint. This data includes the following:

- Number of times that the watchpoint has been written.
- Address of the first byte within the watchpoint that was modified at the last write reference.
- PC-PSL pair that made the last write reference.
- System time at the last write reference.
- Contents of the general registers at the time of the last write reference.
- A copy of up to 15 bytes of instruction stream data beginning at the program counter (PC) of the instruction that made the last write reference. The amount of instruction stream data that is copied here is the lesser of 15 bytes and the remaining bytes on the page containing the PC.
- Contents of the watchpoint before the last write reference.
- Contents of the watchpoint after the last write reference. This value is presumably the current contents of the watchpoint.
- A pointer to an entry in the global circular trace buffer where all recent references to watchpoints are traced.

13.4.3. Trace Table Entries (WPTTEs)

Whenever a watchpoint is written, all the relevant data is recorded in the WPCB associated with the watchpoint. In addition, to maintain a history, the WPDRIVER copies a subset of the data to the oldest WPTTE in the circular trace buffer. Thus, the circular trace buffer contains a history of the last N references to watchpoints. The driver allocates nonpaged pool to accommodate the number of trace table entries specified by the system parameter WPTTE_SIZE. The WPTTEs for all watchpoints are together in the table, but the ones for a particular watchpoint are chained together.

The subset of data in a WPTTE includes the following:

- Starting address of the watchpoint
- Relative offset of the first byte modified on this reference
- Opcode of the instruction that modified the watchpoint
- A relative backpointer to the previous WPTTE of this watchpoint
- PC-PSL of the write reference
- System time of the write reference
- Contents of the watchpoint before this reference

13.5. Analyzing Watchpoint Results

Analyzing watchpoint results is a function of the mode in which the WPDRIVER is used. For example, if you have only one watchpoint and have specified that an XDELTA breakpoint and/or a bugcheck occur on a write to the watchpoint, then when the reference occurs, simply find the program counter (PC) that caused the reference.

This PC (actually the PC of the next instruction) and its processor status longword (PSL) are on the stack at the time of the breakpoint and/or bugcheck. The layout that follows is the stack as it appears within an XDELTA breakpoint. Examined from a crash dump, the stack is similar but does not contain the return address from the JSB to INI\$BRK.

```
+-----+
|address in WPDRIVER from JSB G^INI$BRK| :SP
|PC of next instruction                |
|PSL at watchpoint access              |
+-----+
```

Furthermore, R0 contains the address of the WPCB associated with that watchpoint. You can examine the WPCB to determine the original contents of the watchpoint area and the registers at the time of the write.

Definitions for the watchpoint data structures are in SYS\$LIBRARY:LIB.MLB. Build an object module with its symbol definitions by entering the following DCL commands:

```
$ MACRO/OBJ=SYS$LOGIN:WPDEFS SYS$INPUT: + SYS$LIBRARY:LIB/LIB
    $WPCBDEF    GLOBAL    !n.b. GLOBAL must be capitalized
    $WPREDEF    GLOBAL
    $WPTTEDEF   GLOBAL
    .END
```

CTRL/Z

Then, within SDA, you can format watchpoint data structures. For example, enter the following SDA commands:

```
SDA>READ SYS$LOGIN:WPDEFS.OBJ
SDA>FORMAT @R0 /TYPE=WPCB    !type definition is required
SDA>DEF WPTTE = @R0 + WPCB$L_TTE
SDA>FORMAT WPTTE /TYPE=WPTTE
```

An alternative to crashing the system or using XDELTA to get watchpoint information is the QIO function IO\$_RDSTAT. This function returns watchpoint control block contents and trace table entries for a particular watchpoint.

It requires the following device/function dependent arguments:

- P1---Address of buffer to receive watchpoint data.
- P2---Length of the buffer. The minimum size buffer of 188 bytes is only large enough for WPCB contents.
- P3---Watchpoint address.

The data returned in the buffer has the format shown in the figure below.

Figure 13.1. Format of Data Returned in Buffer

Number of bytes copied to buffer
Total number of WPTTEs for watchpoint
Number of WPTTEs copied to buffer
WPCB
Most recent WPTTE
Next recent WPTTE
Next WPTTE
Next WPTTE

13.6. Watchpoint Protection Overview

The overall design of the watchpoint facility uses protection attributes on system pages and the access violation fault mechanism. To establish a watchpoint within a page of system space, the WPDRIVER changes the protection of the page to disallow writes. The WPDRIVER modifies the access violation vector to point to its own routine, WP\$ACCVIO.

Any subsequent write to this page causes an access violation and dispatch to WP\$ACCVIO. Thus, the WPDRIVER gains control on all write references to watchpoints and can monitor such accesses.

When WP\$ACCVIO is entered, it raises IPL to 31 to block all other threads of execution. It first must determine whether the faulting address (whose reference caused the access violation) is within a page containing a watchpoint. However, any major amount of CPU processing at this point might access an area in system space whose protection has been altered to establish watchpoints. As a result, such processing might cause a reentry into WP\$ACCVIO. To avoid recursive reentry, WP\$ACCVIO first restores all SPTEs that it had modified to their values prior to the establishment of any watchpoints. From this point until this set of SPTEs are remodified, no watchpoints are in effect. Now WP\$ACCVIO can determine whether the reference was to a page containing a watchpoint.

To determine whether the reference is to a watchpoint page, WP\$ACCVIO compares the faulting address to addresses of pages whose protection has been altered by WPDRIVER. If the faulting address is not in one of these pages, then WP\$ACCVIO passes the access violation to the usual OpenVMS service routine, EXE\$ACVIOLAT. If the faulting address is within a page containing a watchpoint, more extensive processing is required.

As a temporary measure, WP\$ACCVIO first records all data related to the reference in its UCB. It cannot immediately associate the access violation with a particular watchpoint. This ambiguity arises from imprecision in the faulting virtual address recorded at the access violation. The CPU need merely place on the stack "some virtual address in the faulting page."

As a result, when a reference to a page with a watchpoint results in an access violation, the watchpoint driver first merely captures the data in its UCB. The data captured at this point includes the following:

- PC and PSL of the faulting instruction

- Current system time
- Values of all the general registers from R0 through SP
- A copy of up to 15 bytes of the instruction stream, beginning at the PC previously captured

If the reference later turns out not to be one to a watchpoint, the captured data is discarded. If the reference is to a watchpoint, the data is copied to the WPCB and circular trace buffer.

The watchpoint driver distinguishes between these two possibilities by reexecuting the faulting instruction under a controlled set of circumstances.

Once the instruction has reexecuted, WP\$TBIT can determine whether watchpoint data has been modified by comparing the current contents of all watchpoints within the page of interest to the contents that they had prior to this reference. Because the driver has run at IPL 31 since the write access that caused an access violation, any change in the contents is attributable to the reexecuted instruction. If the contents of a watchpoint are different, WP\$TBIT copies the data temporarily saved in its UCB to the WPCB associated with this watchpoint and records a subset of this data in a WPTTE.

The driver can cause either or both an XDELTA breakpoint or a bugcheck, depending on what action was requested with the watchpoint definition. If an XDELTA breakpoint was requested, the driver invokes XDELTA. After the user proceeds from the XDELTA breakpoint, if a bugcheck was not requested, the driver restores the SPTEs of pages containing watchpoints, the saved registers and IPL, and REIs to dismiss the exception.

13.7. Restrictions

The WPDRIVER can monitor only those write references to system space addresses that arise in a CPU. I/O devices can write to memory and thereby modify watchpoints without the WPDRIVER's becoming aware of the write.

Because a write access to a watchpoint is determined by comparing the contents of the watchpoint before and after the write, a write of data identical to the original contents is undetectable.

Because the WPDRIVER modifies SPTEs, a device page that directly interprets tables may experience access violations when it attempts to write into a memory page whose protection has been modified to monitor watchpoints. In other words, a page containing a watchpoint should not also contain a buffer for such a controller.

When you create a watchpoint, you should ensure that the system is quiet with respect to activity affecting the watchpoint area. Otherwise, an inconsistent copy of the original contents of the watchpoint area may be saved. WPDRIVER raises IPL to 11 to copy the watchpoint area's original contents. This means that if the area is modified from a thread of execution running as the result of an interrupt above 11, WPDRIVER can copy inconsistent contents. An inconsistent copy of the original contents may result in spuriously detected writes and missed writes.

If the page containing the watchpoint area is written by an instruction that incurs a page fault, the system can crash with a fatal PGFIPLHI bugcheck. As described in the previous section, after detecting an attempt to write to a page with a watchpoint, the WPDRIVER re-executes the writing instruction at IPL 31. Page faults at IPL 31 are not allowed.

If an outer access mode reference to a watchpointed page causes an access violation, the system will likely crash. When an access violation occurs on a page with a watchpoint, the current driver does not probe the intended access and faulting mode against the page's original protection code. Instead,

it assumes that any access violation to that page represents a kernel mode instruction that can be reexecuted at IPL 31. The driver's subsequent attempt to REI, restoring a program status longword (PSL) with an outer mode and IPL 31, causes a reserved operand fault and, generally, a fatal INVEXCEPTN bugcheck.

You must be knowledgeable about the accesses to the page with the watchpoint and careful in using the driver. You should test the watchpoint creation on a standalone system. You should leave the watchpoint in effect long enough to have some confidence that pagefaults in instructions accessing that page are unlikely.

An attempt to CONNECT a WPA unit other than zero results in a fatal WPDRVRERR bugcheck.

The WPDRIVER is suitable for use only on a single CPU system. That is, it should not be used on a symmetric multiprocessing system. There are no plans to remove this restriction in the near future.

Part IV. OpenVMS System Service Logging Utility

This part describes the System Service Logging utility. It explains how to:

- Start logging
- Stop logging
- Display logged information

Chapter 14. System Service Logging

This chapter presents an overview of the System Service Logging utility and describes the System Service Logging commands.

14.1. Overview

System service logging (SSLOG) is used to record system service activity in a process. Its primary purpose is to troubleshoot process failure or misbehavior. This utility is available on OpenVMS Alpha and Integrity server platforms.

Once enabled, the SSLOG mechanism records information about system services requested by code running in the context of that process. The system services logged are:

- Executive and kernel-mode services
- Within privileged shareable image services
- Within the OpenVMS executive

SSLOG does not log the mode of caller services.

SSLOG information is initially recorded in process space buffers. When a buffer is full, it is written to a disk file in the process's default disk and directory. After the disk file is closed, you can analyze it with the ANALYZE/SSLOG utility.

Recorded Information

SSLOG records the following information for each service:

- Service identification
- Location of service request - image and offset
- Access mode of requester
- Service arguments (passed by value; only the addresses of arguments passed by reference)
- Timestamp
- Completion status
- Kernel thread, POSIX thread (PTHREAD), and CPU identifiers

The information is recorded as follows:

- It is initially recorded in a ring of P2 space buffers with each process having its own P2 space buffers.
- A full buffer is written to a disk file. By default, the file is SSLOG.DAT in the current default disk and directory. However, if the logical name SSLOG is defined, its equivalence string is used to form the log file name.

14.2. Enabling Logging

To enable any system service logging, check that the dynamic system parameter `SYSSER_LOGGING` is 1. If not, set it to a value of 1. Once logging is enabled, you can start system service logging for a particular process by DCL command, as shown in the following example.

```
$ SET PROCESS /SSLOG=(STATE=ON,COUNT=4)
```

By default, execution of this command affects the current process. To target another process, use the `/ID` qualifier or specify the process by name.

Use the `COUNT` keyword to specify the number of P2 space buffers to allocate for the process you are logging.

Buffers are pageable and therefore are charged against `PGFLQUOTA`. They are not deallocated until the process is deleted.

For additional information on this command, see the full description of the the section called “`SET PROCESS/SSLOG`” command.

14.3. Disabling Logging

There are two ways to disable logging, depending on whether you want the option to enable logging again on the same process.

- If you might want to re-enable logging on this process, use the following command to disable logging:

```
$ SET PROCESS /SSLOG=(STATE=OFF)
```

You can then re-enable logging later by executing the same command with `STATE=ON`.

- If you want to permanently end logging on this process, use the following command to close and truncate the log file:

```
$ SET PROCESS /SSLOG=(STATE=UNLOAD)
```

After you execute this command, you cannot enable logging on this process again.

14.4. Displaying Logged Information

You display logged information with the DCL command `ANALYZE/SSLOG filename`, where the default filename is `SSLOG.DAT`. For additional information on this command and examples, see the command the section called “`ANALYZE/SSLOG`”.

ANALYZE/SSLOG

Displays the collected data.

Format

```
ANALYZE/SSLOG [/BRIEF | /FULL | /NORMAL | /STATISTICS] [/OUTPUT=filename] [/SELECT
```

Parameters

filespec

Optional name of the log file to be analyzed. The default filename is SSLOG.DAT.

Qualifiers

/BRIEF

Displays abbreviated logged information.

/FULL

Displays logged information, error status messages and sequence numbers.

/NORMAL (Default)

Displays basic logged information.

/STATISTICS[=*BY_STATUS*]

Displays statistics on system services usage; accepts *BY_STATUS* keyword. Outputs a summary of the services logged with a breakdown by access mode. Output is ordered with the most frequently requested services first. If *BY_STATUS* is included, the summary is further separated by completion status. Output is displayed up to 132 columns wide.

/OUTPUT=*filename*

Identifies the output file for storing the results of the log analysis. An asterisk (*) and percent sign (%) are not allowed as wildcards in the file specification. There is no default file type or filename. If you omit the qualifier, results are output to the current SYS\$OUTPUT device.

/SELECT=(*[option[,...]]*)

Selects entries based on your choice of options. You must specify at least one of the following:

Keyword	Meaning
ACCESS_MODE= <i>mode</i>	Selects data by access mode.
IMAGE= <i>image-name</i>	Selects data by image name.
STATUS[= <i>n</i>]	Selects data by status. <i>n</i> is optional. / SELECT=STATUS displays all entries that have an error status.
SYSSER= <i>service-name</i>	Selects data by service name.

/WIDE

Provides for a display of logged information up to 132 columns wide.

Description

The ANALYZE/SSLOG command displays the collected logged data. Note that a system service log must be analyzed on the same platform type as the one on which it was created; for example, a log created on an OpenVMS Alpha system must be analyzed on an OpenVMS Alpha system.

Examples

The following examples demonstrate usage of the ANALYZE/SSLOG command.

```

1. $ ANALYZE /SSLOG /BRIEF
START  1.1      00000414  HERE          IA64      !25-MAY-2004
      14:55:17.77
          NAK      ::SYSTEM          4  65024

SYS$EXIT_INT          sts: -----  acmode: U  !
14:55:17.80
      image:          IMAGE_MANAGEMENT+00047ed0  argct:
      01
SYS$RMSRUNDN         sts: 00010001  acmode: S  !
14:55:17.80
      image:          DCL+00070370  argct:
      02
SYS$DCLAST          sts: 00000001  acmode: E  !
14:55:17.80
      image:          RMS+000e5840  argct:
      03
SYS$RMS_CLOSE       sts: 00010001  acmode: E  !
14:55:17.80
      image:          RMS+000d66c0  argct:
      03
SYS$SETEF           sts: 00000009  acmode: E  !
14:55:17.80
      image:          RMS+00125df0  argct:
      01
SYS$RMS_CLOSE       sts: 00010001  acmode: E  !
14:55:17.80
      image:          RMS+000d66c0  argct:
      03
SYS$SETEF           sts: 00000009  acmode: E  !
14:55:17.80
      image:          RMS+00125df0  argct:
      01
SYS$ERNDWN          sts: 00000001  acmode: S  !
14:55:17.80
      image:          IMAGE_MANAGEMENT+000274d0  argct:
      01
SYS$CMKRNL          sts: 8318ae00  acmode: E  !
14:55:17.80
      image:          IMAGE_MANAGEMENT+00027890  argct:
      02
[...]
```

The above example shows abbreviated SSLOG output.

The first entry displayed is a START message that describes the enabling of system service logging. The major and minor version numbers associated with this log file are both 1. Logging was initiated by process ID 0000041416 whose username was SYSTEM. This log file is from an OpenVMS Integrity server platform. The timestamp shows when logging was started. The process whose services were logged was named HERE and ran on node NAK. Logging was done into four buffers of 65024 bytes each.

Each subsequent entry describes a system service request. The leftmost column is the service name. The next item displayed is the hexadecimal completion status from that service request. If the status is displayed as "-----", one of the following circumstances occurred:

- The buffer filled and was written to disk before the service completed.
- The service returned to the system service dispatcher at an interrupt priority level (IPL) above 2. Because the process space buffers are pageable and page faults are not allowed above IPL 2, completion status cannot be logged when a service returns above IPL 2.

The next item displayed is the access mode from which the service was requested, followed by the time at which the service was requested. The next line shows the image and offset within the image of the service request and the number of arguments with which the service was requested. Service arguments are not displayed when you enter the command ANALYZE/SSLOG/BRIEF.

2. \$ ANALYZE /SSLOG /FULL

```

START version: 1.2 process: 0000042f                ! 5-JUN-2006
14:03:20.07
    username: SYSTEM                                node: XK150S
platform: ALPHA
    buffer count: 6    size: 65024    start_flags: 00000003

SYS$SETEXV                                          acmode: U                !
14:03:20.20
    sts: %SYSTEM-S-NORMAL, normal successful completion

    image:                PROCESS_MANAGEMENT_MON+00008f3c  argct:
04
    arg 1:0000000000000002  2:ffffffff818e8510  3:0000000000000000
    arg 4:0000000000000000
    entry number: 00000002    number at completion: 00000002
    cpu id: 000    kernel thread ID: 0000    Pthread ID:
0
[...]
SYS$GETDVI                                          acmode: U                !
14:03:20.28
    sts: %SYSTEM-S-NORMAL, normal successful completion

    image:                SYSTEM_PRIMITIVES+00054dec  argct:
08
    arg 1:0000000000000000  2:0000000000000000  3:000000000004000c
    arg 4:000000007ae59e10  5:000000007ae59e08  6:0000000000000000
    arg 7:0000000000000000  8:0000000000000000
    entry number: 00000193    number at completion: 00000193
    cpu id: 000    kernel thread ID: 0000    Pthread ID:
1

MOUNTSHR                                          :00010000    acmode: U                !
14:03:20.28
    sts: %SYSTEM-S-NORMAL, normal successful completion

    image:                MOUNTSHR+0009008c  argct:
02
    arg 1:0000000000000003  2:0000000000000000
    entry number: 00000194    number at completion: 00000195

```

```

    cpu id:   000   kernel thread ID:  0000   Pthread ID:
1
SYS$$SETPRT                                acmode: E                                !
14:03:20.28
    sts: %SYSTEM-S-NORMAL, normal successful completion

    image:                                MOUNTSHR+00091d94   argct:
05
    arg  1:000000007ff8bf88  2:0000000000000000  3:0000000000000000
    arg  4:0000000000000004  5:0000000000000000
    entry number: 00000195   number at completion: 00000195
    cpu id:   000   kernel thread ID:  0000   Pthread ID:
1
SYS$$SETSPM                                acmode: U                                !
14:03:20.28
    sts: %SYSTEM-S-NORMAL, normal successful completion

    image:                                MOUNTSHR+000900a8   argct:
01
    arg  1:0000000000000000
    entry number: 00000196   number at completion: 00000196
    cpu id:   000   kernel thread ID:  0000   Pthread ID:
1
MOUNTSHR                                :00010000   acmode: U                                !
14:03:20.28
    sts: %SYSTEM-S-NORMAL, normal successful completion

    image:                                MOUNTSHR+000901ac   argct:
02
    arg  1:0000000000000001  2:000000007ae5a080
    entry number: 00000197   number at completion: 0000019B
    cpu id:   000   kernel thread ID:  0000   Pthread ID:
1
[...]
```

The above example shows full SSLOG output.

In the /FULL display, the START entry also shows the flags with which logging was initiated:

- Bit 0, when set, means that service arguments were logged.
- Bit 1, which is always set, means that the P2 space buffers are being written to a file.

The /FULL display shows the arguments for each system service request, as well as its entry number, and interprets the completion status. The display includes kernel thread and POSIX thread identifiers in addition to the identifier of the CPU on which the system service began.

The system service name is not available for services implemented in privileged shareable images. Instead the image name and an internally generated service number are displayed.

When logging is initiated for a particular service, an entry sequence number is associated with that entry. The sequence number is incremented with each attempt to log a system service. The /FULL display shows the sequence number associated with each service request and the number current at

the time the service completed. If the service requests no other loggable system services, the two numbers are identical; otherwise, the two numbers differ.

Note that the number at completion is 0 for a service whose completion status could not be logged.

In this example, the number when the second MOUNTSHR system service request is issued is 19716, and the number at completion is 19B16. From this you can infer that four other services were requested as part of processing MOUNTSHR system service request, namely, the services whose entry numbers are 19816 through 19B16.

3. \$ ANALYZE /SSLOG /BRIEF /WIDE

```

START  1.2      0000042e  XK150S  ::USER                ALPHA  2 65024  ! 5-
JUN-2006 10:52:51.95
service                status      mode imagename+offset
-----
time
-----

SYS$SETEXV            00000001  U
  PROCESS_MANAGEMENT_MON+00008f3c  !10:52:52.06
SYS$SETPRT            00000001  U
  PROCESS_MANAGEMENT_MON+0005274c  !10:52:52.06
SYS$SETPRT            00000024  U
  PROCESS_MANAGEMENT_MON+0005274c  !10:52:52.06
SYS$SETPRT            00000024  U
  PROCESS_MANAGEMENT_MON+0005274c  !10:52:52.06
SYS$IMGACT            00000001  U
  IMAGE_MANAGEMENT+000163b8      !10:52:52.06
SYS$CMKRNL            00000001  U
  LOGINOUT+00030174      !10:52:52.06
SYS$GETJPI            00000001  U
  PROCESS_MANAGEMENT_MON+000527e4  !10:52:52.06
SYS$GETDVI            00000001  U
  SYSTEM_PRIMITIVES+00054dec    !10:52:52.06
SYS$SETPRV            00000001  U
  LOGINOUT+0003323c      !10:52:52.06
SYS$SETPRV            00000001  U
  LOGINOUT+00033278      !10:52:52.06
SYS$PERSONA_EXPORT_ARB 00000001  K
  PROCESS_MANAGEMENT_MON+0004e9e8  !10:52:52.06
SYS$TRNLNM            000001bc  U
  LOGINOUT+000365f8      !10:52:52.06
SYS$SETPRV            00000001  U
  LOGINOUT+00030a08      !10:52:52.06
[...]
SYS$ASSIGN_LOCAL      00000154  E
  IO_ROUTINES_MON+0001a544    !10:52:52.14
SYS$CMKRNL            8180e100  E
  MOUNTSHR+000964a8      !10:52:52.14
missing entry numbers: curr:1082 prev: 721

SYS$SYNCH_INT        -----  S
  PROCESS_MANAGEMENT_MON+00035634  !10:52:52.15
SYS$SYNCH_INT        -----  S
  PROCESS_MANAGEMENT_MON+00035634  !10:52:52.15
SYS$RMS_FLUSH        00018001  S
  RMS+00056808          !10:53:52.10

```

```

SYS$QIO                                00000001  E
RMS+000742bc      !10:53:52.10
[...]
```

The above example shows abbreviated SSLOG output in a wide format.

Sometimes system services are requested too quickly for logging to keep up. When a buffer fills, it is written asynchronously to the log file. If there are only two buffers, as in this example, the second can fill while the first is still being written and thus not yet available. In that case, entries are lost.

Because each attempt to log a service request has an entry number associated with it, the ANALYZE/SSLOG utility can detect gaps in entry numbers. In this example, the line that begins "missing entry numbers" indicates a gap of 361 entries.

4. \$ ANALYZE /SSLOG /NORMAL

```

START version: 1.1 process: 00000414 HERE          !25-MAY-2004
14:55:17.77
      username: SYSTEM                          node: NAK
platform: IA64

      buffer count: 4      size: 65024      start_flags: 00000003
SYS$EXIT_INT                                sts: ----- acmode: U  !
14:55:17.80
      image:                                IMAGE_MANAGEMENT+00047ed0  argct:
01
      arg 1:0000000010000001
      entry number: 00000002      number at completion: 00000000

SYS$RMSRUNDOWN                                sts: 00010001 acmode: S  !
14:55:17.80
      image:                                DCL+00070370  argct:
02
      arg 1:000000007ffabf14  2:0000000000000000
      entry number: 00000003      number at completion: 00000008

SYS$DCLAST                                    sts: 00000001 acmode: E  !
14:55:17.80
      image:                                RMS+000e5840  argct:
03
      arg 1:ffffffff832f70b0  2:0000000000000002  3:0000000000000000
      entry number: 00000004      number at completion: 00000004

SYS$RMS_CLOSE                                sts: 00010001 acmode: E  !
14:55:17.80
      image:                                RMS+000d66c0  argct:
03
      arg 1:000000007ff67e20  2:0000000000000000  3:0000000000000000
      entry number: 00000005      number at completion: 00000006

SYS$SETEF                                     sts: 00000009 acmode: E  !
14:55:17.80
      image:                                RMS+00125df0  argct:
01
      arg 1:0000000000000001e
      entry number: 00000006      number at completion: 00000006
```

```

SYS$RMS_CLOSE                sts: 00010001  acmode: E   !
14:55:17.80
    image:                    RMS+000d66c0  argct:
03
    arg 1:000000007ff67e20  2:0000000000000000  3:0000000000000000
    entry number: 00000007    number at completion: 00000008

```

[...]

The above example shows normal SSLOG output in narrow format.

The difference between the /NORMAL and /FULL displays is that the service completion status is interpreted in a /FULL display.

5. \$ ANALYZE /SSLOG /WIDE

```

START  version: 1.1 process: 20200224 HERE2 !28-APR-2004 14:17:58.54
      username: USER                node: NODEAZ platform:
      ALPHA

```

```

SYS$EXIT_INT                 sts: -----  acmode: U  image:
  IMAGE_MANAGEMENT+00010838    !14:17:58.82
argct:01  1:0000000010000001

```

```

SYS$RMSRUNDOWN              sts: 00010001  acmode: S  image:
  DCL.EXE+000804b0           !14:17:58.82
argct:02  1:000000007ff9cb34  2:0000000000000000

```

```

SYS$DCLAST                  sts: 00000001  acmode: E  image:  RMS
+0004e200                    !14:17:58.82
argct:03  1:00000000811338b0  2:0000000000000002  3:0000000000000000

```

```

SYS$RMS_CLOSE              sts: 00010001  acmode: E  image:  RMS
+000484b8                    !14:17:58.82
argct:03  1:000000007ff8beb0  2:0000000000000000  3:0000000000000000

```

```

SYS$SETEF                   sts: 00000009  acmode: E  image:  RMS
+0005fe70                    !14:17:58.82
argct:01  1:0000000000000001e

```

```

SYS$RMS_CLOSE              sts: 00010001  acmode: E  image:  RMS
+000484b8                    !14:17:58.82
argct:03  1:000000007ff8beb0  2:0000000000000000  3:0000000000000000

```

```

SYS$SETEF                   sts: 00000009  acmode: E  image:  RMS
+0005fe70                    !14:17:58.82
argct:01  1:0000000000000001e

```

[...]

The above example shows normal (default) SSLOG output in a wide format.

6. \$ ANALYZE /SSLOG /WIDE /FULL

```

START version: 1.1 process: 00000415 HERE !11-
MAY-2006 10:41:38.82
      username: SYSTEM                      node: NAK
      platform: IA64

SYS$EXIT_INT          sts: -----  acmode: U  image:
IMAGE_MANAGEMENT+00047600 !10:41:38.85
argct:01 1:0000000010000001          entry number: 00000002      number at
completion: 00000000
      cpu id: 000  kernel thread ID: 0000  Pthread ID:
0

SYS$RMSRUNDWN          acmode: S  image:          DCL
+0006fdb0              !10:41:38.85
      sts: %RMS-S-NORMAL, normal successful completion
argct:02 1:000000007ffabf14 2:0000000000000000
      entry number: 00000003      number at completion: 00000008
      cpu id: 000  kernel thread ID: 0000  Pthread ID:
0

SYS$DCLAST            acmode: E  image:          RMS
+000e3ca0              !10:41:38.85
      sts: %SYSTEM-S-NORMAL, normal successful completion
argct:03 1:ffffffff842f68b0 2:0000000000000002 3:0000000000000000
      entry number: 00000004      number at completion: 00000004
      cpu id: 000  kernel thread ID: 0000  Pthread ID:
0

SYS$RMS_CLOSE          acmode: E  image:          RMS
+000d4d90              !10:41:38.85
      sts: %RMS-S-NORMAL, normal successful completion
argct:03 1:000000007ff67e20 2:0000000000000000 3:0000000000000000
      entry number: 00000005      number at completion: 00000006
      cpu id: 000  kernel thread ID: 0000  Pthread ID:
0

SYS$SETEF             acmode: E  image:          RMS
+00123740              !10:41:38.85
      sts: %SYSTEM-S-ACCVIO, access violation, reason mask=!XB, virtual
      address=!XH, PC=!XH, PS=!XL
argct:01 1:0000000000000001e
      entry number: 00000006      number at completion: 00000006
      cpu id: 000  kernel thread ID: 0000  Pthread ID:
0

SYS$RMS_CLOSE          acmode: E  image:          RMS
+000d4d90              !10:41:38.85
      sts: %RMS-S-NORMAL, normal successful completion
argct:03 1:000000007ff67e20 2:0000000000000000 3:0000000000000000
      entry number: 00000007      number at completion: 00000008
      cpu id: 000  kernel thread ID: 0000  Pthread ID:
0

```

)

The above example shows full SSLOG output in a wide format.

```
7. $ ANALYZE /SSLOG /WIDE /SELECT=(IMAGE=DCL,SYSSER=SYS$IMGACT)-
_$ /OUTPUT=SSL_SEL2.LOG SSLOG.DAT

START version: 1.1 process: 2020041b SYSTEM
      !30-AUG-2004 18:30:28.79
      username: SYSTEM node: WFGLX4
      platform: ALPHA

SYS$IMGACT sts: 00000001 acmode: S image:
      DCL+0007eb40 !18:30:44.26
argct:08 1:000000007ff9cd58 2:000000007ff9cd50 3:000000007ffcf800
      4:0000000000000000
      5:0000000000000000 6:0000000000000000 7:0000000000000000
      8:0000000000000000
      entry number: 0000002E number at completion: 000000B7

SYS$IMGACT sts: 00000001 acmode: S image:
      DCL+0007eb40 !18:30:49.81
argct:08 1:000000007ff9cd58 2:000000007ff9cd50 3:000000007ffcf800
      4:0000000000000000
      5:0000000000000000 6:0000000000000000 7:0000000000000000
      8:0000000000000000
      entry number: 00000195 number at completion: 00000203

SYS$IMGACT sts: 00000001 acmode: S image:
      DCL+0007eb40 !18:31:06.19
argct:08 1:000000007ff9cd58 2:000000007ff9cd50 3:000000007ffcf800
      4:0000000000000000
      5:0000000000000000 6:0000000000000000 7:0000000000000000
      8:0000000000000000
      entry number: 000003FB number at completion: 0000046A

STOP
      !30-AUG-2004 18:31:06.19
```

The above example selects only those entries that describe SYS\$IMGACT requests made from DCL and writes the analysis to file SSL_SEL2.LOG. (Parts of the display have been moved left to fit within manual page boundaries.)

```
8. $ ANALYZE /SSLOG /STATISTICS /OUTPUT=SSL_STAT.LOG SSLOG.DAT

START version: 1.1 process: 2020041b SYSTEM !30-AUG-2004
      18:30:28.79
      username: SYSTEM node: WFGLX4
      platform: ALPHA

      buffer count: 2 size: 65024 start_flags: 00000003

Service Count User Super
Exec Kernel Rate/sec -----
-----
SYS$TRNLNM 168 4 0
164 0 4.5
```

SYS\$RMS_SEARCH			129	129	0
0	0	3.4			
SYS\$QIO			121	0	0
94	27	3.2			
SYS\$SYNCH_INT			92	88	4
0	0	2.5			
SYS\$RMS_PUT			85	85	0
0	0	2.3			
SYS\$CMKRNL			55	0	0
55	0	1.5			
SYS\$SETPRT			51	36	0
15	0	1.4			
SYS\$DASSGN			49	0	0
24	25	1.3			
SYS\$GETDVI			46	2	0
44	0	1.2			
SYS\$ASSIGN_LOCAL			44	0	0
44	0	1.2			
SYS\$MGBLSC			40	0	0
40	0	1.1			
SYS\$CRMPSC			27	0	0
27	0	0.7			
SYS\$GETJPI			22	22	0
0	0	0.6			
SYS\$RMS_OPEN			21	0	0
21	0	0.6			
SYS\$DEQ			19	0	0
8	11	0.5			
SYS\$IMGACT			18	15	3
0	0	0.5			
SYS\$CRETVA			16	0	0
16	0	0.4			
SYS\$ENQ			15	0	0
8	7	0.4			
SYS\$SETRWM			12	0	0
6	6	0.3			
SYS\$DELTVA			12	0	0
0	12	0.3			
SYS\$PERSONA_ASSUME			12	0	0
12	0	0.3			
SYS\$EXPREG			12	9	0
3	0	0.3			
SYS\$RMS_CLOSE			7	1	0
6	0	0.2			
SYS\$CLRCLUEVT			6	0	0
0	6	0.2			
SYS\$SETEF			6	0	0
6	0	0.2			
SYS\$DACEFC			6	0	0
0	6	0.2			
SYS\$PERSONA_EXTENSION_LOOKUP			6	0	0
0	6	0.2			
SYS\$GETSYI			5	5	0
0	0	0.1			
SYS\$DCLAST			5	0	0
5	0	0.1			
SYS\$RMSRUNDWN			3	0	3
0	0	0.1			

SYS\$ERNDWN			3	0	3
0	0	0.1			
SYS\$SETEXV			3	3	0
0	0	0.1			
SYS\$KRNDWN			3	0	3
0	0	0.1			
SYS\$EXIT_INT			3	3	0
0	0	0.1			
SYS\$RMS_GET			3	0	3
0	0	0.1			
SYS\$DCLEXH			3	0	3
0	0	0.1			
SYS\$PERSONA_EXPORT_ARB			3	0	0
0	3	0.1			
SYS\$DALLOC			3	0	0
0	3	0.1			
SYS\$SETPFM			3	0	0
0	3	0.1			
SYS\$PERSONA_CLONE			2	0	0
2	0	0.1			
SYS\$PERSONA_DELETE			2	0	0
2	0	0.1			
SYS\$RMS_CREATE			2	2	0
0	0	0.1			
SYS\$RMS_CONNECT			2	2	0
0	0	0.1			
SYS\$SET_PROCESS_PROPERTIESW			1	1	0
0	0	0.0			
SYS\$RMS_PARSE			1	1	0
0	0	0.0			
SYS\$PROCESS_SCAN			1	1	0
0	0	0.0			
SYS\$SETPRV			1	1	0
0	0	0.0			

The above example shows the use of the /STATISTICS qualifier. The output lists the most frequently requested service first. Each entry shows the total number of requests for that service, a breakdown by access mode, and the rate per second.

Note that only OpenVMS executive services are listed in a /STATISTICS display; services in privileged shareable images are omitted.

9. \$ ANALYZE /SSLOG /STATISTICS=BY_STATUS

```
START version: 1.1 process: 2020041b SYSTEM !30-AUG-2004
18:30:28.79
username: SYSTEM node: WFGLX4
platform: ALPHA
```

```
buffer count: 2 size: 65024 start_flags: 00000003
```

Service	Kernel	Status	Count	User	Super
Exec			Rate/sec		
-----	-----	-----	-----	-----	-----
SYS\$TRNLNM			168	4	0
164	0	All	4.5		

				46	0	0
46	0	000001BC	1.2	122	4	0
118	0	00000001	3.3	129	129	0
SYS\$RMS_SEARCH						
0	0	All	3.4	2	2	0
0	0	00018001	0.1	126	126	0
0	0	00010001	3.4	1	1	0
0	0	000182CA	0.0	121	0	0
SYS\$QIO						
94	27	All	3.2	4	0	0
0	4	0000026C	0.1	117	0	0
94	23	00000001	3.1	92	88	4
SYS\$SYNCH_INT						
0	0	All	2.5	92	88	4
0	0	00000000	2.5	85	85	0
SYS\$RMS_PUT						
0	0	All	2.3	84	84	0
0	0	00018001	2.2	1	1	0
0	0	00000000	0.0			
[...]						

The above example shows the use of `/STATISTICS = BY_STATUS`. Similar to the previous example, it also has an additional line for each status returned by a system service.

RUN/SSLOG_ENABLE

Creates a process with system service logging enabled.

Requires CMEXEC, CMKRNL, or SETPRV privilege to log argument values. The SYSGEN parameter SYSSER_LOGGING must be enabled or the command will fail.

Refer to online help or the *VSI OpenVMS DCL Dictionary* for other qualifiers that can be used with the RUN command when creating a process.

Format

```
RUN /SSLOG_ENABLE[=(COUNT=n [,FLAGS=[NO]ARG])]
```

Parameters

COUNT=n

Specifies how many P2-space buffers to log. The default is 2.

FLAGS=[NO]ARG

Specifies whether or not service argument values are to be logged. The default is ARG, which requires privileges. If the value is ARG but you lack privilege, no argument values are logged.

If both **COUNT** and **FLAGS** are specified, they must be separated by a comma. If only one is specified, the parentheses may be omitted.

Qualifiers

None.

Description

The `RUN/SSLOG_ENABLE` command creates a process with system service logging enabled.

When enabling SSLOG for a process, you can specify the number of buffers to be used for logging. Buffers are allocated in P2 space and are charged against the process's paging file quota. Each buffer is 65,02410 bytes or FE0016 bytes. The buffer space remains allocated and the quota charged until the process is deleted.

Before you delete the process, stop the logging and close the log file by executing the `SET PROCESS/SSLOG=STATE=UNLOAD` command. The log file does not close automatically.

To analyze the log file, use the DCL command `ANALYZE/SSLOG`.

Examples

1. `$ RUN /SSLOG_ENABLE SSLOG_TEST.EXE`

This command creates a new process to run the image `SSLOG_TEST.EXE` and log the results.

2. `$ RUN /SSLOG_ENABLE SSLOG_TEST.EXE /PROCESS_NAME=SUBA`

This command creates a new process named `SUBA` to run the image `SSLOG_TEST.EXE` and log the results.

SET PROCESS/SSLOG

Enables or disables system service logging on the current process or on a specified process.

Requires GROUP privilege to change other processes in your group. Requires WORLD privilege to change processes outside your group. Requires CMEXEC, CMKRNL, or SETPRV privilege to log argument values. SYSGEN parameter SYSSER_LOGGING must be enabled or the command will fail.

Refer to online help or the *VSI OpenVMS DCL Dictionary* for other SET PROCESS command qualifiers.

Format

```
SET PROCESS/SSLOG=(STATE={ON|OFF|UNLOAD} [,COUNT=n] [,FLAGS=[NO]ARGUMENTS])
```

Parameters

process-name

Specifies the name of the process for which logging is to be enabled or disabled.

COUNT=*n*

Specifies how many P2-space buffers to log. The default is 2.

FLAGS=[NO]ARG

Specifies whether or not service argument values are to be logged. The default is ARG, which requires privileges. If the value is ARG but you lack privilege, no argument values are logged.

STATE=*state*

Turns system service logging on or off. Possible states are:

ON	Enables system service logging.
OFF	Disables (turns off) system service logging; logging can still be reenabled.
UNLOAD	Stops logging and closes the log file, which is named SSLOG.DAT by default.

Qualifiers

/IDENTIFICATION=*identification_number*

Specify to target a specific process by number.

Description

The SET PROCESS/SSLOG command:

- Enables or disables system service logging
- Opens the log file used to log data
- Can specify a specific process by name or ID (identification number)
- Can stop logging and close the file of logged data

When enabling SSLOG for a process, you specify the number of buffers to be used for logging. The buffers are allocated in P2 space and are charged against the process's paging file quota. Each buffer is 65,02410 bytes or FE0016 bytes. The buffer space remains allocated and the quota charged until the process is deleted.

Between the time when SSLOG is first enabled and when the log file is closed, logging can be stopped and resumed.

Before you delete the process, stop the logging and close the log file. The log file does not close automatically.

To analyze the log file, use the DCL command ANALYZE/SSLOG.

Examples

1. `$ SET PROCESS /SSLOG=(STATE=ON,COUNT=4)`

This command turns on system service logging with four P2 space buffers, each having a size of FE0016 bytes. If the process has SETPRV, CMKRNL, or CMEXEC privilege, argument values are logged.

2. \$ SET PROCESS /SSLOG=(STATE=UNLOAD)

This command stops logging and closes the log file.

